

CHARDONNAY ELEGANCE

STEP			ADDITION
Preparation of the base	The sparkling wine base must be clarified and protein stabilized. Possible acidity correction		Acids, clarifying agents (X-PRO bactoclean)
Filtration and loading	Filtration must be protected with nitrogen:		0,5 g/Hl PREMIUM STAB + 0,5 g/hl TI PREMIUM
PREPARATION OF PIED DE CUVE in a 5 hl tank	10 liters	Yeast Rehydration:	PREMIUM CHARDONNAY 1KG*
	20 liters	heat 8L water up to 50-60°C add 100 g sugar, wait until temperature goes to 30-35°C	
	25 liters	Add 5 l base wine and 10 g V ACTIVE PREMIUM®	mix for 1 hour letting air blend into the liquid
	40 liters	Add 15 l base wine And 15 g V ACTIVE PREMIUM®	Mix for 2 hours letting air blend into the liquid
	70 liters	Add 30 l base wine Add 30 g V ACTIVE PREMIUM®	Mix for 2 hours letting air blend into the liquid
	120 liters	Add 50 l base wine Add 50 g V ACTIVE PREMIUM®	Mix for 3 hours letting air blend into the liquid
	250 liters	Add 130 l base wine Add 100 g V ACTIVE PREMIUM®	Wait 14 hours
	The "pied de couve" is ready *for 50 hl of wine		
Sugar addition	Sugar additions should take into account potential alcohol, pressure and desired residual sugars.		
Additions to the wine	Tannins: protects from oxydation and provides fine tuning Nutrition: organic nutrition rich in amminoacids XPRO: better the foam and protects from oxidation		1 g/hl PREMIUM® LIMOUSINE 20-30 g/hl V STARTER FRUIT 5-10 g/hl XPRO FINESSE
Oxygenation	When the pressure has reached 0.5 bar, open the valve and oxygenate the entire mass with air or macro-ox at a dose of 8 ml/L in 6 hours.		
Second fermentation	Check the progress of the fermentation by both the increase in pressure and the decrease in sugar. Stir regularly		In case the fermentation slows down or develops undesired smells, is possible to add 20 g/hl BOOSTER ACTIVE PREMIUM.
Fermentation stop	Once the desired pressure and residual sugars are reached, lower the temperature. Consider a little clarification if necessary.		10 g/hl X-PRO Bactoclean: avoids bacterial fermentations and help the cleaning of the wine
Racking and fine lees	Evaluate the possible permanence of the yeast on the lees with mixing.		
Filtration	Before starting filtration add 10 g/HL of potassium bitartrate to promote tartaric precipitation in the fsecond tank. During filtration, add 10-11 g/HL of metabisulphite		10 g/HL of metabisulphite K 10 g/HL of bitartarate K
Final additions	Take the sample for analysis and final additions, determine the CO2 pressure in the tank and bring it close to 5.2 bar before bottling.		Final additions: tannins etc.. Ex: 0,5 g/hl SMARTAN ZEST

- XPRO® FINESSE supports the elegance, freshness and firmness of the perlage.
- V STARTER FRUIT® is composed of pure organic nitrogen and should be supplied to the yeast from the beginning.

ANALYTICS:

- At the beginning: Basic Oenochemistry + Protein Stabil. + Cu, Clarification
- During fermentation: A general control analysis, daily sugars and pressure
- Fermentation end: Copper, end of fermentation analysis, clarification and stability tests
- Before bottling: Complete wine analysis. Pressure