Parallel Computing - Notes - v0.6.0-dev

260236

October 2024

Preface

Every theory section in these notes has been taken from the sources:

- Validity of the single processor approach to achieving large scale computing capabilities. [1]
- Introduction to parallel algorithms, Carnegie Mellon University. [2]
- Course slides. [3]
- Reevaluating Amdahl's law. [4]
- OpenMP by Example, Johnston Hans. [5]
- Introduction to parallel computing, volume 110. [6]
- Structured Parallel Programming: Patterns for Efficient Computation. [7]
- Multithreading Architecture. [9]

About:

GitHub repository

These notes are an unofficial resource and shouldn't replace the course material or any other book on parallel computing. It is not made for commercial purposes. I've made the following notes to help me improve my knowledge and maybe it can be helpful for everyone.

As I have highlighted, a student should choose the teacher's material or a book on the topic. These notes can only be a helpful material.

Contents

1	\mathbf{PR}	AM 5						
	1.1	Prerequisites						
	1.2	Definition						
	1.3	How it works						
		1.3.1 Computation						
		1.3.2 PRAM Classificiation 6						
		1.3.3 Strengths of PRAM						
		1.3.4 How to compare PRAM models						
	1.4	MVM algorithm						
	1.5	SPMD sum						
	1.6	MM algorithm						
	1.7	PRAM variants and Lemmas						
	1.8	PRAM implementation						
	1.9	Amdahl's and Gustafson's Laws						
2	Fun	damentals of architecture 22						
	2.1	Introduction						
		2.1.1 Simplest processor						
		2.1.2 Superscalar processor						
		2.1.3 Single Instruction, Multiple Data (SIMD) processor 24						
		2.1.4 Multi-Core Processor						
	2.2	Accessing Memory						
		2.2.1 What is a memory?						
		2.2.2 How to reduce processor stalls						
		2.2.2.1 Cache						
		2.2.2.2 Multi-threading						
3	\mathbf{Pro}	gramming models 30						
	3.1	Implicit SPMD Program Compiler (ISPC)						
	3.2	Shared Address Space Model						
,	D	allel Programming Models and pthreads 35						
4	4.1	allel Programming Models and pthreads How to create parallel algorithms and programs						
	4.1 4.2							
	4.2	v 1						
	$\frac{4.3}{4.4}$	Technologies						
	4.4	4.4.1 Flynn's taxonomy						
		4.4.3.1 Creation						
		4.4.3.2 Termination						
		4.4.3.3 Joining						
		4.4.3.4 Detaching						
		4.4.3.5 Joining through Barriers						
		4.4.3.6 Mutexes						
		/L/L3 / Condition variables 50						

syntax 53 sharing 56 For 56 Sections 61 Single/Master 62 Tasks 63	5 Open	$\mathrm{MP} \ \mathrm{v5.2}$	51
sharing 56 For 56 Sections 61 Single/Master 62 Tasks 63	5.1 Ir	ntroduction	51
For	5.2 B	Basic syntax	53
Sections 61 Single/Master 62 Tasks 63	5.3 V	Vork sharing	56
Single/Master 62 Tasks 63	5.	.3.1 For	56
Tasks	5.	.3.2 Sections	61
	5.	.3.3 Single/Master	62
70	5.	.3.4 Tasks	63
70	$5.4 ext{ S}$	ynchronization	66
70	. .		
	Index		70

1 PRAM

1.1 Prerequisites

Before we introduce the PRAM model, we need to cover some useful topics.

- A Machine Model describes a "machine". It gives a value to the operations on the machine. It is necessary because: it makes it easy to deal with algorithms; it achieves complexity bounds; it analyses maximum parallelism.
- A Random Access Machine (RAM) is a model of computation that describes an abstract machine in the general class of register machines. Some features are:
 - Unbounded number of local memory cells;
 - Each memory cell can hold an integer of **unbounded** size;
 - Instruction set includes simple operations, data operations, comparator, branches;
 - All operations take unit time;
 - The definition of time complexity is the number of instructions executed:
 - The definition of space complexity is the number of memory cells used.

1.2 Definition

Definition 1: PRAM

A parallel random-access machine (parallel RAM or PRAM) is a shared-memory abstract machine. As its name indicates, the PRAM is intended as the parallel-computing analogy to the random-access machine (RAM) (not to be confused with random-access memory). In the same way that the RAM is used by sequential-algorithm designers to model algorithmic performance (such as time complexity), the PRAM is used by parallel-algorithm designers to model parallel algorithmic performance (such as time complexity, where the number of processors assumed is typically also stated).

The PRAM model has many interesting features:

- Unbounded collection of RAM processors $(P_0, P_1, \text{ and so on})$;
- Processors don't have tape;
- Each processor has unbounded registers;
- Unbounded collection of share memory cells;
- All processors can access all memory cells in unit time;
- All communication via shared memory.

1 PRAM 1.3 How it works

1.3 How it works

1.3.1 Computation

A single **processor** of the PRAM, at each computation, is **composed of 5 phases** (carried out in parallel by all the processors):

- 1. Reads a value from one of the cells $X\left(1\right),\ldots,X\left(N\right)$
- 2. Reads one of the shared memory cells $A(1), A(2), \ldots$
- 3. Performs some internal computation
- 4. May write into one of the output cells $Y(1), Y(2), \ldots$
- 5. May write into one of the shared memory cells $A(1), A(2), \ldots$

1.3.2 PRAM Classificiation

During execution, a subset of processors may remain idle. Also, some processors can read from the same cell at the same time (not really a problem), but they could also try to write to the same cell at the same time (**write conflict**). For these reasons, PRAMs are classified according to their read/write capabilities (realistic and useful):

- Exclusive Read (ER). All processors can simultaneously read from distinct memory locations.
- Exclusive Write (EW). All processors can simultaneously write to distinct memory locations.
- Concurrent Read (CR). All processors can simultaneously read from any memory location.
- Concurrent Write (CW). All processors can write to any memory location.

? But what value is ultimately written?

It depends on the mode we choose:

- Priority Concurrent Write. Processors have priority based on which value is decided, the highest priority is allowed to complete write.
- Common Concurrent Write. All processors are allowed to complete write if and only if all the value to be written are equal. Any algorithm for this model has to make sure that this condition is satisfied. Otherwise, the algorithm is illegal and the machine state will be undefined.
- Arbitrary/Random Concurrent Write. One randomly chosen processor is allowed to complete write.

1 PRAM 1.3 How it works

1.3.3 Strengths of PRAM

PRAM is attractive and important model for designers of parallel algorithms because:

- It is **natural**. The number of operations executed per one cycle on P processors is at most P (equal to P is the ideal case).
- It is strong. Any processor can read/write any shared memory cell in unit time.
- It is simple. It abstracts from any communication or synchronization overhead, which makes the complexity and correctness of PRAM algorithm easier.
- It can be used as a **benchmark**. If a problem has no feasible/efficient solution on PRAM, it has no feasible/efficient solution for any parallel machine.

1.3.4 How to compare PRAM models

Consider two generic PRAMs, models A and B. Model A is **computationally stronger** than model B ($A \ge B$) **if and only if any algorithm** written for model B will **run unchanged** on model A in the **same parallel time** and with the **same basic properties**.

However, there are some useful metrics that can be used to compare models:

• Time to solve problem of input size n on <u>one</u> processor, using best sequential algorithm:

$$T^*\left(n\right) \tag{1}$$

• Time to solve problem of input size *n* on **p processors**:

$$T_{p}\left(n\right)$$
 (2)

• Speedup on p processors:

$$SU_{p}(n) = \frac{T^{*}(n)}{T_{p}(n)}$$
(3)

• **Efficiency**, which is the work done by a processor to solve a problem of input size *n* divided by the work done by *p* processors:

$$E_{p}(n) = \frac{T_{1}(n)}{pT_{p}(n)}$$

$$\tag{4}$$

• Shortest run time on any process p:

$$T_{\infty}\left(n\right)$$
 (5)

1 PRAM 1.3 How it works

• Cost, equal to processors and time:

$$C(n) = P(n) \cdot T(n) \tag{6}$$

• Work, equal to the total number of operations:

$$W\left(n\right) \tag{7}$$

Some properties on the metrics:

• The time to solve a problem of input n on a single processor using the best sequential algorithm is not equal to the time to solve a problem of input n in parallel using one of the p processors available. In other words, the problem should not be solvable on a single processor on a parallel machine (otherwise, what would be the point of using a parallel model?)

$$T^* \neq T_1$$

- $SU_P \le P$
- $SU_P \le \frac{T_1}{T_{\infty}}$
- $E_p \leq 1$
- $T_1 \ge T^* \ge T_p \ge T_\infty$
- $T^* \approx T_1 \Rightarrow E_p \approx \frac{T^*}{pT_p} = \frac{\mathrm{SU}_p}{p}$
- $E_p = \frac{T_1}{pT_p} \le \frac{T_1}{pT_\infty}$
- $T_1 \in O(C), T_p \in O\left(\frac{C}{p}\right)$
- $\bullet \ W \leq C$
- $p \approx \text{AREA}$ $W \approx \text{ENERGY}$ $\frac{W}{T_p} \approx \text{POWER}$

1.4 MVM algorithm

The Matrix-Vector Multiply (MVM) algorithm consists of four steps:

- 1. Concurrent read of vector X(1:n) (transfer N elements);
- 2. Simultaneous reads of different sections of the general matrix A (transfer $\frac{n^2}{p}$ elements to each processor);
- 3. Compute $\frac{n^2}{p}$ operations per processor;
- 4. Simultaneous writes (transfer $\frac{n}{p}$ elements from each processor).

Let i be the processor index, so the MVM algorithm is simply written as:

```
GLOBAL READ (Z \leftarrow X)

GLOBAL READ (B \leftarrow A_i)

COMPUTE (W := BZ)

GLOBAL WRITE (W \rightarrow y_i)
```

Algorithm 1: Matrix-Vector Multiply (MVM)




Figure 1: Example of MVM algorithm.

The performance of the MVM algorithm is as follows:

• The **time to solve** a problem of size n^2 is equal to the big O of the squared size of the problem as input divided by the number of processors available:

$$T_p\left(n^2\right) = O\left(\frac{n^2}{p}\right)$$

• The **cost** is equal to the number of processors and the time it takes to solve the problem. So it is quite trivial:

$$C = O\left(\cancel{p} \cdot \frac{n^2}{\cancel{p}} \right) = O\left(n^2\right)$$

• The **work** is equal to the cost, and the **linear power** P is equal to the ratio of work and time to solve the problem on p processors:

$$W = C \qquad \frac{W}{T_p} = P$$

• The **perfect efficiency** is equal to:

$$E_p = \frac{T_1}{pT_p} = \frac{n^2}{p\frac{n^2}{p}} = 1$$

1.5 SPMD sum

The Single Program Multiple Data (SPMD) is a term that has been used to describe computational models for exploiting parallelism, where multiple processors work together to execute a program to get results faster.

In this section, we will see an SPMD approach on a Parallel Random Access Machine (PRAM). We will introduce one of the most common and simple mathematical operations: the sum.

The following pseudocode takes as **input an array** of size $n = 2^k$. In this case, n is a power of 2 because it ensures that the array can be evenly divided at each step of the computation. The value k is the number of iterations or levels of the summation process.

```
GLOBAL READ (A \leftarrow A(I))
2
        GLOBAL WRITE (A 
ightarrow B(I))
3
        FOR H = 1 : K
             IF i \leq n \div 2^h THEN BEGIN
                   GLOBAL READ (X \leftarrow B(2i -
                   GLOBAL READ (Y \leftarrow B(2i))
                   Z := X + Y
                   GLOBAL WRITE (Z \rightarrow B(i))
9
              END
        IF I = 1 THEN
11
              GLOBAL WRITE (Z \rightarrow S)
12
13 END
```

Algorithm 2: Single Program Multiple Data (SPMD) sum

- First, read the entire input array A and copy the read data to another array B.
- Loop over h (1 to k). In each iteration, for each index i less than or equal to $n \div 2^h$, read values from array B at positions 2i 1 and 2i; sum these values (and store the result in Z) and store the result (Z) back into B(i).
- Once all iterations are complete, the final sum is stored in a variable S.

For example, if n = 8, then k would be 3, meaning that the algorithm will run for 3 iterations to sum all the elements in parallel.

\overline{h}	i	adding
	1	1,2
1	2	3,4
1	3	5,6
	4	7,8
2	1	1,2
2	2	3,4
3	1	1,2




Figure 2: Computation of the sum of eight elements on a PRAM with eight processors. Each internal node represents a sum operation. The specific processor executing the operation is indicated below each node.


Performance of sum

When the size of the array is equal to the number of processors (N = P), the speedup and efficiency decrease:

- $\bullet \ T^*\left(N\right) = T_1\left(N\right) = N$
- $\bullet \ T_{N=P}(N) = 2 + \log N$
- $SU_P = \frac{N}{2 + \log N}$
- $T^*(N) = P \cdot (2 + \log N) \approx N \log N$

$$\bullet \ E_p = \frac{T_1}{pT_p} = \frac{N}{N\log N} = \frac{1}{\log N}$$





If the size of the array is much larger than the number of processors $(N \gg P)$, the speedup and power are linear, the cost is fixed and the efficiency is maximum (equal to 1):

•
$$T^*(N) = T_1(N) = N$$


•
$$T_p(N) = \frac{N}{p} + \log p$$

•
$$SU_P = \frac{N}{\frac{N}{p} + \log p} \approx P$$

• COST =
$$p\left(\frac{N}{p} + \log p\right) \approx N$$

• WORK =
$$N + P \approx N$$

•
$$E_p = \frac{T_1}{pT_p} = \frac{N}{p\left(\frac{N}{p} + \log p\right)} \approx 1$$



n = 1'000'000

Example 1

Refer to Figure 2 (page 12), the performance metrics are:

- $T_8 = 5$
- $C = 8 \cdot 5 = 40$ (could do 40 steps)
- W = 2n = 16 (16 on 40, wasted 24)
- $E_p = \frac{2}{\log n} = \frac{2}{3} = 0.67$
- $\frac{W}{C} = \frac{16}{40} = 0.4$

There is also the **Prefix Sum**, which takes **advantage of idle processors in the sum**. It computes all prefix sums:

$$S_i = \sum_{1}^{i} a_j$$
 a_1 , $a_1 + a_2$, $a_1 + a_2 + a_3$




Figure 4: Prefix sum.

1.6 MM algorithm

The Matrix Multiply (MM) algorithm consists of three steps:

- 1. Compute the two matrices $A_{i,l}$ and $B_{l,j}$, so use the concurrent read.
- 2. Make the **sum**.
- 3. **Store** the result using exclusive write.


Algorithm 3: Matrix Multiply (MM)

Performance of MM

- $T_1 = n^3$
- $T_{p=n^3} = \log n$

•
$$SU = \frac{n^3}{\log n}$$

- $Cost = n^3 \log n$
- $\bullet \ E_p = \frac{T_1}{pT_p} = \frac{1}{\log n}$



1.7 PRAM variants and Lemmas

The PRAM model presented here is one of the most commonly used. However, there are other important variants:

- PRAM model with a **limited number of shared memory cells** (small memory PRAM). If the input data set exceeds the capacity of the shared memory, the I/O values can be evenly distributed among the processors.
- PRAM model with **limited number of processors** (small PRAM). If the number of execution threads is higher, processors can interleave multiple threads.
- PRAM model with **limited size of one machine word**.
- PRAM model with access conflicts handling. These are restrictions on simultaneous access to shared memory cells.

Lemma 1. Assume P' < P and same size of shared memory. Any problem that can be solved for a P processor PRAM in T steps can be solved in a P' processor PRAM in:

$$T' = O\left(\frac{TP}{P'}\right) \tag{8}$$

Proof. Partition P is simulated processors into P' groups of size $\frac{P}{P'}$ each. Associate each of the P' simulating processors with one of these groups. Each of the simulating processors simulates one step of its group of processors by:

- Executing all their read and local computation substeps first;
- Executing their write substeps then.

QED

Lemma 2. Assume M' < M. Any problem that can be solved for a P processor and M-cell PRAM in T steps can be solved on a $\max(P, M')$ -processors M'-cell PRAM in $O\left(\frac{TM}{M'}\right)$ steps.

Proof. Partition M simulated shared memory cells into M' continuous segments S, of size $\frac{M}{M'}$ each. Each simulating processor P_I' ($1 \le I \le P$), will simulate processor P_I of the original PRAM. Each simulating processor P_I' ($1 \le I \le M'$), stores the initial contents of S_I into its local memory and will use M'[I] as an auxiliary memory cell for simulation of accesses to cell of S_I . Simulation of one original read operation:

```
EACH P_I' (I=1,\ldots,\max(P,M')) REPEATS FOR K = 1, ..., \frac{M}{M'} WRITE THE VALUE OF THE K-TH CELL OF S_I INTO M'[I] (I=1,\ldots,M') READ THE VALUE WHICH THE SIMULATED PROCESSOR P_I (I=1,\ldots,P) WOULD READ IN THIS SIMULATED SUBSTEP, IF IT APPEARED IN THE SHARED MEMORY
```

The local computation substep of P_I $(I=1,\ldots,P)$ is simulated in one step by P_I' . SImulation of one original write operation is analogous to that of read. QED

1.8 PRAM implementation

The PRAM is an ideal model for creating parallel algorithms. Now we look at "is it really implementable?" The short answer is yes.

The longest answer is the following. There are already some examples of PRAM being converted to real machine models, such as Explicit Multi-Threading (XMT), Rigel, Tilera, etc. If conversion is not easy or possible, the implementation can be "direct":

- The concurrent read is implemented as a detect-and-multicast technique.
- The concurrent write is implemented depending on the end result we want to achieve. Fetch-and-operate and prefix-sum are examples of serialized writing; otherwise, the CRCW technique is used:

 $-\,$ Common CRCW: detect and merge

- Priority CRCW: detect-and-priorities

- Arbitrary CRCW: arbitrary

Example 2: Boolean DNF (sum of products) common CRCW

A logical formula is considered to be in DNF if it is a disjunction of one or more conjunctions of one or more literals.

Consider X as the sum of products of AND/OR operations:

$$X = a_1b_1 + a_2b_2 + \dots$$

The PRAM code, with X initialized to 0 and task index equal to \$, is:

if
$$(a_{\$}b_{\$})$$
 X = 1;

The common result is that not all processors write X and those that do write 1. The time complexity is O(1). It works on common, priority and arbitrary CRCW.

Despite the previous example, exists also the PRAM SoP for the concurrent write. Let boolean X as:

$$X = a_1b_1 + a_2b_2 + \dots$$

The PRAM algorithm is:

if
$$(a_ib_i) X = 1;$$

Where all cores which write into X, write the same value.

✓ PRAM advantages

- Large body of algorithms.
- Easy to think about it.
- Sync version of shared memory. It eliminates sync and common issues, allows focus on algorithms, but allows adding these issues and allows conversion to async versions.
- Exists architectures for both synch (PRAM) and async (SM) model.
- PRAM algorithms can be mapped to other models.

1.9 Amdahl's and Gustafson's Laws

The Amdahl's Law is a formula which gives the theoretical speedup in latency of the execution of a task at fixed workload that can be expected of a system whose resources are improved. The law can be stated as:

Definition 2: Amdahl's Law

The overall performance improvement gained by optimizing a single part of a system is limited by the fraction of time that the improved part is actually used.

In practice, Amdahl's law says that the computation consists of interleaved segments of two types:


1. **Serial segments** (which cannot be parallelized);

2. Parallelizable segments.

Therefore, the metrics we can obtain are the time on P processors metric, that it is greater than the fraction of time on a processor divided by the processors P, and the speedup metric, that it is less than the number of processors P:

$$T_P > \frac{T_1}{P}$$
 $SU < P$

Graphically, we can see a fixed part of the line, which is the **serial segment** (no speedup), and a set of instructions that can be **parallelized** (the sum of these segments is equal to the unit time 1).




Furthermore, if we identify the parallelizable segment as f and the serial segment as 1 - f, we obtain the following expressions:

$$SU(P,f) = \frac{T_1}{T_P} = \frac{T_1}{T_1 \cdot (1-f) + \frac{T_1 \cdot f}{P}} = \frac{1}{(1-f) + \frac{f}{P}}$$

$$\lim_{P \to \infty} SU(P,f) = \frac{1}{1-f}$$
(9)

In the following figure we can see the speedup with parameter f. Note the pessimism: for a problem with inherent f=90%, there is no point in using more than 10 processors.






Figure 5: Amdahl's law, SU(P), parameter f.

The original paper presenting Amdahl's Law [1] can be viewed by clicking on the link below or by scanning the QR code.

Amdahl's Law



Amdahl's law applies only to the cases where the problem size is fixed. In practice, as more computing resources become available, they tend to get used on larger problems (larger datasets), and the time spent in the parallelizable part often grows much faster than the inherently serial work. In this case, Gustafson's law gives a less pessimistic and more realistic assessment of the parallel performance. [7]

Gustafson's Law gives the speedup in the execution time of a task that theoretically gains from parallel computing, using a hypothetical run of the task on a single-core machine as the baseline. To put it another way, it is the theoretical "slowdown" of an already parallelized task if running on a serial machine.

Against Amdahl's law, Gustafson suggests the following ideas:

- Portion f is not fixed;
- The absolute serial time is fixed;
- Parallel problem size is increased to exploit more processors;
- Fixed serial time (s of total) and fixed parallel time (1 s of total) are invariants;
- Fixed time model and not fixed size model (as Amdahl's law):

$$SU(P) = \frac{T_1}{T_P} = \frac{s + P \cdot (1 - s)}{s + (1 - s)} = s + P \cdot (1 - s)$$
 (10)

Gustafson's law suggests a linear speedup and is empirically applicable to highly parallel algorithms.




Figure 6: Gustafson's law.

Amdahl's Law states that as computing power increases, computational requirements remain the same. In other words, the analysis of the same data will take less time with more computing power.

Gustafson, on the other hand, argues that more computing power leads to more careful and complete analysis of the data. Where it would not have been possible or practical to simulate the impact of nuclear denotation on every building, car, and their contents (including furniture, structural strength, etc.) because such a calculation would have taken more time than was available to provide an answer, the increase in computing power will prompt researchers to add more data to more fully simulate more variables, giving a more accurate result.

The original paper presenting Gustafson's Law [4] can be viewed by clicking on the link below or by scanning the QR code.

Gustafson's Law



2 Fundamentals of architecture

The main purpose of this chapter is to introduce some basics of parallel computing theory. It will introduce the simplest and trivial processor and the more complex and efficient variants. The topics introduced are explained in a simple way and without any deepening, because it is only an introduction. For those who have studied computer science, this chapter might be a little boring and you might notice that some topics are explained in a simplistic way.

2.1 Introduction

2.1.1 Simplest processor

Inside a computer, a processor executes instructions.

- Fetch/Decode: Determine which instruction to run next;
- **ALU** (execution unit): Performs the operation described by an instruction, which may change values in the processor's registers or the computer's memory;
- **Registers**: maintain program state, store values of variables used as inputs and outputs to operations.

The simplest and most basic processor executes **one instruction per clock** cycle.



Figure 7: The simplest and most basic processor.

2.1.2 Superscalar processor

A more "complex" and realistic model is the superscalar processor. This processor can decode and execute up to two instructions per clock. The execution is slightly different from the simplest processor. The processor automatically finds independent instructions in an instruction sequence and can execute them in parallel on multiple execution units.



Figure 8: The superscalar processor.

The superscalar processor takes advantage of **Instruction-Level Parallelism** (**ILP**)¹ within an instruction stream.

- Processing different instructions from the same instruction stream in parallel (within a core).
- Parallelism is automatically detected by the hardware during execution.

 $^{^1}$ Instruction-level parallelism (ILP) is the parallel or simultaneous execution of a sequence of instructions in a computer program. More specifically ILP refers to the average number of instructions run per step of this parallel execution.

2.1.3 Single Instruction, Multiple Data (SIMD) processor

Adding execution units (ALUs) to the simplest processor can increase compute capability. Amortize the cost/complexity of managing an instruction stream across many ALUs using Single Instruction, Multiple Data (SIMD) processing. Therefore, the same instruction is sent to all ALUs. This operation is performed in parallel on all ALUs.

✓ Advantages

- Efficient for data-parallel workloads: amortize control costs over many ALUs.
- Vectorization done by:
 - Compiler (explicit SIMD): parallelism is explicitly requested by the programmer through intrinsics, conveyed through parallel language semantics, and inferred through loop dependency analysis by the "auto-vectorizing" compiler. In other words, the SIMD parallelization is done at compile time, and when we inspect the program binary, we can see the SIMD instructions.
 - At runtime by hardware (<u>implicit SIMD</u>): the compiler generates a binary with scalar instructions, but n instances of the program are always executed together on the processor. The hardware (not the compiler) is responsible for the simultaneous execution of the same instruction by multiple program instances on different data on SIMD ALUs.

2.1.4 Multi-Core Processor

A Multi-Core Processor (MCP) is a microprocessor on a single integrated circuit (IC) with two or more separate central processing units (CPUs), called *cores* to emphasize their multiplicity (e.g., *dual-core* or *quad-core*). Each core reads and executes program instructions, specifically ordinary CPU instructions (such as add, move data, and branch). However, the MCP can execute instructions on separate cores simultaneously, increasing overall speed for programs that support multithreading or other parallel computing techniques.

✓ Advantages

- Provides thread-level parallelism: execute a completely different instruction stream on each core simultaneously.
- Software creates threads to expose parallelism to hardware (e.g., via threading API)

2.2 Accessing Memory

2.2.1 What is a memory?

A computer's memory is organized as an array of bytes. Each byte is identified by its address in memory (its position in that array).

Address	Value
0x0	16
0x1	255
0x2	14
0x3	0
0x4	0
0x5	0
0x6	6
0x7	0
8x0	32
0x9	48
OxA	255
0xB	255
0xC	255
0xD	0
OxE	0
OxF	0
0x10	128
:	:
0x1F	0

Table 1: Example illustration of the program's memory address space of 32 bytes, range from 0x0 to 0x1F.

From the processor's point of view, loading an instruction to access the contents present in memory is done with the ld assembly instruction. For example, ld $RO \leftarrow mem[R2]$ means "take the value from register R2 and put that value into register R0".

Before we introduce new concepts, let us take a moment to explain some important **terminology**:

- Memory Access Latency, is the time it takes for the memory system to deliver data to the processor.
- Processor Stall. A processor stalls when it cannot execute the next instruction in an instruction stream because of a dependency on a previous instruction that has not been completed. Accessing memory is a major source of stalling, which is one of the main reasons why memory accesses should be limited.

For example, in the following three assembler instructions, the add has to wait for the loading of R2 and R3 values, making parallelization more complicated:

```
ld r0 mem[r2]
ld r1 mem[r3]
add r0, r0, r1
```

• Memory Bandwidth, is the rate at which the memory system can provide data to a processor.

Bandwidth is the <u>critical</u> resource in modern computing.

High-performance parallel programs will:

- 1. Organize computation to fetch data from memory less frequently. For example, reuse data previously loaded by the same thread (temporal locality optimizations) or share data across threads (inter-thread cooperation);
- 2. Prefer to perform additional arithmetic to store/reload values:
- 3. Programs need to access memory infrequently to take advantage of modern processors.

2.2.2 How to reduce processor stalls

2.2.2.1 Cache

One of the most common solutions is caching.

A cache is a hardware or software component that stores data so that future requests for that data can be served faster; the data stored in a cache might be the result of an earlier computation or a copy of data stored elsewhere.

- A Cache Hit occurs when the requested data is found in a cache;
- A Cache Miss occurs when it cannot.


Cache hits are served by reading data from the cache, which is faster than recomputing a result or reading from a slower data store, so the **more requests** that can be served from the cache, the faster the system performs. [10]

Many modern CPUs have logic that predicts what data will be accessed in the future and "pre-fetches" that data into caches. **Prefetching** reduces stalls because the data is resident in the cache when it is accessed. But beware, the other side of the coin is that if the **guess is wrong**, the **performance is worse than the system without prefetching!**


2.2.2.2 Multi-threading

A Multithreaded Processor is one that has the ability to follow multiple instruction streams without software intervention. In practice, then, this includes any machine that stores multiple program counters (PCs) in hardware within the processor (i.e., on chip, for microprocessor-era machines). [9]

The main idea in this architecture is to interleave processing of multiple threads on the same core to hide stalls. In other words, if we can't make progress on the current thread, we work on another one.




practice, we see that a single arithmetic instruction takes 3 clock cycles and the memory stall takes 12 clock cycles. This means that from this situation we are using the CPU at only 20% (3 work clock cycles on 15)! Without suggesting the final solution, try to see what happens when we add another thread.



We have gained three clock cycles, and now we are taking advantage of the 40% of the core.

Now, how many threads do we need to achieve 100% utilization? The answer is simple: the number of clock cycles of the operations to be done before the stall plus the clock cycles of the stall divided by the working operations (operations that are not stalls). In our case: $15 \div 3 = 5$.



Note that if we add more threads, there will be no benefit because the CPU is already at 100%.

✓ Multithreaded Processor benefits

- A processor with multiple hardware threads has the **ability to avoid stalls** by executing instructions from other threads when one thread must wait for a long latency operation to complete. The latency of the memory operation is not changed by multithreading, it just no longer causes reduced processor utilization.
- A multithreaded processor hides memory latency by performing

arithmetic from other threads. Program that feature more arithmetic per memory access need fewer threads to hide memory stalls.

Type of hardware-supported multithreading

- Core manages execution contexts for multiple threads. This type still has the same number of ALU resources: multi-threading only helps to use them more efficiently in the face of high latency operations such as memory access. The processor decides which thread to run each clock cycle.
- Coarse-Grain Multithreading, also called Block Multithreading or Switch-On-Event Multithreading, has multiple hardware contexts associated with each processor core. A hardware context is the program counter, register file, and other data required to enabled a software thread to execute on a core. However, only one hardware context has access to the pipeline at a time. [9]
- Fine-Grain Multithreading (FGMT), also known as Interleaved Multithreading or Temporal Multithreading, is the type just described on the previous pages, as in the example on page 27.
- Simultaneous Multithreading (SMT) has multiple hardware contexts associated with each core. In a simultaneous multithreaded processor, instructions from multiple threads are available to be issued on any cycle. Therefore, all hardware contexts, and in particular all register files, must be accessible to the pipeline and its execution resources. [9]

In other words, each clock, the core selects instructions from multiple threads to execute on ALUs.

3 Programming models

3.1 Implicit SPMD Program Compiler (ISPC)

Before introducing the ISPC compiler, we give the definition of SPMD.

Definition 1: Single Program, Multiple Data (SPMD)

Single Program, Multiple Data (SPMD) is a term that has been used to refer to computational models for exploiting parallelism, where multiple processors work together to execute a program to achieve faster results.

The difference between *SPMD* and *SIMD* (page 24) is that in SPMD parallel execution, multiple autonomous processors simultaneously execute the same program at independent points, rather than in SIMD it is vectorization at the instruction level so that each CPU instruction processes multiple data elements.

In other words:

- SPMD: is the **programming abstraction**, because the programmer has to think; the program is written in terms of this abstraction.
- SIMD: in general, the compilers (ISPC) issue special vector instructions that execute the logic performed by each parallel instance created (ISPC gang spawned). In addition, the compilers handle the mapping of conditional control flow to vector instructions.

The difference and the terminology used by ISPC will become clearer in the following pages. We suggest that finish this section and come back here in a moment.

Definition 2: Implicit SPMD Program Compiler (ISPC)

Implicit SPMD Program Compiler (ISPC) is a compiler for a variant of the C programming language, with extensions for Single Program, Multiple Data (SPMD) programming. Under the SPMD model, the programmer writes a program that generally appears to be a regular serial program, though the execution model is actually that a number of program instances execute in parallel on the hardware. In other words, the ISPC gives the programmer some API to do parallelization on the code; it also generates high quality SIMD code to increase performance.

The definition, implementation, and other details are explained in the official Intel GitHub repository.

? How it works?

Let us take a general main program; when we call an ispc function, it causes a spawn of gang of ISPC program instances upon return, all instances have completed. These instances execute the same ISPC code simultaneously, and each instance has its own copy of local variables. Take the following ISPC code as an example:

```
export void ispc_sinx(
      uniform int N,
      uniform int terms,
      uniform float* x,
      uniform float* result
6){
       // assume N % programCount = 0
      for (uniform int i=0; i<N; i+=programCount) {</pre>
           int idx = i + programIndex;
9
           float value = x[idx];
           float numer = x[idx] * x[idx] * x[idx];
11
           uniform int denom = 6; // 3!
12
           uniform int sign = -1;
13
           for (uniform int j=1; j<=terms; j++) {
14
15
               value += sign * numer / denom
               numer *= x[idx] * x[idx];
16
               denom *= (2*j+2) * (2*j+3);
17
               sign *= -1;
          }
19
20
           result[idx] = value;
      }
21
22 }
```

In the example, the programCount (row 8) and programIndex (row 9) variables, uniform (row 2, and so on) data type tell us:

- programIndex gives the index of the SIMD-lane being used for running each program instance (in other words, it's a varying integer value that has value zero for the first program instance, and so forth).
- programCount gives the total number of instances in the gang.
- A variable that is declared with the uniform qualifier represents a single value that is shared across the entire gang.

Together, these can be used to uniquely map executing program instances to input data (programIndex and programCount, uniform data type).

With the ISPC analogy, the **SPMD programming model** should be clear:

- 1. **Single thread of control** (typically a main program);
- Invoke the SPMD function (in the previous example, the ispc_sinx function);
- 3. SPMD execution, then multiple instances of the function run in parallel (multiple logical threads of control);
- 4. Returns and resumes a single thread of control.




Figure 9: Example of execution with 8 instances (programCount equal to 8). For all program instances, there are eight non-contiguous values in memory. A special instruction called gather is needed to implement this, but unfortunately it is a more complex and expensive SIMD instruction rather than a contiguous implementation.

Figure 9 shows a possible execution of the ISPC function using 8 instances. The result is obtained and all is well. But there is one interesting observation. **Each ISPC instance writes each value in a non-contiguous way**. This can be done better:

```
export void ispc_sinx_v2(
       uniform int N,
       uniform int terms.
       uniform float* x,
       uniform float* result
6){
       // assume N % programCount = 0
       uniform int count = N / programCount;
       int start = programIndex * count;
           (uniform int i=0; i < count; i++) {</pre>
10
           int idx = start + i;
           float value = x[idx];
           float numer = x[idx] * x[idx] * x[idx];
13
           uniform int denom = 6; // 3!
uniform int sign = -1;
14
           for (uniform int j=1; j \le terms; j++) {
16
                value += sign * numer / denom
17
                numer *= x[idx] * x[idx];
18
                denom *= (j+3) * (j+4);
19
                sign *= -1;
20
21
22
           result[idx] = value;
       }
23
24 }
```



Figure 10: Example of execution with 8 instances (programCount equal to 8). A single "packed vector load" instruction efficiently implements this. For all program instances, since the eight values are contiguous in memory.

3.2 Shared Address Space Model

We give a general introduction to memory in the chapter 2.2. In parallel computing theory, each thread communicates with other threads using read/write operations. These instructions operate on a special area called the Shared Address Space (also called Shared Variables).

Definition 3: Shared Address Space

The **Shared Address Space** view of a parallel platform supports a common data space that is accessible to all processors. Processors interact by modifying data objects stored in this shared-address-space. [6]

Now the first and trivial question should be: a powerful tool is the possibility to allow communication between threads, but how can we guarantee that two or more threads accessing the same resource do not create well known problems, such as race condition?

This property, commonly called **mutual exclusion** or **atomic operation**, can be guaranteed with some techniques:

• Lock/Unlock mutex around a critical section:

```
Lock lock_variable;

Lock lock_variable;

lock_variable.lock();

// critical section
lock_variable.unlock();
```

• Some languages have first-class support for atomicity of code blocks:

```
atomic {
2  // critical section
3 }
```

Intrinsics for hardware-supported atomic read-modify-write operations:

```
atomicAdd(x, 10);
```

The shared address space requires hardware support to be efficiently implemented. The main idea is that each processor can directly reference the contents of any memory location. Some interesting examples that can be explored in depth are: SUN Niagara 2, Knights landing (KNL): 2nd Generation Intel Xeon Phi processor.

4 Parallel Programming Models and pthreads

4.1 How to create parallel algorithms and programs

Although *parallel algorithms* and *parallel programs* are in the same father set, the parallel computing topic, these two arguments are a little different.

Definition 1: Parallel Algorithms

A parallel algorithm, as opposed to a traditional serial algorithm, is an algorithm which can do multiple operations in a given time.

Definition 2: Parallel Programs

A parallel program is a program that uses multiple CPU cores, with each core performing a task independently.

However, designing parallel algorithms is not an easy task because there is no heuristic for designing parallel algorithms. There are some rules that help in the design. The same reasoning applies to parallel programs, because they depend on the chosen language and architecture.

Furthermore, there is no single correct solution, but several possible parallel solutions. A good first approach is to start with machine-independent issues (concurrency) and delay target-specific issues as much as possible.

Design a parallel algorithm	Design a parallel program	
Understand the problem to be solved	Analyze the target architecture(s)	
Analyze data dependencies	Choose the best parallel programming model and language	
Partition the solution	Analyze the communications (cost, latency, bandwidth, visibility, synchronization, etc.)	

Table 2: Design parallel algorithms and parallel programs.

The PCAM (Partitioning, Communication, Agglomeration, Mapping) methodology described by Argonne National Laboratory is intended to promote an exploratory approach to design in which machine independent issues, such as *concurrency*, are considered early and machine specific aspects of design are deferred until late in the design process. In other words, we immediately consider the machine-independent issues (e.g., concurrency) at the beginning of the design approach, and all machine-specific aspects are postponed to an advanced stage of the design process.

This methodology structures the design process into four distinct stages:

- 1. Partitioning. The computation that is to be performed and the data operated on by this computation are decomposed into small tasks. Practical issues such as the number of processors in the target computer are ignored, and attention is focused on recognizing opportunities for parallel execution.
- 2. <u>Communication</u>. The communication required to coordinate task execution is determined, and appropriate communication structures and algorithms are defined.
- 3. <u>Agglomeration</u>. The task and communication structures defined in the first two stages of a design are evaluated with respect to performance requirements and implementation costs. If necessary, tasks are combined into larger tasks to improve performance or to reduce development costs.
- 4. <u>Mapping</u>. Each task is assigned to a processor in a manner that attempts to satisfy the competing goals of maximizing processor utilization and minimizing communication costs. Mapping can be specified statically or determined at runtime by load-balancing algorithms.

In the first two stages, we focus on concurrency and scalability and seek to discover algorithms with these qualities. In the third and fourth stages, attention shifts to locality and other performance-related issues.




Figure 11: PCAM design methodology for parallel programs. Starting with a problem specification, develop a partition, determine communication requirements, agglomerate tasks, and finally map tasks to processors.

4.2 Analyze parallel algorithms

Whether we want to analyze our parallel algorithm created with the PCAM model or evaluate a general parallel algorithm, we need some metrics.

The classical **metrics** needed to evaluate a parallel algorithm are:

- Time complexity: quantifies the amount of time required to produce a solution.
- Resource complexity: quantifies how many resources are needed to produce the solution in that time.

In general, to analyze a **parallel algorithm**, we can consider its **structure** as a directed acyclic graph (DAG)², where the nodes are the task and the edges are the data dependencies.

Parallel Algorithm Terminology and Metrics

- Concurrent tasks, each task is executed independently.
- Parallel tasks, each task is executed at the *same time* (because multiple computing resources are available).
- Work W is the *number of operations executed*. It may be higher than the sequential version of the algorithm due to communication overhead, etc.
- Span S is the longest chain of dependencies (i.e., the critical path) that determines the minimum time required to execute the algorithm. This is a lower bound on the running time, regardless of the number of processors. The range indicates the ability of an algorithm to get better performance on more processors.

? How do we calculate the Span metric?

- As we just said, we represent a parallel algorithm as a DAG graph, where nodes represent tasks and edges represent dependencies between tasks;
- 2. We assign weights to each node that represent the time required to perform the corresponding task;
- 3. We try to find the Critical Path. In other words, we determine the path from the start node to the end node that has the maximum cumulative weight;
- 4. Finally, the sum of the weights of the nodes on the critical path gives us the span value!

 $^{^2}$ A **Directed Acyclic Graph (DAG)** is a directed graph, i.e. with oriented edges, without cycles.

• Parallelism *P* is the *measure of efficiency in the use of resources*. Trivially, it is the number of operations performed divided by the longest chain of dependencies:

$$P = \frac{W}{S} \tag{11}$$

It indicates how many processors can be effectively used by the computation. If the work is equal to the span, the parallelism is 1 and the computation is sequential. Ideally, but not necessarily, we win with polylogarithmic span, because if the work is $O(n \log n)$ and the span is $O(\log^2 n)$, then the parallelism is $O\left(\frac{n}{\log n}\right)$, which is actually quite high (and unlikely to be a bottleneck on most machines in the next 25 years). [2]

This measure is one of the most important. It indicates the number of processors that are not idle. It is obvious that a good parallel algorithm is designed to have the lowest possible work (less operation, then less resource usage, then less cost, and so on) and the highest possible parallelism (achievable by reducing the span, and this should be trivial, since the metric P is given by work divided by the span, so reducing the denominator, you can get a higher value).

As in all things, there is a **trade-off** between the lowest possible "work" and the highest possible "parallelism". Reducing the work too much could eliminate the possibility of parallelizing our algorithm, and on the other hand, reducing the span too aggressively could cause communication/synchronization overhead.




Figure 12: Example of DAG implementation with work equal to 9, span equal to 5, and parallelism equal to 1.8 $(9 \div 5)$. The span calculus is not well known, has been calculated *a priori*.

Finally, we use a mathematical annotation and not only a graphical (DAG) annotation. The **Composition Rules** help determine how to combine smaller parallel tasks into a larger algorithm, while analyzing the Work and Span of the combined algorithm:

• Single operation. An operation takes 1 unit of work and 1 unit of span time.

$$W(op) = 1$$
 $S(op) = 1$

• Sequential Composition.

– The total work of executing e_1 and e_2 sequentially is the sum of their individual work.

$$W(e_1, e_2) = W(e_1) + W(e_2)$$

- The total span of executing e_1 and e_2 sequentially is the sum of their individual spans.

$$S(e_1, e_2) = S(e_1) + S(e_2)$$

• Parallel Composition.

– The total work of executing e_1 and e_2 in **parallel** is still the sum of their individual works.

$$W(e_1||e_2) = W(e_1) + W(e_2)$$

- The total span of executing e_1 and e_2 in **parallel** is the *maximum of* their individual spans, since they can be executed simultaneously.

$$S(e_1||e_2) = \max(W(e_1), W(e_2))$$

4.3 Technologies

Some famous architecture to work with parallel programming:

• Verilog/VHDL are hardware description languages. The target architectures are \overline{ASIC} and \overline{FPGA} . The parallelism and the communication are explicit.

✓ Pros

- Complete control on computation and memory
- No overhead introduced in the computation
- Provides access to potentially large computational power

A Cons

- Requires specific hardware (e.g., ASIC or FPGA) to implement functionality
- Difficult to learn: completely different programming language and programming paradigm
- Depends on the chosen target architecture
- MPI is a *library*. The target architectures are *Multi CPUs*. The parallelism is implicit and the communication is explicit.

✓ Pros

- Can be adopted on different types of architecture
- Scalable solutions
- Synchronization and data communication are explicitly managed

A Cons

- Communication can introduce significant overhead
- Programming paradigm more difficult than shared memory-based ones
- Standard does not reflect immediately advances in architecture characteristics
- <u>PThread</u> is a *library*. The target architectures are *Multi-core CPUs*. The parallelism is explicit and the communication is implicit.

✓ Pros

- Can be adopted on different types of architecture
- Explicit parallelism and full control over application

A Cons

- Task management overhead can be significant
- Not easily scalable solutions
- Low level API
- OpenMP is a C/Fortran extensions. The target architectures are Multicore CPUs. The parallelism is explicit and the communication is implicit.

✓ Pros

- Easy to learn
- Scalable solution
- Parallel applications can also be executed sequentially

A Cons

- Mainly focused on shared memory homogeneous systems
- Requires small interaction between tasks
- <u>CUDA</u> is a *C extensions*. The target architectures are *CPU plus GPU(s)*. The **parallelism** is **implicit/explicit** and the **communication** is **implicit/explicit**.

✓ Pros

- Provides access to the computational power of GPUs
- Writing a CUDA kernel is quite easy
- Already optimized libraries

A Cons

- Targets only NVIDIA GPUs
- Difficult to extract massive parallelism from application
- Difficult to optimize CUDA kernel
- OpenCL is a C/C++ extensions and API. The target architectures are heterogeneous architecture. The parallelism is implicit/explicit and the communication is implicit/explicit.

✓ Pros

- Target-independent standard
- Hides architecture details
- Same programming infrastructure for every heterogeneous architecture: CPU + GPU (and FPGA)

A Cons

- Difficult programming paradigm for its heterogeneity
- Hiding of architecture details makes difficult to obtain best performances
- Gradually abandoned
- Apache Spark is an API. The target architectures are multi CPUs. The parallelism is implicit and the communication is implicit.

✓ Pros

- API for different languages
- Explicit parallelization and communication are not required
- Preinstalled on cloud provide VMs

A Cons

- Suitable only for big data applications
- Does not (yet) fully support GPUs

Regardless of these technologies, it is quite common to mix some of them:

- **OpenMP** + **CUDA**: allows to exploit multi-core CPU and GPU. CUDA is used to parallelize GPU code and OpenMP is used to parallelize CPU code.
- MPI + OpenMP: the most common scenario are:
 - 1. MPI used to express coarser parallelism (multi CPU) and OpenMP used to express finer parallelism (multi core).
 - $2.\,$ MPI used to implement communication and OpenMP used to parallelize computation.
- OpenCL + Verilog or VHDL: in principle, hardware kernels (implemented for example on FPGA) can be used as accelerators; OpenMP used to describe parallelism among different processing elements; Verilog/VHDL used to describe hardware kernel. An example of target: Intel Xeon Scalable.

4.4 Threads

4.4.1 Flynn's taxonomy

Flynn's taxonomy is a classification of computer architectures, proposed by Michael J. Flynn. The classification system has been used as a tool in the design of modern processors and their functionalities. Since the rise of multiprocessing central processing units (CPUs), a multiprogramming context has evolved as an extension of the classification system.

The four initial classifications defined by Flynn are based upon the number of concurrent instruction (or control) streams and data streams available in the architecture:

- Single Instruction stream, Single Data stream (SISD)
- Single Instruction stream, Multiple Data streams (SIMD)
- Multiple Instruction stream, Single Data stream (MISD)
- Multiple Instruction stream, Multiple Data stream (MISD)

It is important to quote it because it is the basis for the development of many advanced technologies.

4.4.2 Definition

A UNIX process can be created by the operating system and contains information about program resources and program execution status.

Definition 3: Thread

A thread is an independent stream of instructions within a process. Threads can be scheduled by the operating system, and each thread can run concurrently with other threads. A thread also has local resources and can access the shared process resources.

In other words, a thread can be thought of as any **procedure that runs** independently of its main program. We can create each thread dynamically during execution. A good point is that a multi-threaded program is lighter than a multi-process program.

When a thread exists within a process, it shares most of the process resources, for example:

- Changes made by one thread to shared system resources (such as closing a file) will be seen by all other threads.
- Two pointers having the same value point to the same data.
- Implicit communication by reading and writing shared variables.
- Reading and writing to the same memory locations requires explicit synchronization by the programmer. If this rule is not followed, the code may suffer from a data race or race condition ³ problem.

The most common models for threaded programs are the manager / worker model⁴ and pipeline.

This chapter introduces the POSIX threads model.

Definition 4: pthreads

POSIX Threads, commonly known as **pthreads**, is an **execution** model that exists independently from a programming language, as well as a parallel execution model. It allows a **program to control multiple different flows of work that overlap in time**. Each flow of work is referred to as a thread, and creation and control over these flows is achieved by making calls to the POSIX Threads API.

POSIX threads and OpenMP are two implementations of a shared memory parallel programming model using threads. The programmer is responsible for handling parallelism and synchronization, usually through a library of subroutines or a set of compiler directives. Typically, hardware vendors have implemented their own proprietary versions of threads, but in this course we will look at POSIX threads (pthreads) and OpenMP.

³In parallel computing, a **Data Race** or **Race Condition** is a software problem that occurs when two threads (or processes) access the same variables, and at least one does a write. They can finish in a different order than expected.

⁴The manager/worker pattern is described as follows. The idea is that the work that needs to be done can be divided by a "manager" into separate pieces and the pieces can be assigned to individual "worker" processes. Thus the manager executes a different algorithm from that of the workers, but all of the workers execute the same algorithm. Most implementations of MPI allow MPI processes to be running different programs (executable files), but it is often convenient (and in some cases required) to combine the manager and worker code into a single program.

4.4.3 pthreads API

In 1995, the IEEE POSIX 1003.1c standard specified the API for explicitly managing threads. An API is a set of C language programming types and procedure calls.

- Header file to include in the main file: pthread.h.
- To **compile** and use it, it is necessary to add the **flag** -pthread to the gcc (or g++) options.

The API are divided by what we want to do. In general, there are two sets: thread management and thread synchronization.

- Thread Management
 - Creation (page 45)
 - Termination (page 46)
 - Joining (page 47)
 - Detaching (page 48)
 - Joining through Barriers (page 49)
- Thread Synchronization
 - Mutexes (page 50)
 - Condition variables (page 50)

4.4.3.1 Creation

Once threads are created, they are peers, and may create other threads. There is no implied hierarchy or dependency between threads. The maximum number of threads depends on the implementation.

```
pthread API: pthread_create

int pthread_create(
   pthread_t * thread,
   const pthread_attr_t * attr,
   void * (* start_routine) (void *),
   void * arg

begin{center}
   void * (* start_routine) (void *)
   void * arg
   void * arg
   void * arg
   void * arg
```

- Return value: on success, pthread_create() returns 0; on error, it returns an error number, and the contents of *thread are undefined.
- Arguments:
 - thread: identifier for the new thread returned by the subroutine.
 - attr: used to set thread attributes, such as joinable, detached, scheduling and stack size.

- start_routine: the C routine that the thread will execute once it is created.
- arg: argument passed to start_routine. It must be passed by address as a pointer cast of type void.

4.4.3.2 Termination

The thread returns from its startup routine when its "life" ends. The thread makes a call to the pthread_exit subroutine.

Doc.

```
pthread API: pthread_exit

void pthread_exit(void *retval)
```

- Return value: this function does not return to the caller.
- Arguments:
 - retval: function terminates the calling thread and returns a value via retval.

The thread is canceled by another thread via the pthread_cancel routine.

```
pthread API: pthread_cancel

int pthread_cancel(pthread_t thread)
```

- Return value: on success, pthread_cancel() returns 0; on error, it returns a nonzero error number.
- Arguments:
 - thread: the pthread_cancel() function sends a cancellation request to the thread thread.

4.4.3.3 **Joining**

The join function blocks the calling thread until the specified thread exits.

```
pthread API: pthread_join

int pthread_join(pthread_t thread, void **retval)
```

- Return value: on success, pthread_join() returns 0; on error, it returns an error number.
- Arguments:
 - thread: the pthread_join() function waits for the thread specified by thread to terminate. If that thread has already terminated, then pthread_join() returns immediately. The thread specified by thread must be joinable.
 - If multiple threads simultaneously try to join with the same thread, the results are undefined. If the thread calling pthread_join() is canceled, then the target thread will remain joinable (i.e., it will not be detached).
 - retval: if retval is not NULL, then pthread_join() copies the exit status of the target thread (i.e., the value that the target thread supplied to pthread_exit()) into the location pointed to by retval. If the target thread was canceled, then PTHREAD_CANCELED is placed in the location pointed to by retval.

4.4.3.4 Detaching

The detach function marks a thread as detached. When a thread is detached, its resources are automatically released back to the system when the thread terminates, without the need for another thread to join with it.

Why would I need to detach a thread and not join it?

Good question. The answer depends on what we have to do.

- Fire and forget tasks. When we start a thread to perform a task that doesn't require further interaction or result processing, releasing it ensures that the resources are automatically cleaned up when the task is complete.
- Resource management. Detaching avoids the need for another thread to call pthread_join(), which can save system resources and reduce the complexity of our code. It's especially useful in a highly concurrent application with many short-lived threads.
- Avoid deadlocks. When we have potential circular dependencies or complex synchronization between threads, detaching threads can help avoid deadlocks by eliminating the need for one thread to wait on another.
- Long-running background tasks. For tasks that should run independently in the background and not block the main program flow, detaching makes sense. We make sure they clean up after themselves without having to explicitly manage their lifecycle.

Doc.



int pthread_detach(pthread_t thread)

- Return value: on success, pthread_detach() returns 0; on error, it returns an error number.
- Arguments:
 - thread: the pthread_detach() function marks the thread identified by thread as detached. When a detached thread terminates, its resources are automatically released back to the system without the need for another thread to join with the terminated thread.
 - Attempting to detach an already detached thread results in unspecified behavior.

4.4.3.5 Joining through Barriers

The barrier init function initializes a barrier object, and the barrier wait function blocks a thread until the specified number of threads have called it. A barrier object is, in parallel computing, a synchronization tool that ensures that multiple threads reach a certain point of execution before any of them continue. It's like a checkpoint that everyone must reach before continuing, ensuring coordinated progress in a parallel algorithm.⁵

```
pthread API: pthread_barrier_init

int pthread_barrier_init(
    pthread_barrier_t * barrier,
    pthread_barrierattr_t * attr,
    unsigned int count

)
```

```
pthread API: pthread_barrier_wait

int pthread_barrier_wait(pthread_barrier_t * barrier)
```

- Return value: on success, function return 0; on error, they return an error number.
- Arguments: the main and most important argument is count, which specifies the number of threads to wait for.

⁵For example, imagine multiple threads working on different parts of a matrix. A barrier can ensure that all threads finish their part of the computation before moving on to the next phase, such as combining results or performing subsequent operations.

4.4.3.6 Mutexes

Mutex variables are the basic method of protecting shared data when multiple writes occur. Only one thread can lock a mutex variable at a time. If multiple threads attempt to lock a mutex, only one thread will succeed. Threads that fail to acquire the mutex are blocked. There is also the trylock function, which returns immediately if the mutex is currently locked (by any thread, including the current thread). Note that a lock function has the potential to create a deadlock situation.

There are also three types of mutex that can be set using the settype function:

- Normal Mutex (PTHREAD_MUTEX_NORMAL). A normal mutex does not check for errors such as deadlock. If a thread tries to lock a mutex it already owns, the thread will deadlock.
- Error Check Mutex (PTHREAD_MUTEX_ERRORCHECK). Provides error checking. If a thread tries to lock a mutex it already owns, lock function will return an error instead of deadlocking.
- Recursive Mutex (PTHREAD_MUTEX_RECURSIVE). Allows the same thread to lock the mutex multiple times without deadlocking. Each lock must have a corresponding unlock.

Doc.

```
pthread API: pthread_mutex_lock

int pthread_mutex_lock(pthread_mutex_t *mutex)

pthread API: pthread_mutex_trylock

int pthread_mutex_trylock(pthread_mutex_t *mutex)

pthread API: pthread_mutex_unlock

int pthread_mutex_unlock(pthread_mutex_t *mutex)
```

4.4.3.7 Condition variables

Mutexes implement synchronization by serializing data accesses. Condition variables allow threads to synchronize explicitly by signaling the meeting of a condition. Without condition variables, the programmer would need to poll to check if the condition is met.

5 OpenMP v5.2

5.1 Introduction

OpenMP is a scalable model that gives parallel programmers a simple and flexible interface for developing portable parallel applications in C/C++ and Fortran.

- Header file to include in the main file: omp.h.
- To compile and use it, it is necessary to add the flag -fopenmp to the gcc (or c++) options.

✓ Benefits

- Standard across a variety of shared memory architectures and platforms.
- Supports three famous languages: Fortran, C and C++.
- Scalable from embedded systems to the supercomputer.
- The directives are intuitive, and with a limited set of directives we can implement parallel algorithms.
- Incremental parallelization of serial program.
- Coarse-grained and fine-grained parallelism. See here here an interesting difference between coarse-grained and fine-grained architecture:



? How it works?

OpenMP is based on the **fork-join paradigm**. A "master" thread forks a specified number of "slave" threads. Tasks are divided among the "slaves", and each "slave" runs concurrently as the runtime allocates threads to different processors.

- 1. Thread #0 born. OpenMP programs start with a single thread;
- 2. **Fork**. At the start of a parallel region, the *master* creates a team of parallel worker threads (*slaves*).
- 3. **OpenMP code block**. Statements in the parallel block are executed in parallel by each thread.
- 4. **Join**. At the end of the parallel region, all threads synchronize (implicit barrier, see definition on page 49) and join the master thread. [5]




Figure 13: Example of an OpenMP program called Hello. At runtime, the *master* thread forks 3 additional *slave* threads to print hello. The example is very trivial, but here is a graphical representation of the workflow. An interesting thing to note is that **OpenMP creates** a sort of **region where each thread executes all the instructions in the OpenMP block**. This is important to understand. [5]

5.2 Basic syntax

We can manage OpenMP work flow using the directive syntax. We remember that the reference guide of OpenMP is available on their website:

Reference Guide



A directive is a combination of the base-language mechanism and a directive-specification (the directive-name followed by optional clauses). A construct consists of a directive and, often, additional base language code. In C++ directives are formed from either pragmas or attributes.

```
OpenMP: pragma omp

#pragma omp directive-specification
```

The number of OpenMP threads can be set using:

- At compilation time: using the environment variable OMP_NUM_THREADS
- At runtime: using the function

```
OpenMP: omp_set_num_threads

void omp_set_num_threads(int num_threads)
```

Other useful function to get information about threads:

• The number of threads in the current team:

```
OpenMP: omp_get_num_threads

int omp_get_num_threads()
```

The binding region for an omp_get_num_threads region is the innermost enclosing parallel region. If called from the sequential part of a program, this routine returns 1.

• The upper bound on the number of threads that could be used to form a new team if a parallel construct without a num_threads clause were encountered after execution returns from this routine.

```
OpenMP: omp_get_max_threads
int omp_get_max_threads()
```

• The thread number of the calling thread, within the current team.

```
OpenMP: omp_get_thread_num

int omp_get_thread_num()
```

OpenMP programs execute serially until they reach a parallel directive. As we have explained at page 52, the thread that was executing the code spawns a group of "slave" threads and becomes the "master" (thread ID 0). The code in the structured block is replicated, each thread executes a copy. At the end of the block there is an implied barrier, only the "master" thread continues.

```
OpenMP: pragma omp parallel

#pragma omp parallel optional-clauses
```

The parallel directive has **optional** clauses, the most commonly used are:

• Specify the number of threads to spawn:

```
#pragma omp parallel num_threads(int)
```

• Conditional parallelization with:

```
1 #pragma omp parallel if (condition)
```

```
} else {
          printf_s("val = %d, serialized\n", val);
15
16 }
17
18 int main( )
19 {
      omp_set_num_threads(2);
20
      test(0);
      test(2);
22
23 }
  The output will be:
val = 0, serialized
val = 2, parallelized with 2 threads
```

• Data scope clauses (explained in the following pages).

The number of threads in a parallel region is determined by the following factors, in order of priority (high to low):

- 1. Evaluation of the if clause;
- 2. Value of the num_threads clause;
- 3. Use of the omp_set_num_threads() library function;
- 4. Setting of the ${\tt OMP_NUM_THREADS}$ environment variable;
- 5. Implementation default, e.g., the number of CPUs on a node.

5.3 Work sharing

Work-sharing constructs divide the execution of a region of code among the team members who encounter it. A work-sharing construct must be enclosed in a parallel region for the directive to be executed in parallel. Note that the constructs do not start new threads. Also, there is no implicit barrier at the *entry* of a work-sharing construct, but there is an implicit barrier at the *exit* of a work-sharing construct.

5.3.1 For

The for directive shares iterations of a loop across the team (data parallelism).




Figure 14: OpenMP for loop.

```
OpenMP: pragma omp for

#pragma omp parallel

{
3      #pragma omp for
4      /* for loop */

5 }
```

The for directive parallelize execution of iterations. The number of iteration cannot be internally modified. Some common clauses are:

- schedule that describes how iterations of the loop are distributed among the threads in the team. The schedule type can be either dynamic, guided, runtime, or static.
 - static. Loop iterations are divided into blocks of size chunk and then statically allocated to threads. If chunk is <u>not</u> specified, the iterations are divided evenly (if possible) among the threads.




Figure 15: static schedule.

- dynamic. Loop iterations are divided into blocks of size chunk and distributed among the threads at runtime; when a thread completes one chunk, it is dynamically allocated another. The default chunk size is 1. In fact, we can see in the image that the order is not always the same.




Figure 16: dynamic schedule.

- runtime. Depends on environment variable OMP_SCHEDULE.
- guided. Static, gradually decreases the chunk size (chunk specifies the smallest one).

```
OpenMP: guided schedule

#pragma omp for schedule(guided)
```




Figure 17: guided schedule.

```
Example 2: schedule types
#include <stdio.h>
2 #include <omp.h>
4 #define NUM_THREADS 4
5 #define STATIC_CHUNK 5
6 #define DYNAMIC_CHUNK 5
7 #define NUM_LOOPS 20
8 #define SLEEP_EVERY_N 3
10 int main()
11 {
       int nStatic1[NUM_LOOPS],
12
           nStaticN[NUM_LOOPS];
13
14
       int nDynamic1[NUM_LOOPS],
           nDynamicN[NUM_LOOPS];
15
      int nGuided[NUM_LOOPS];
16
17
       omp_set_num_threads(NUM_THREADS);
18
19
20
       #pragma omp parallel
21
22
           #pragma omp for schedule(static, 1)
23
           for (int i = 0 ; i < NUM_LOOPS ; ++i)</pre>
24
25
                if ((i % SLEEP_EVERY_N) == 0)
                    Sleep(0);
26
27
               nStatic1[i] = omp_get_thread_num();
28
29
           \verb|#pragma omp for schedule(static, STATIC_CHUNK)|\\
30
           for (int i = 0 ; i < NUM_LOOPS ; ++i)</pre>
31
           {
32
                if ((i % SLEEP_EVERY_N) == 0)
33
                    Sleep(0);
34
               nStaticN[i] = omp_get_thread_num( );
35
36
           }
37
38
           #pragma omp for schedule(dynamic, 1)
           for (int i = 0 ; i < NUM_LOOPS ; ++i)</pre>
39
           {
40
                if ((i % SLEEP_EVERY_N) == 0)
41
42
                    Sleep(0);
               nDynamic1[i] = omp_get_thread_num();
43
44
45
           \verb"#pragma omp for schedule(dynamic, DYNAMIC_CHUNK)"
46
           for (int i = 0 ; i < NUM_LOOPS ; ++i)</pre>
47
           {
48
49
                if ((i % SLEEP_EVERY_N) == 0)
```

```
Sleep(0);
            nDynamicN[i] = omp_get_thread_num();
52
53
        #pragma omp for schedule(guided)
54
        for (int i = 0 ; i < NUM_LOOPS ; ++i)</pre>
56
            if ((i % SLEEP_EVERY_N) == 0)
57
               Sleep(0);
            nGuided[i] = omp_get_thread_num();
59
60
61
     }
62
63
     printf_s("
     printf_s("| static | static | dynamic | dynamic |
64
     guided |\n");
                  1 | %d | 1 | %d |
65
     printf_s("|
               STATIC_CHUNK, DYNAMIC_CHUNK);
66
     printf_s("
68
     for (int i=0; i<NUM_LOOPS; ++i)</pre>
69
70
        printf_s("| %d | %d | %d | %d
                   " %d |\n",
72
                   nStatic1[i], nStaticN[i],
73
                   nDynamic1[i], nDynamicN[i], nGuided[
74
     i]);
75
76
78 }
 The result will be:
2 | static | static | dynamic | dynamic | guided |
3 | 1 | 5 | 1 | 5 |
        | 0 | 0
                                 | 1 |
5 | 0
                        1 2
6
      1
         0
                      3
                              2
                                       1
        İ
7
             0
                     3
      2
                                       1
            0
        | |
                   3
2
8
      3
                              2
9
      0
             0
                              2
                                       1
                    2
        -1
                 -
10
      1
             1
                              3
                                       3
                    2
11
      2
             1
                              3
      3
                     0
                              3
                                       3
12
         1
                    0
        -1
13
             1
      0
                              3
                                       3
14
                     0
        15
      2
             2
                              0
                     1
             2
                                       2
16
      3
                     1
                              0
17
             2
                              0
                 -1
                                 1
                                       3 |
      1
        | |
             2
                      2
                              0
18
19
```

```
20
21
        0
                  3
                             3
                                        1
                                                    1
                  3
                             3
22
        1
                                        1
                                                    1
23
        2
                  3
                             3
                                        1
                             0
24
        3
             -
                  3
                       1
                                        1
                                                    3
                                                        1
25
```

• nowait to avoid synchronization at the end of the parallel loop. It overrides the barrier implicit in a directive.

1 #pragma omp for nowait

```
Example 3: nowait clause
 #include <stdio.h>
3 #define SIZE 5
5 void test(int *a, int *b, int *c, int size)
6 {
        int i;
        #pragma omp parallel
8
9
              #pragma omp for nowait
for (i = 0; i < size; i++)
   b[i] = a[i] * a[i];</pre>
11
12
13
             #pragma omp for nowait
for (i = 0; i < size; i++)
    c[i] = a[i]/2;</pre>
14
15
16
        }
17
18 }
19
20 int main( )
21 {
        int a[SIZE], b[SIZE], c[SIZE];
22
23
        int i;
24
        for (i=0; i<SIZE; i++)</pre>
25
26
             a[i] = i;
27
        test(a,b,c, SIZE);
28
29
        for (i=0; i<SIZE; i++)
    printf_s("%d, %d, %d\n", a[i], b[i], c[i]);</pre>
30
31
32 }
   The output will be:
 1 0, 0, 0
2 1, 1, 0
3 2, 4, 1
4 3, 9, 1
5 4, 16, 2
```

5.3.2 Sections

Section identifies code sections to be divided among all threads.

Sections allow to specify that the enclosed section(s) of code are to be executed in parallel. Each section is executed once by a thread in the team.

The sections directive identifies a noniterative work-sharing construct that specifies a set of constructs that are to be divided among threads in a team. Each section is executed once by a thread in the team.

Each section is preceded by a section directive, although the section directive is optional for the first section. The section directives must appear within the lexical extent of the sections directive. There's an **implicit barrier** at the end of a sections construct, unless a **nowait** is specified.

Restrictions to the sections directive are as follows:

- A section directive must not appear outside the lexical extent of the sections directive.
- Only a single nowait clause can appear on a sections directive.




Figure 18: Breaks work into separate, discrete sections, each executed by a thread (functional parallelism).

5.3.3 Single/Master

A section (not the directive) of code should be executed on a single thread, not necessarily the main (master) thread. The single directive identifies a construct that specifies that the associated structured block is executed by only one thread in the team (not necessarily the master thread).

- single specifies that a section of a code is **executed only by a single** thread.
- master specifies that a section of a code is executed only by the master.

There's an **implicit barrier** after the **single** construct unless a **nowait** clause is specified.

5.3.4 Tasks

The following section has been enhanced with slides from Senior Principal Engineer Mattson Tim. He's a senior principal engineer at Intel, where he's been since 1993. His profile can be seen here and the slides are available online here. He has also made an interesting YouTube series on the introduction to OpenMP.

Tasks are independent units of work. They consist of: code to execute, data environment, and internal control variables (ICV). Threads perform the work of each task. The runtime system decides when to execute tasks; each task can be deferred or executed immediately.

Some useful terminology:

- Task construct. It identifies the task directive plus the structured block.
- *Task*. It is the package of code and instructions for allocating data created when a thread encounters a task construct.
- *Task region*. It is the dynamic sequence of instructions generated by the execution of a task by a thread.

Tasks are guaranteed to complete at thread barriers (using the barrier directive) or at task barriers (using the taskwait directive):

```
#pragma omp parallel // omp directive to parallel the code
2
      #pragma omp task // multiple foo tasks created here,
3
                        // one for each thread
      #pragma omp barrier // all foo tasks guaranteed
                           // to be completed here
                           // only one thread can access to
      #pragma omp single
                           // this piece of code
          \#pragma omp task // one bar task created here
          bar();
13
      // foo task guaranteed to be completed here
14
15 }
```

Example 4: Fibonacci with tasks

Let us see a Fibonacci example of data scoping using the tasks. In the following code, we create the Fibonacci function and we create two tasks, but each task has a private variable and these variables are also used in the return statement:

```
int fib(int n) {
   int x, y;
   if(n < 2)
        return n;
        #pragma omp task
        x = fib(n-1);
        #pragma omp task
        y = fib(n-2);</pre>
```

```
#pragma omp taskwait
       return x + y;
10
11 }
  A good solution is to "share" the x and y variables because we need both
  values to calculate the sum.
int fib(int n) {
       int x, y;
if(n < 2)</pre>
          return n;
       #pragma omp task shared(x)
       x = fib(n-1);
       #pragma omp task shared(y)
       y = fib(n-2);
       #pragma omp taskwait
10
       return x + y;
11 }
```

✓ Main advantage

Note the following code:

```
1 // create a team of threads
2 #pragma omp parallel
3 {
      // one thread executes the single construct
      // and other threads wait at the implied
      // barrier at the end of the single construct
      #pragma omp single
      { // block 1
          node *p = head;
10
           while(p) { // block 2
               // the single thread creates a task
11
               ^{\prime\prime} with its own value for the pointer p
12
               #pragma omp task firstprivate(p)
                  process(p);
14
               p = p \rightarrow next; // block 3
15
16
           // execution moves beyond the barrier
17
18
           // once all the tasks are complete
19
20 }
```

The tasks have the **potential to parallelize irregular patterns and recursive function calls**. See Figure 19 (page 65) to understand how the runtime system can optimize execution using the tasks.




Figure 19: The main advantage of the tasks is to parallelize irregular patterns and recursive function calls.

5.4 Synchronization


The following section has been enhanced with slides from Senior Principal Engineer Mattson Tim. He's a senior principal engineer at Intel, where he's been since 1993. His profile can be seen here and the slides are available online here. He has also made an interesting YouTube series on the introduction to OpenMP.

OpenMP is a multi-threaded, shared address model. This means that threads communicate by sharing variables. Unfortunately, this can cause some problems such as race conditions (page 44). The solution is to **use synchronization to protect against data conflicts**. The good news is that synchronization can avoid data race problems, but it is also an **expensive method**. So we can use synchronization, but we **need to change the way data is accessed to minimize the need for synchronization**.

Synchronization brings one or more threads to a well-defined and known point in their execution. The two most common forms of synchronization are:

- Barrier: each thread wait at the barrier until all threads arrive.
- Mutual exclusion: define a block of code that only one thread at a time can execute.

The OpenMP directives are: critical, atomic, and barrier. These are high-level synchronization directives, but there are also low-level synchronization directives, such as flush and locks, but they are too complex at the moment, we will see them later.



(a) Barrier. Each thread wait at the barrier until all threads arrive.

(b) Mutual exclusion. Define a block of code that only one thread at a time can execute.

Barrier. Each thread waits until all threads arrive.

```
OpenMP: barrier

#pragma omp barrier name
```

An optional name may be used to identify the critical region. A thread waits at the beginning of a critical region until no other thread is executing a critical region (anywhere in the program) with the same name. All unnamed critical directives map to the same unspecified name.

Example 5: synchronization with barrier directive

The following example includes several critical directives. The example illustrates a queuing model in which a task is dequeued and worked on. To guard against many threads dequeuing the same task, the dequeuing operation must be in a critical section. Because the two queues in this example are independent, they're protected by critical directives with different names, xaxis and yaxis. [8]

<u>Mutual exclusion</u>. Only one thread at a time can enter a *critical* region.

```
OpenMP: critical

#pragma omp critical
```

	omp critical	omp single
Meaning	Run code segment one by one by all threads	Run code segment once by any thread
Number of times code is executed	Number of threads	Only one
Use case	Avoid race condition	Manage control variables or signals

Table 3: **A** omp critical vs omp single

Example 6: synchronization with critical directive Note the following code: 1 float res; 3 #pragma omp parallel float B; int i, id, nthrds, niters = big_number; id = omp_get_thread_num(); nthrds = omp_get_num_threads(); for (i = id; i < niters; i += nthrds) {</pre> $B = big_job(i);$ #pragma omp critical // threads wait their turn; res += consume(B); // only one at a time // calls consume 13 } 15 } 16

Atomic. Provides mutual exclusion, but only when updating a memory location. It ensures that a particular memory location is accessed atomically. It is valid only for the following statement and not for a structured block.

The statement inside the atomic must be one of the following forms:

- x binop = expr
- x++ or ++x
- x-- or --x

Where x is an lvalue of scalar type and binop is a non-overloaded builtin operator.

```
OpenMP: atomic

#pragma omp atomic
```

```
#pragma omp parallel

#pragma omp parallel

double tmp, B;

B = DOIT();

tmp = big_ugly(B);

#pragma omp atomic

X += tmp;

}
```

References

- [1] Gene M Amdahl. Validity of the single processor approach to achieving large scale computing capabilities, reprinted from the afips conference proceedings, vol. 30 (atlantic city, nj, apr. 18–20), afips press, reston, va., 1967, pp. 483–485, when dr. amdahl was at international business machines corporation, sunnyvale, california. *IEEE Solid-State Circuits Society Newsletter*, 12(3):19–20, 2007.
- [2] Guy E. Blelloch, Laxman Dhulipala and Yihan Sun. Introduction to parallel algorithms. https://www.cs.cmu.edu/~guyb/paralg/paralg/parallel.pdf, 2024. [Accessed 22-10-2024].
- [3] Ferrandi Fabrizio. Parallel computing. Slides from the HPC-E master's degree course on Politecnico di Milano, 2024.
- [4] John L Gustafson. Reevaluating Amdahl's law. Communications of the $ACM,\,31(5):532-533,\,1988.$
- [5] Johnston Hans. OpenMP by Example. https://people.math.umass.edu/~johnston/PHI_WG_2014/OpenMPSlides_tamu_sc.pdf, 2024. [Accessed 23-10-2024].
- [6] Vipin Kumar, Ananth Grama, Anshul Gupta, and George Karypis. Introduction to parallel computing, volume 110. Benjamin/Cummings Redwood City, CA, 1994.
- [7] M. McCool, J. Reinders, and A. Robison. Structured Parallel Programming: Patterns for Efficient Computation. ITPro collection. Elsevier Science, 2012.
- [8] Microsoft. The critical directive. https://learn.microsoft.com/en-us/cpp/parallel/openmp/a-examples?view=msvc-170#a5-the-critical-directive, 2024. [Accessed 29-10-2024].
- [9] M. Nemirovsky and D. Tullsen. *Multithreading Architecture*. Synthesis Lectures on Computer Architecture. Springer International Publishing, 2022.
- [10] Wikipedia. Cache (computing) Wikipedia. https://en.wikipedia.org/wiki/Cache_(computing). [Accessed 20-10-2024].

\mathbf{Index}

A	
Amdahl's Law	19
Arbitrary Concurrent Write	6
В	
Barrier Object	49
Block Multithreading	29
C	
Cache	27
Cache Hit	27
Cache Miss Coarse-Grain Multithreading	27 29
Common Concurrent Write	6
Composition Rules	38
Concurrent Read (CR)	6
Concurrent tasks in parallel algorithms	37
Concurrent Write (CW)	6
D	
Data Race	44
Directed Acyclic Graph (DAG)	37
Directed Reyelle Graph (DRG)	91
\mathbf{E}	
Error Check Mutex (PTHREAD_MUTEX_ERRORCHECK)	50
Exclusive Read (ER)	6
Exclusive Write (EW)	6
\mathbf{F}	
Fine-Grain Multithreading (FGMT)	29
Flynn's taxonomy	43
G	
Gustafson's Law	20
-	
I I I I GDMD D G II (IGDG)	90
Implicit SPMD Program Compiler (ISPC)	30
Instruction-Level Parallelism (ILP) Interleaved Multithreading	23 29
Intericaved without meading	23
M	
Machine Model	5
Matrix Multiply (MM) algorithm	15
Matrix-Vector Multiply (MVM) algorithm	9
Memory Access Latency Memory Bandwidth	25
Multi-Core Processor (MCP)	$\begin{array}{c} 26 \\ 24 \end{array}$
Multithreaded Processor	27

	Index
INT	
N Normal Mutex (PTHREAD_MUTEX_NORMAL)	50
O	
OpenMP	51
P	
Parallel Algorithm	35
Parallel Program	35
Parallel Random-Access Machine (parallel RAM or PRAM)	5
Parallel tasks in parallel algorithms	37
Parallelism metrico for parallel algorithms	38
PCAM (Partitioning, Communication, Agglomeration, Mapping)	35
POSIX Threads	44
Prefetching	27
Prefix Sum	14
Priority Concurrent Write	6
Processor Stall	25
R	
Race Condition	44
Random Access Machine (RAM)	5
Random Concurrent Write	6
Recursive Mutex (PTHREAD_MUTEX_RECURSIVE)	50
${f S}$	
Shared Address Space	34
Shared Variables	34
Simultaneous Multithreading (SMT)	29
Single Instruction, Multiple Data (SIMD)	24
Single Program Multiple Data (SPMD)	11
Single Program, Multiple Data (SPMD)	30
Span metric for parallel algorithms	37
SPMD programming model	31
Superscalar Processor	23
Switch-On-Event Multithreading	29
${f T}$	
Temporal Multithreading	29
Thread	43
\mathbf{W}	
Work metric for parallel algorithms	37