



# Parallel and Distributed Software Systems: Lab Session 2 Tutorial: Simulation of data centre management systems using DCSim

December, 2nd 2014 pds@intec.ugent.be

# Objectives of this tutorial:

- · Learn how large-scale data centres are simulated using DCSim
- · Learn how to set up a DCSim project
- Introduction to the DCSim\_vis visualizer

### Before you start:

- In this tutorial and lab session we use the DCSim data centre simulator<sup>1</sup> and the DCSim\_vis visualizer. Both have been packaged as jar files and are available on Minerva.
- To make it easier to create, run and modify simulations, start files have been provided. These files are available on Minerva in the "resource allocation" folder in "lab sessions", and contain DCSim, DCSim\_vis and a pds package containing start code.
- While DCSim is not restricted to one specific IDE, we use Netbeans during the tutorial and lab session.

# 1 Data centres

Data centres contain large numbers of server and network resources, and are used to power many Internet and cloud applications. As the use and complexity of these applications increases, the scale of the data centres in which they are executed must increase as well. This however results in many management challenges, including the cost-efficient use of resources, failure management, quality and security challenges, and energy efficiency.

Modern data centres are generally managed by virtualizing the servers, making it possible to host multiple Virtual Machines (VMs) on a single host. Using VMs has multiple advantages: the application contained in the VM is less dependent on the underlying hardware, multiple VMs can be co-located on a single host, the resources allocated to a VMs can change when the application needs change, and VMs can be migrated to other hosts when the need presents itself.

# 2 DCSim

In recent years, the scale of data centres has increased greatly. Developing and evaluating the algorithms that manage on these large-scale environments by running the algorithms on physical hardware is impossible, because the number of servers needed for a realistic evaluation quickly becomes cost-prohibitive. Therefore, the data centre is typically simulated. This makes it possible to quickly evaluate the performance of algorithms using fewer resources, at the cost of slightly less accurate results. DCSim is an event-based data centre

<sup>1</sup>https://github.com/digs-uwo/dcsim


simulator, which is capable of simulating events within a data centre. The simulator models a collection of hosts within a virtual data centre. VMs are executed on the hosts, and managed by a data centre management system. Various management algorithms, policies, and VM properties can be modified, making it possible to evaluate management algorithms in multiple scenarios.

By default, DCSim models a data centre where multiple applications are deployed. The applications are based on a multi-tier architecture, meaning they consist of multiple interacting VMs. Application workloads are modelled by using utilization traces, which can be selected by the user, and a queuing model is used to determine the duration of request handling. A host energy model is used to model the energy use of hosts, making it possible to determine the energy efficiency of data centre management policies.

## 2.1 DCSim architecture

While not all of its internal workings need to be understood to use DCSim, it is important to understand how hosts, VMs and applications are defined and how they interact.

#### 2.1.1 The data centre



 ${\bf Figure \ 1:} \ {\bf The \ classes \ representing \ the \ data \ centre \ and \ its \ state}.$ 

Figure 1 shows the various classes that are used to represent a data centre using DCSim. VMs represent a single task which is associated with an application, and are executed on hosts. Multiple VMs may be allocated on a single host. VMs are represented using the Vm class. To link a Vm with a Host on which it is deployed a VmAllocation object, representing a VM allocation is used.

The DataCentre class represents a single data centre. The data centre may consist of multiple Clusters that each contain multiple Racks. A rack contains multiple Hosts. Host and data centre management is done using AutonomicManagers. An autonomic manager represents a single agent that makes management decisions, possibly by merely forwarding instructions to other management agents. The actions that a manager executes are determined by selected management policies, that implement a Policy interface. Every host has an associated autonomic manager that is responsible for managing it. Using policies, the management information associated with a host can also be transmitted to a different autonomic manager, e.g. a centralized management node. DCSim provides three pre-implemented policies:

- The HostMonitoringPolicy is responsible for monitoring the status of a host. The policy will then transmit the status to a chosen autonomic manager.
- The HostOperationsPolicy handles basic host operations such as executing migrations and shutting down the host when it is unused.
- The DefaultVmPlacementPolicy uses a simple VM placement algorithm to allocate VM requests on hosts.

The hosts also have associated ResourceManagers and ResourceSchedulers, which can be modified to change how resources are divided between VMs. Additionally, a PowerModel which models the energy use of servers based on their resource use is provided.




Figure 2: A simple data centre configuration illustrating how host autonomic managers and the data centre autonomic manager can work together to manage the data centre.

Figure 2 illustrates how a simple data centre with two hosts using a centralized management system can be configured. The hosts within the data centre execute VMs, and are managed by a local host autonomic manager. This host forwards management state to the a centralized data centre autonomic manager, which is done using the HostMonitoringPolicy. Based on the received information, the data centre autonomic manager can make management decisions, which it forwards back to the host autonomic managers. The host autonomic managers are then responsible for executing the changes, for which the HostOperationsPolicy is used. Once the host state changes, these changes will then be forwarded to back to the data centre autonomic manager by the HostMonitoringPolicy.

### 2.1.2 The applications




Figure 3: The classes representing Applications and VMs.

The way applications are specified in DCSim is depicted in Figure 3. An Application consists of multiple Tasks, that work together to provide the application. Conceptually, these tasks map to application components, such as for example the various tiers in a three tier web application.

Multiple instances of a task may be needed to service all client requests. In this case, a LoadBalancer is used to balance requests between multiple TaskInstances. Every TaskInstance is associated with a Vm. This Vm can then be associated with a physical host as discussed in the previous section.

The Application is an abstract class which defines how applications within the data centre must be defined. DCSim provides a default application implementation which models a multi-tier interactive application. This InteractiveApplication defines multiple tiers, where requests must go from one tier to the next. The number of requests arriving at the first tier is defined using a Workload. A default TraceWorkload which determines the load based on an external trace file is provided.




Figure 4: An illustration of how a multi-tier web application can be modeled in DCSim.

Figure 4 shows how a multi-tier web application is represented in DCSim. The application itself consists of three tasks, one for every application layer. Each of these tasks is provided using one or more VMs that are load balanced. The number of incoming requests is determined by an application workload, which may vary throughout time.

#### 2.1.3 DCSim metrics

After finishing a simulation, the DCSim simulator shows a simulation summary containing the most important measured metrics. Within this tutorial and lab session, we will focus on a limited subset of these parameters:

- The **mean number of active hosts** represents the number of hosts that are, on average, active during the simulated scenario.
- The **total power consumption** represents the energy use of the hosts during the simulated scenario and is shown in kWh.
- The **mean power consumption** measures the average power consumption during the scenario, and is measured in Watt per second.
- The **CPU underprovision** metric returns the average percentage of CPU demand for which there is insufficient capacity. When this occurs, the applications that have fewer resources than needed will perform perform badly.
- The **maximum response time** metric is indicative of how long it takes for a VM to respond to a request during high load.
- The **failed placement** metric counts the number of application placement requests that failed because there was insufficient host capacity for adding them.

# 2.2 Creating a DCSim project

In this section, we will how a DCSim project can be created in Netbeans, and how a small demo scenario can be started. Correctly configuring and implementing DCSim simulation is relatively complex because many components must be included and correctly configured. Therefore, start and helper files are provided on Minerva (dcsim\_startfiles.zip).

- 1. Download the DCSim start files from Minerva, and unzip them on the computer.
- 2. Create a new project in Netbeans by right clicking in the "Projects" panel and selecting "New Project". Select "Java Application" from the "Java" category.




Figure 5: Create a new project.

Choose a project name and uncheck the "Create Main Class" checkbox. Click on "Finish" to create the new project.




Figure 6: Choose a project name and uncheck the "Create Main Class" checkbox.

- 4. Next, add commons-math3-3.0.jar, log4j-1.2.16.jar and dcsim2.jar, as dependencies for the project. These files are stored in the "dcsim" directory of the start files. This can be done by right-clicking on the "Libraries" drop-down in the "Projects" panel and selecting "Add JAR/Folder...", and then navigating to these start files on the hard disk.
- 5. Next, copy the "config" and "traces" directories from the "dcsim" folder in the start files to the project folder as illustrated in Figure 7. This can be done by selecting and copying the files in a file manager and pasting them in the Netbeans window. Note that the folders must end up next to the "src" directory of the project and not in it, meaning the "Files" panel which shows all project files must be used.



Figure 7: Copying the "config" and "traces" directory to the Netbeans project. This should be done using the "Files" panel in Netbeans.

- 6. Afterwards, copy the "pds" directory from the "dcsim" directory in the start files to the "src" directory in Netbeans.
- 7. After this, all of the DCSim dependencies have been added, and a simulation can be started. The project should look like the one shown in below.




Figure 8: The project after adding the DCSim libraries and the config, traces and pds folders.

# 2.3 Running a simulation

#### 2.3.1 Running a first simulation

Once the Netbeans project has been created and all the DCSim dependencies have been added, it is possible to start simulations. A simple simulation can be started by right-clicking the SimpleRunner.java class and selecting "Run File". After a short duration, the simulation report containing various metrics is printed on the console:

```
INFO
         \verb"edu.uwo.csd.dcsim.core.Simulation"
                                                        - Starting DCSim
                                                        - Random Seed: -5217230306070299805
   INFO
         edu.uwo.csd.dcsim.core.Simulation
   INFO edu.uwo.csd.dcsim.core.Simulation
   INFO edu.uwo.csd.dcsim.core.Simulation
                                                        \hbox{- Completed simulation dynamic-service-spawn-simple VmPlacement Policy}
   INFO pds.SimpleRunner
   INFO pds.SimpleRunner
                                                        - Active Hosts
                                                            max: 10.0
   INFO pds.SimpleRunner
   INFO pds.SimpleRunner
                                                            mean: 9.943
                                                            min: 0.0
10
   INFO pds.SimpleRunner
                                                            util: 32.195%
   INFO pds.SimpleRunner
11
12
   INFO pds.SimpleRunner
                                                             total util: 32.011%
   INFO
         pds.SimpleRunner
                                                            consumed: 212.317kWh
   INFO pds.SimpleRunner
15
   INFO pds.SimpleRunner
                                                            max: 2161.566Ws
   INFO pds.SimpleRunner
                                                            mean: 1769.306Ws
16
   INFO pds.SimpleRunner
                                                            min: 0.0Ws
17
   INFO pds.SimpleRunner
                                                            efficiency: 0.0cpu/watt
18
   INFO
        pds.SimpleRunner
   INFO
         pds.SimpleRunner
                                                        - -- APPLICATIONS --
                                                        - CPU Underprovision
21
   INFO
         pds.SimpleRunner
22
   INFO
         pds.SimpleRunner
                                                            percentage: 0.0%
                                                        - SLA
         pds.SimpleRunner
23
   INFO
24
   INFO pds.SimpleRunner
                                                           aggregate penalty
   INFO pds.SimpleRunner
   INFO pds.SimpleRunner
                                                             max: 0.0
^{27}
   INFO
         pds.SimpleRunner
                                                             mean: 0.0
28
   INFO pds.SimpleRunner
                                                             min: 0.0
                                                            per application penalty
   INFO pds.SimpleRunner
29
   INFO pds.SimpleRunner
30
                                                             mean: 0.0
31
   INFO pds.SimpleRunner
   INFO
         pds.SimpleRunner
                                                             max: 0.0
33
   INFO pds.SimpleRunner
                                                             95th: 0.0
34
   INFO
         pds.SimpleRunner
                                                             75th: 0.0
                                                             50th: 0.0
   INFO pds.SimpleRunner
35
   INFO pds.SimpleRunner
                                                             25th: 0.0
36
   INFO
         pds.SimpleRunner
                                                             min: 0.0
37
   INFO
         pds.SimpleRunner
                                                        - Response Time
38
39
   INFO
         pds.SimpleRunner
                                                             max: 0.003
40
   INFO pds.SimpleRunner
                                                             mean: 0.0
41
   INFO pds.SimpleRunner
                                                             min: 0.0
                                                        - Throughput
   INFO
         pds.SimpleRunner
42
   INFO pds.SimpleRunner
                                                            max: 598.656
43
   INFO
         pds.SimpleRunner
                                                             mean: 0.0
   INFO
         pds.SimpleRunner
                                                             min: 141.625
                                                        - Spawning
46
   TNFO
         pds.SimpleRunner
                                                            spawned: 220
47
   INFO pds.SimpleRunner
   INFO pds.SimpleRunner
                                                            shutdown: 46
48
   INFO
49
         pds.SimpleRunner
                                                            failed placement: 16
   INFO
                                                        - Interactive Application Model Algorithm:
         pds.SimpleRunner
                                                        - Schweitzers MVA Approximation
51
   INFO
         pds.SimpleRunner
52
   INFO pds.SimpleRunner
                                                           - MANAGEMENT -
53
   INFO
         pds.SimpleRunner
                                                        - Messages
54
   INFO
         pds.SimpleRunner
   INFO pds.SimpleRunner
                                                             edu.uwo.csd.dcsim.management.events.HostStatusEvent: 14325
55
56
   INFO pds.SimpleRunner
                                                        - Message BW
   INFO
         pds.SimpleRunner
                                                             edu.uwo.csd.dcsim.management.events.HostStatusEvent: 0.0
                                                        - Migrations
58
   INFO
         pds.SimpleRunner
59
   INFO pds.SimpleRunner
                                                        - -- SIMULATION --
60
   INFO
         pds.SimpleRunner
   INFO
         pds.SimpleRunner
                                                            execution time: 9.0s
61
   INFO
         pds.SimpleRunner
                                                            simulated time: 5.0 days
62
   INFO
         pds.SimpleRunner
                                                            metric recording start: Oms
   INFO
         pds.SimpleRunner
                                                            metric recording duration: 5.0 days
65
   TNFO
         pds.SimpleRunner
                                                            application scheduling timed out: 0
   BUILD SUCCESSFUL (total time: 9 seconds)
```

## 2.3.2 The SimpleRunner class

The code of the SimpleRunner class is shown below. We will now briefly explain the how the simulation was set up and configured.

```
public class SimpleRunner {
    private static Logger logger = Logger.getLogger(SimpleRunner.class);
3
    public static void main(String args[]) {
4
      Simulation.initializeLogging();
5
6
      SimulationTask task = new DynamicServiceSpawning(
          "dynamic-service-spawn-simpleVmPlacementPolicy",
          -52172303060702998051,
          10,
10
          "traces/clarknet",
11
          new DynamicServiceSpawning.PolicyInstaller() {
12
            public void installDatacentrePolicies(AutonomicManager dcAM){
13
              dcAM.installPolicy(new VmPlacementPolicy(new FirstFitVmPlacementAlgorithm()));
14
            }
15
          }
16
          );
17
18
19
      task.run();
20
21
       task.getMetrics().printDefault(logger);
22
    }
  }
23
```

- Lines 2 and 5 initialize the logging system which is used for printing out simulation results.
- A SimulationTask of the type DynamicServiceSpawning is instantiated on Line 7. This is a helper class
  defined in the pds.helper package which creates and configures a data centre, and creates a simple
  scenario where a large collection of single-task applications are generated, deployed and removed over
  time. A host autonomic manager that forwards requests to a centralized data centre autonomic manager
  is installed on every host, making it possible to change data centre policies by modifying the configuration
  of the data centre autonomic manager. The arguments for instantiating the DynamicServiceSpawning
  object are the following:
  - A name for the simulation (Line 8), which is printed in the simulation output and which is used to name trace and log files associated with the simulation.
  - A seed for the random generator used in the simulator. This seed is used to create the random generator, and ensures it always results in the same sequence of random numbers. This makes it possible to run the simulation multiple times using the same seed, resulting in an identical scenario (same arrival time, start and stop time, and load for applications) for multiple executions (Line 9).
  - The number of hosts in the simulated data centre (Line 10).
  - The data centre trace used to model the workload of the simulated VMs (Line 11). In this lab session
    we use the ClarckNet trace, which records two weeks of HTTP logs from an Internet access provider.
    This trace is stored in the "traces" folder within the project.
  - A policy installer instance which installs policies on the data centre autonomic manager once it is created.
- A VM placement policy is installed in the data centre on Line 14. This policy is used to determine on which host new VMs are allocated. In this example, a FirstFitVmPlacementAlgorithm is used which allocates VMs on the first host it can find with sufficient resource capacity. The FirstFitVmPlacementAlgorithm must be wrapped in a DefaultVmPlacementPolicy helper object which does the heavy lifting when it comes to aggregating host load information and executing the changes which are computed by the placement algorithm. Both the DefaultVmPlacementPolicy and FirstFitVmPlacementAlgorithm are defined in the pds.vmplacementpolicies package.
- The task is started on Line 19, using the run() method.
- Finally, the results of the simulation are printed on Line 21, resulting in the console output shown above.

# 2.4 Visualizing a simulation

While having a simulation summary showing statistics for various metrics is useful, it is hard to observe what is happening within the data centre during the simulation. This makes it thard to interpret and debug unexpected results. The DCSim\_vis tool can be used in conjunction with DCSim to visualize the execution results of a simulation based on a provided trace file. This trace file must be generated during the execution of a simulation, and can afterwards be inspected using DCSim\_vis. We provide a custom build of the DCSim\_vis tool, provided as dcsim\_vis.jar in the start files, which provides both a textual and visual interface. The runner allows the user to select a trace file, and generates the necessary files. The visualizer itself is implemented as a locally executed web site, which the dcsim\_vis.jar runner automatically opens in Firefox. Firefox must therefore be installed for the visualizer to run correctly.

## 2.4.1 Starting the visualizer

1. To be able to visualize a simulation, a detailed trace must be generated during the simulation. As these traces require much disk space they are disabled by default. To enable them, the "simulation.properties" file in the "config" directory should be edited<sup>2</sup>. The line "enableTrace=false" should be modified and replaced by the line "enableTrace=true".

```
#logging
detailedConsole=false
enableConsoleLogFile=false
enableSimulationLogFile=true
enableTrace=true
```

Figure 9: The enableTrace parameter must be set to "true" in the simulation.properties file.

- 2. Run SimpleRunner again. Now that trace files have been enabled, a new file with the .trace extension will be created within the log folder in the project folder. Navigate to this file using the file explorer and note down the full path of the trace file. In this example, /home/username/NetBeansProjects/DCSim/log/SimpleRunner-2014\_11\_06-16\_41\_04.trace was created.
- 3. Next, run the dcsim\_vis.jar file, and select the trace file in the shown file manager.




Figure 10: Select the trace file.

- 4. The trace file will now be processed automatically. Once the processing has finished, a Firefox window containing DCSim\_vis should be shown. It may be necessary to resize the window to correctly see its contents.
- 5. If Firefox is not started automatically, navigate to the folder containing the trace file, and enter the newly created folder (it has the same name as the trace file, but the ".trace" extension is removed). From this folder navigate to the "html/Animation/" directory, and open "HostsMainAnimation.htm".

<sup>&</sup>lt;sup>2</sup>The config directory is present in the project directory, and not in the src directory, and will therefore not show up in the "projects" panel in Netbeans. By switching to the "Files" panel these files can be accessed.

Alternatively, the command line interface of dcsim\_vis.jar may be used:

- 1. Open a terminal window and navigate to the folder in the start files containing the dcsim\_vis.jar file.
- 2. Execute the command "java -jar dcsim\_vis.jar" with as argument the full path to the trace file.

```
$ java -jar dcsim_vis.jar /home/username/NetBeansProjects/DCSim/log/SimpleRunner-2014_11_06-16
       _41_04.trace
  Parsing
2
  Closed all Writers....
  Wrote capacities....
  Wrote VMs Details events....
  Wrote VMs events per hosts events ....
  Wrote VMs Stats per host....
  VMs Iteration: 01
  DONE!
  Parsing DONE
10
  Unzipping web files
11
12 html/
13 html/Hosts/
source/img/glyphicons-halflings-white.png
16 Start.html
Unzipping web files DONE
18 Starting Firefox
19 Starting Firefox DONE
```

- 3. The script will then generate the visualization data, and start a new window containing DCSim\_vis. It may be necessary to resize the window to correctly see its contents.
- 4. If Firefox is not started automatically, navigate to the folder containing the trace file, and enter the newly created folder (it has the same name as the trace file, but the ".trace" extension is removed). From this folder navigate to the "html/Animation/" directory, and open "HostsMainAnimation.htm".




Figure 11: The main DCSim\_vis window.

## 2.4.2 Using the visualizer

Once DCSim\_vis starts, it is possible to view the state the simulation had throughout its execution. The playback can be controlled using the controls at the top of the window. The most important controls are listed here:

- 1. Play starts playing the simulation.
- 2. Pause pauses the simulation playback.
- 3. Reverse rewinds the simulation.
- 4. **Restart** stops the playback of the simulation and starts again from the beginning.
- 5. The dropdown box, initially showing **Tx1** shows the time multiplier. By default DCSim\_vis shows the simulation in real-time: one second within the simulation corresponds to one second in the visualizer. As the SimpleRunner simulates 5 days, it is best to increase this multiplier to a much larger value such as **Tx1000**.




Figure 12: Fast-forwarding in DCSim\_vis.

Playing back the simulation, DCSim\_vis shows when and where VMs are allocated. Additionally, the load of the various resources of the hosts is shown in different colours.




Figure 13: DCSim\_vis showing the allocation of VMs on a collection of hosts.

When the resources of a host are greyed out, this shows that the host has been turned off, meaning it is not using any power. If a host resource type is underutilized, it is shown in yellow. When a host resource is over-utilized, it is shown in red. Finally, when a host has high utilization, without being over-utilized, it is shown in green. The various considered resource types are, in the order shown in DCSim\_vis: CPU load, memory usage, bandwidth usage, storage power and serve power utilization.