Chapter 5

Scheduling

Any operating system is likely to run with more processes than the computer has processors, so a plan is needed to time-share the processors among the processes. Ideally the sharing would be transparent to user processes. A common approach is to provide each process with the illusion that it has its own virtual processor by *multiplexing* the processes onto the hardware processors. This chapter explains how xv6 achieves this multiplexing.

Multiplexing

Xv6 multiplexes by switching each processor from one process to another in two situations. First, xv6's sleep and wakeup mechanism switches when a process waits for device or pipe I/O to complete, or waits for a child to exit, or waits in the sleep system call. Second, xv6 periodically forces a switch when a process is executing user instructions. This multiplexing creates the illusion that each process has its own CPU, just as xv6 uses the memory allocator and hardware page tables to create the illusion that each process has its own memory.

Implementing multiplexing poses a few challenges. First, how to switch from one process to another? Although the idea of context switching is simple, the implementation is some of the most opaque code in xv6. Second, how to switch transparently to user processes? Xv6 uses the standard technique of driving context switches with timer interrupts. Third, many CPUs may be switching among processes concurrently, and a locking plan is necessary to avoid races. Fourth, a process's memory and other resources must be freed when the process exits, but it cannot do all of this itself because (for example) it can't free its own kernel stack while still using it. Finally, each core of a multi-core machine must remember which process it is executing so that system calls affect the correct process's kernel state. Xv6 tries to solve these problems as simply as possible, but nevertheless the resulting code is tricky.

xv6 must provide ways for processes to coordinate among themselves. For example, a parent process may need to wait for one of its children to exit, or a process reading a pipe may need to wait for some other process to write the pipe. Rather than make the waiting process waste CPU by repeatedly checking whether the desired event has happened, xv6 allows a process to give up the CPU and sleep waiting for an event, and allows another process to wake the first process up. Care is needed to avoid races that result in the loss of event notifications. As an example of these problems and their solution, this chapter examines the implementation of pipes.

Code: Context switching



Kernel

Figure 5-1. Switching from one user process to another. In this example, xv6 runs with one CPU (and thus one scheduler thread).

Figure 5-1 outlines the steps involved in switching from one user process to another: a user-kernel transition (system call or interrupt) to the old process's kernel thread, a context switch to the current CPU's scheduler thread, a context switch to a new process's kernel thread, and a trap return to the user-level process. The xv6 scheduler has its own thread (saved registers and stack) because it is sometimes not safe for it execute on any process's kernel stack; we'll see an example in exit. In this section we'll examine the mechanics of switching between a kernel thread and a scheduler thread.

swtch+code
contexts
struct context+code
trap+code
yield+code
sched+code
swtch+code
cpu>scheduler+code
swtch+code

Switching from one thread to another involves saving the old thread's CPU registers, and restoring the previously-saved registers of the new thread; the fact that %esp and %eip are saved and restored means that the CPU will switch stacks and switch what code it is executing.

The function swtch performs the saves and restores for a thread switch. swtch doesn't directly know about threads; it just saves and restores register sets, called *contexts*. When it is time for a process to give up the CPU, the process's kernel thread calls swtch to save its own context and return to the scheduler context. Each context is represented by a struct context*, a pointer to a structure stored on the kernel stack involved. Swtch takes two arguments: struct context **old and struct context *new. It pushes the current registers onto the stack and saves the stack pointer in *old. Then swtch copies new to %esp, pops previously saved registers, and returns.

Let's follow a user process through swtch into the scheduler. We saw in Chapter 3 that one possibility at the end of each interrupt is that trap calls yield. Yield in turn calls sched, which calls swtch to save the current context in proc->context and switch to the scheduler context previously saved in cpu->scheduler (2822).

Swtch (3052) starts by copying its arguments from the stack to the caller-saved registers %eax and %edx (3060-3061); swtch must do this before it changes the stack pointer and can no longer access the arguments via %esp. Then swtch pushes the register state, creating a context structure on the current stack. Only the callee-saved registers need to be saved; the convention on the x86 is that these are %ebp, %ebx, %esi,

%edi, and %esp. Swtch pushes the first four explicitly (3064-3067); it saves the last implicitly as the struct context* written to *old (3070). There is one more important register: the program counter %eip. It has already been saved on the stack by the call instruction that invoked swtch. Having saved the old context, swtch is ready to restore the new one. It moves the pointer to the new context into the stack pointer (3071). The new stack has the same form as the old one that swtch just left—the new stack was the old one in a previous call to swtch—so swtch can invert the sequence to restore the new context. It pops the values for %edi, %esi, %ebx, and %ebp and then returns (3074-3078). Because swtch has changed the stack pointer, the values restored and the instruction address returned to are the ones from the new context.

In our example, sched called swtch to switch to cpu->scheduler, the per-CPU scheduler context. That context had been saved by scheduler's call to swtch (2781). When the swtch we have been tracing returns, it returns not to sched but to scheduler, and its stack pointer points at the current CPU's scheduler stack.

swtch+code sched+code swtch+code cpu-

>scheduler+code swtch+code scheduler+code swtch+code ptable.lock+code sched+code sleep+code exit+code sched+code swtch+code cpu-

>scheduler+code scheduler+code ptable.lock+code swtch+code ptable.lock+code swtch+code yield+code

Code: Scheduling

The last section looked at the low-level details of swtch; now let's take swtch as a given and examine switching from a process through the scheduler to another process. A process that wants to give up the CPU must acquire the process table lock ptable.lock, release any other locks it is holding, update its own state (proc->state), and then call sched. Yield (2828) follows this convention, as do sleep and exit, which we will examine later. Sched double-checks those conditions (2813-2818) and then an implication of those conditions: since a lock is held, the CPU should be running with interrupts disabled. Finally, sched calls swtch to save the current context in proc->context and switch to the scheduler context in cpu->scheduler. Swtch returns on the scheduler's stack as though scheduler's swtch had returned (2781). The scheduler continues the for loop, finds a process to run, switches to it, and the cycle repeats.

We just saw that xv6 holds ptable.lock across calls to swtch: the caller of swtch must already hold the lock, and control of the lock passes to the switched-to code. This convention is unusual with locks; usually the thread that acquires a lock is also responsible for releasing the lock, which makes it easier to reason about correctness. For context switching it is necessary to break this convention because ptable.lock protects invariants on the process's state and context fields that are not true while executing in swtch. One example of a problem that could arise if ptable.lock were not held during swtch: a different CPU might decide to run the process after yield had set its state to RUNNABLE, but before swtch caused it to stop using its own kernel stack. The result would be two CPUs running on the same stack, which cannot be right.

A kernel thread always gives up its processor in sched and always switches to the same location in the scheduler, which (almost) always switches to some kernel thread that previously called sched. Thus, if one were to print out the line numbers where xv6 switches threads, one would observe the following simple pattern: (2781), (2822), (2781), (2822), and so on. The procedures in which this stylized switching between two

threads happens are sometimes referred to as *coroutines*; in this example, sched and scheduler are co-routines of each other.

There is one case when the scheduler's call to swtch does not end up in sched. We saw this case in Chapter 2: when a new process is first scheduled, it begins at forkret (2853). Forkret exists to release the ptable.lock; otherwise, the new process could start at trapret.

Scheduler (2758) runs a simple loop: find a process to run, run it until it yields, repeat. scheduler holds ptable.lock for most of its actions, but releases the lock (and explicitly enables interrupts) once in each iteration of its outer loop. This is important for the special case in which this CPU is idle (can find no RUNNABLE process). If an idling scheduler looped with the lock continuously held, no other CPU that was running a process could ever perform a context switch or any process-related system scheduler-call, and in particular could never mark a process as RUNNABLE so as to break the idling CPU out of its scheduling loop. The reason to enable interrupts periodically on an idling CPU is that there might be no RUNNABLE process because processes (e.g., the shell) are waiting for I/O; if the scheduler left interrupts disabled all the time, the I/O wait+code would never arrive.

The scheduler loops over the process table looking for a runnable process, one that has p->state == RUNNABLE. Once it finds a process, it sets the per-CPU current process variable proc, switches to the process's page table with switchuvm, marks the process as RUNNING, and then calls swtch to start running it (2774-2781).

One way to think about the structure of the scheduling code is that it arranges to enforce a set of invariants about each process, and holds ptable.lock whenever those invariants are not true. One invariant is that if a process is RUNNING, a timer interrupt's yield must be able to switch away from the process; this means that the CPU registers must hold the process's register values (i.e. they aren't actually in a context), %cr3 must refer to the process's pagetable, %esp must refer to the process's kernel stack so that swtch can push registers correctly, and proc must refer to the process's proc[] slot. Another invariant is that if a process is RUNNABLE, an idle CPU's scheduler must be able to run it; this means that p->context must hold the process's kernel thread variables, that no CPU is executing on the process's kernel stack, that no CPU's %cr3 refers to the process's page table, and that no CPU's proc refers to the process.

Maintaining the above invariants is the reason why xv6 acquires ptable.lock in one thread (often in yield) and releases the lock in a different thread (the scheduler thread or another next kernel thread). Once the code has started to modify a running process's state to make it RUNNABLE, it must hold the lock until it has finished restoring the invariants: the earliest correct release point is after scheduler stops using the process's page table and clears proc. Similarly, once scheduler starts to convert a runnable process to RUNNING, the lock cannot be released until the kernel thread is completely running (after the swtch, e.g. in yield).

ptable.lock protects other things as well: allocation of process IDs and free process table slots, the interplay between exit and wait, the machinery to avoid lost wakeups (see next section), and probably other things too. It might be worth thinking about whether the different functions of ptable.lock could be split up, certainly for clarity and perhaps for performance.

coroutines sched+code scheduler+code swtch+code sched+code forkret+code ptable.lock+code scheduler+code ptable.lock+code RUNNABLE+code switchuvm+code swtch+code ptable.lock+code yield+code RUNNABLE+code scheduler+code p->context+code ptable.lock+code ptable.lock+code wait+code

Code: mycpu and myproc

struct cpu+code mycpu+code myproc+code sequence coordination conditional synchronization

xv6 maintains a struct cpu for each processor, which records the process currently running on the processor (if any), the processor's unique hardware identifier (apicid), and some other information. The function mycpu (2437) returns the current processor's struct cpu. mycpu does this by reading the processor identifier from the local APIC hardware and looking through the array of struct cpu for an entry with that identifier. The return value of mycpu is fragile: if the timer were to interrupt and cause the thread to be moved to a different processor, the return value would no longer be correct. To avoid this problem, xv6 requires that callers of mycpu disable interrupts, and only enable them after they finish using the returned struct cpu.

The function myproc (2457) returns the struct proc pointer for the process that is running on the current processor. myproc disables interrupts, invokes mycpu, fetches the current process pointer (c->proc) out of the struct cpu, and then enables interrupts. If there is no process running, because the the caller is executing in scheduler, myproc returns zero. The return value of myproc is safe to use even if interrupts are enabled: if a timer interrupt moves the calling process to a different processor, its struct proc pointer will stay the same.

Sleep and wakeup

Scheduling and locks help conceal the existence of one process from another, but so far we have no abstractions that help processes intentionally interact. Sleep and wakeup fill that void, allowing one process to sleep waiting for an event and another process to wake it up once the event has happened. Sleep and wakeup are often called *sequence coordination* or *conditional synchronization* mechanisms, and there are many other similar mechanisms in the operating systems literature.

To illustrate what we mean, let's consider a simple producer/consumer queue. This queue is similar to the one that feeds commands from processes to the IDE driver (see Chapter 3), but abstracts away all IDE-specific code. The queue allows one process to send a nonzero pointer to another process. If there were only one sender and one receiver, and they executed on different CPUs, and the compiler didn't optimize too agressively, this implementation would be correct:

```
100
        struct q {
101
           void *ptr;
102
        };
103
104
105
        send(struct q *q, void *p)
106
107
           while(q->ptr != 0)
108
109
           q \rightarrow ptr = p;
110
111
```

```
void*
112
113
        recv(struct q *q)
114
115
          void *p;
116
117
          while((p = q->ptr) == 0)
118
119
          q->ptr = 0;
120
          return p;
121
```

busy waiting polling sleep+code wakeup+code chan+code wait channel

Send loops until the queue is empty (ptr == 0) and then puts the pointer p in the queue. Recv loops until the queue is non-empty and takes the pointer out. When run in different processes, send and recv both modify q->ptr, but send only writes the pointer when it is zero and recv only writes the pointer when it is nonzero, so no updates are lost.

The implementation above is expensive. If the sender sends rarely, the receiver will spend most of its time spinning in the while loop hoping for a pointer. The receiver's CPU could find more productive work than *busy waiting* by repeatedly *polling* q->ptr. Avoiding busy waiting requires a way for the receiver to yield the CPU and resume only when send delivers a pointer.

Let's imagine a pair of calls, sleep and wakeup, that work as follows. Sleep(chan) sleeps on the arbitrary value chan, called the *wait channel*. Sleep puts the calling process to sleep, releasing the CPU for other work. Wakeup(chan) wakes all processes sleeping on chan (if any), causing their sleep calls to return. If no processes are waiting on chan, wakeup does nothing. We can change the queue implementation to use sleep and wakeup:

```
201
        void*
202
        send(struct q *q, void *p)
203
204
          while(q->ptr != 0)
205
206
          q \rightarrow ptr = p;
          wakeup(q); /* wake recv */
207
208
209
210
        void*
211
        recv(struct q *q)
212
213
          void *p;
214
          while((p = q->ptr) == 0)
215
216
            sleep(q);
217
          q->ptr = 0;
218
          return p;
219
        }
```

Recv now gives up the CPU instead of spinning, which is nice. However, it turns out not to be straightforward to design sleep and wakeup with this interface without suffering from what is known as the "lost wake-up" problem (see Figure 5-2). Suppose that recv finds that q->ptr == 0 on line 215. While recv is between lines 215 and




Figure 5-2. Example lost wakeup problem

216, send runs on another CPU: it changes q->ptr to be nonzero and calls wakeup, which finds no processes sleeping and thus does nothing. Now recv continues executing at line 216: it calls sleep and goes to sleep. This causes a problem: recv is asleep waiting for a pointer that has already arrived. The next send will wait for recv to consume the pointer in the queue, at which point the system will be *deadlocked*.

The root of this problem is that the invariant that recv only sleeps when q->ptr == 0 is violated by send running at just the wrong moment. One incorrect way of protecting the invariant would be to modify the code for recv as follows:

```
300
        struct q {
301
          struct spinlock lock;
302
          void *ptr;
303
        }:
304
305
306
        send(struct q *q, void *p)
307
308
          acquire(&q->lock);
          while(q->ptr != 0)
309
310
311
          q->ptr = p;
312
          wakeup(q);
313
          release(&q->lock);
314
        }
315
316
        void*
317
        recv(struct q *q)
318
319
          void *p;
320
          acquire(&q->lock);
321
322
          while((p = q->ptr) == 0)
323
            sleep(q);
324
          q->ptr = 0;
325
          release(&q->lock);
326
          return p;
327
```

One might hope that this version of recv would avoid the lost wakeup because the

deadlocked

lock prevents send from executing between lines 322 and 323. It does that, but it also deadlocks: recv holds the lock while it sleeps, so the sender will block forever waiting for the lock.

sleep+code sleep+code wakeup+code SLEEPING+code sched+code RUNNABLE+code

We'll fix the preceding scheme by changing sleep's interface: the caller must pass the lock to sleep so it can release the lock after the calling process is marked as asleep and waiting on the sleep channel. The lock will force a concurrent send to wait until the receiver has finished putting itself to sleep, so that the wakeup will find the sleeping receiver and wake it up. Once the receiver is awake again sleep reacquires the lock before returning. Our new correct scheme is useable as follows:

```
400
        struct q {
401
          struct spinlock lock;
402
          void *ptr;
403
        };
404
405
        void*
406
        send(struct q *q, void *p)
407
408
          acquire(&q->lock);
409
          while(q->ptr != 0)
410
411
          q->ptr = p;
412
          wakeup(q);
413
          release(&q->lock);
414
        }
415
        void*
416
417
        recv(struct q *q)
418
419
          void *p;
420
421
          acquire(&q->lock);
          while((p = q->ptr) == 0)
422
423
            sleep(q, &q->lock);
424
          q \rightarrow ptr = 0;
425
          release(&q->lock);
426
          return p;
427
```

The fact that recv holds q->lock prevents send from trying to wake it up between recv's check of q->ptr and its call to sleep. We need sleep to atomically release q->lock and put the receiving process to sleep.

A complete sender/receiver implementation would also sleep in send when waiting for a receiver to consume the value from a previous send.

Code: Sleep and wakeup

Let's look at the implementation of sleep (2874) and wakeup (2953). The basic idea is to have sleep mark the current process as SLEEPING and then call sched to release the processor; wakeup looks for a process sleeping on the given wait channel and marks it as RUNNABLE. Callers of sleep and wakeup can use any mutually convenient

number as the channel. Xv6 often uses the address of a kernel data structure involved ptable.lock+code in the waiting.

Sleep (2874) begins with a few sanity checks: there must be a current process ptable.lock+code (2878) and sleep must have been passed a lock (2881-2882). Then sleep acquires ptable.lock (2891). Now the process going to sleep holds both ptable.lock and lk. Holding 1k was necessary in the caller (in the example, recv): it ensured that no other chan+code process (in the example, one running send) could start a call to wakeup(chan). Now that sleep holds ptable.lock, it is safe to release lk: some other process may start a call to wakeup(chan), but wakeup will not run until it can acquire ptable.lock, so it must wait until sleep has finished putting the process to sleep, keeping the wakeup from missing the sleep.

wakeup+code ptable.lock+code wakeup1+code wakeup+code SLEEPING+code RUNNABLE+code

There is a minor complication: if 1k is equal to &ptable.lock, then sleep would deadlock trying to acquire it as &ptable.lock and then release it as lk. In this case, sleep considers the acquire and release to cancel each other out and skips them entirely (2890). For example, wait (2964) calls sleep with &ptable.lock.

Now that sleep holds ptable.lock and no others, it can put the process to sleep by recording the sleep channel, changing the process state, and calling sched (2895-2898).

At some point later, a process will call wakeup (chan). Wakeup (2964) acquires ptable.lock and calls wakeup1, which does the real work. It is important that wakeup hold the ptable.lock both because it is manipulating process states and because, as we just saw, ptable.lock makes sure that sleep and wakeup do not miss each other. Wakeup1 is a separate function because sometimes the scheduler needs to execute a wakeup when it already holds the ptable.lock; we will see an example of this later. Wakeup1 (2953) loops over the process table. When it finds a process in state SLEEPING with a matching chan, it changes that process's state to RUNNABLE. The next time the scheduler runs, it will see that the process is ready to be run.

Xv6 code always calls wakeup while holding the lock that guards the sleep condition; in the example above that lock is q->lock. Strictly speaking it is sufficient if wakeup always follows the acquire (that is, one could call wakeup after the release). Why do the locking rules for sleep and wakeup ensure a sleeping process won't miss a wakeup it needs? The sleeping process holds either the lock on the condition or the ptable.lock or both from a point before it checks the condition to a point after it is marked as sleeping. If a concurrent thread causes the condition to be true, that thread must either hold the lock on the condition before the sleeping thread acquired it, or after the sleeping thread released it in sleep. If before, the sleeping thread must have seen the new condition value, and decided to sleep anyway, so it doesn't matter if it misses the wakeup. If after, then the earliest the waker could acquire the lock on the condition is after sleep acquires ptable.lock, so that wakeup's acquisition of ptable.lock must wait until sleep has completely finished putting the sleeper to sleep. Then wakeup will see the sleeping process and wake it up (unless something else wakes it up first).

It is sometimes the case that multiple processes are sleeping on the same channel; for example, more than one process reading from a pipe. A single call to wakeup will wake them all up. One of them will run first and acquire the lock that sleep was called with, and (in the case of pipes) read whatever data is waiting in the pipe. The

other processes will find that, despite being woken up, there is no data to be read. pipewrite+code From their point of view the wakeup was "spurious," and they must sleep again. For piperead+code struct pipe+code this reason sleep is always called inside a loop that checks the condition.

RUNNABLE+code

No harm is done if two uses of sleep/wakeup accidentally choose the same channel: they will see spurious wakeups, but looping as described above will tolerate this problem. Much of the charm of sleep/wakeup is that it is both lightweight (no need to create special data structures to act as sleep channels) and provides a layer of indirection (callers need not know which specific process they are interacting with).

Code: Pipes

The simple queue we used earlier in this chapter was a toy, but xv6 contains two real queues that use sleep and wakeup to synchronize readers and writers. One is in the IDE driver: a process adds a disk request to a queue and then calls sleep. The IDE interrupt handler uses wakeup to alert the process that its request has completed.

A more complex example is the implementation of pipes. We saw the interface for pipes in Chapter 0: bytes written to one end of a pipe are copied in an in-kernel buffer and then can be read out of the other end of the pipe. Future chapters will examine the file descriptor support surrounding pipes, but let's look now at the implementations of pipewrite and piperead.

Each pipe is represented by a struct pipe, which contains a lock and a data buffer. The fields nread and nwrite count the number of bytes read from and written to the buffer. The buffer wraps around: the next byte written after buf[PIPESIZE-1] is buf[0]. The counts do not wrap. This convention lets the implementation distinguish a full buffer (nwrite == nread+PIPESIZE) from an empty buffer (nwrite == nread), but it means that indexing into the buffer must use buf[nread % PIPESIZE] instead of just buf[nread] (and similarly for nwrite). Let's suppose that calls to piperead and pipewrite happen simultaneously on two different CPUs.

Pipewrite (6830) begins by acquiring the pipe's lock, which protects the counts, the data, and their associated invariants. Piperead (6851) then tries to acquire the lock too, but cannot. It spins in acquire (1574) waiting for the lock. While piperead waits, pipewrite loops over the bytes being written—addr[0], addr[1], ..., addr[n-1]—adding each to the pipe in turn (6844). During this loop, it could happen that the buffer fills (6836). In this case, pipewrite calls wakeup to alert any sleeping readers to the fact that there is data waiting in the buffer and then sleeps on &p->nwrite to wait for a reader to take some bytes out of the buffer. Sleep releases p->lock as part of putting pipewrite's process to sleep.

Now that p->lock is available, piperead manages to acquire it and enters its critical section: it finds that p->nread != p->nwrite (6856) (pipewrite went to sleep because p->nwrite == p->nread+PIPESIZE (6836)) so it falls through to the for loop, copies data out of the pipe (6863-6867), and increments nread by the number of bytes copied. That many bytes are now available for writing, so piperead calls wakeup (6868) to wake any sleeping writers before it returns to its caller. Wakeup finds a process sleeping on &p->nwrite, the process that was running pipewrite but stopped when the buffer filled. It marks that process as RUNNABLE.

The pipe code uses separate sleep channels for reader and writer (p->nread and wait+code p->nwrite); this might make the system more efficient in the unlikely event that there are lots of readers and writers waiting for the same pipe. The pipe code sleeps inside exit+code a loop checking the sleep condition; if there are multiple readers or writers, all but the first process to wake up will see the condition is still false and sleep again.

ZOMBIE+code struct proc+code sched+code p->kstack+code p->pgdir+code swtch+code

Code: Wait, exit, and kill

Sleep and wakeup can be used for many kinds of waiting. An interesting example, seen in Chapter 0, is the wait system call that a parent process uses to wait for a child to exit. When a child exits, it does not die immediately. Instead, it switches to the ZOMBIE process state until the parent calls wait to learn of the exit. The parent is then responsible for freeing the memory associated with the process and preparing the struct proc for reuse. If the parent exits before the child, the init process adopts the child and waits for it, so that every child has a parent to clean up after it.

An implementation challenge is the possibility of races between parent and child wait and exit, as well as exit and exit. Wait begins by acquiring ptable.lock. Then it scans the process table looking for children. If wait finds that the current process has children but that none have exited, it calls sleep to wait for one of them to exit (2707) and scans again. Here, the lock being released in sleep is ptable.lock, the special case we saw above.

Exit acquires ptable.lock and then wakes up any process sleeping on a wait channel equal to the current process's parent proc (2651); if there is such a process, it will be the parent in wait. This may look premature, since exit has not marked the current process as a ZOMBIE yet, but it is safe: although wakeup may cause the parent to run, the loop in wait cannot run until exit releases ptable.lock by calling sched to enter the scheduler, so wait can't look at the exiting process until after exit has set its state to ZOMBIE (2663). Before exit yields the processor, it reparents all of the exiting process's children, passing them to the initproc (2653-2660). Finally, exit calls sched to relinquish the CPU.

If the parent process was sleeping in wait, the scheduler will eventually run it. The call to sleep returns holding ptable.lock; wait rescans the process table and finds the exited child with state == ZOMBIE. (2657). It records the child's pid and then cleans up the struct proc, freeing the memory associated with the process (2687-2694).

The child process could have done most of the cleanup during exit, but it is important that the parent process be the one to free p->kstack and p->pgdir: when the child runs exit, its stack sits in the memory allocated as p->kstack and it uses its own pagetable. They can only be freed after the child process has finished running for the last time by calling swtch (via sched). This is one reason that the scheduler procedure runs on its own stack rather than on the stack of the thread that called sched.

While exit allows a process to terminate itself, kill (2975) lets one process request that another be terminated. It would be too complex for kill to directly destroy the victim process, since the victim might be executing on another CPU or sleeping while midway through updating kernel data structures. To address these challenges, kill does very little: it just sets the victim's p->killed and, if it is sleeping,

priority inversion

wakes it up. Eventually the victim will enter or leave the kernel, at which point code round robin in trap will call exit if p->killed is set. If the victim is running in user space, it will soon enter the kernel by making a system call or because the timer (or some other device) interrupts.

If the victim process is in sleep, the call to wakeup will cause the victim process to return from sleep. This is potentially dangerous because the condition being waiting for may not be true. However, xv6 calls to sleep are always wrapped in a while loop that re-tests the condition after sleep returns. Some calls to sleep also test p->killed in the loop, and abandon the current activity if it is set. This is only done when such abandonment would be correct. For example, the pipe read and write code (6837) returns if the killed flag is set; eventually the code will return back to trap, which will again check the flag and exit.

Some xv6 sleep loops do not check p->killed because the code is in the middle of a multi-step system call that should be atomic. The IDE driver (4379) is an example: it does not check p->killed because a disk operation may be one of a set of writes that are all needed in order for the file system to be left in a correct state. To avoid the complication of cleaning up after a partial operation, xv6 delays the killing of a process that is in the IDE driver until some point later when it is easy to kill the process (e.g., when the complete file system operation has completed and the process is about to return to user space).

Real world

The xv6 scheduler implements a simple scheduling policy, which runs each process in turn. This policy is called *round robin*. Real operating systems implement more sophisticated policies that, for example, allow processes to have priorities. The idea is that a runnable high-priority process will be preferred by the scheduler over a runnable low-priority process. These policies can become complex quickly because there are often competing goals: for example, the operating might also want to guarantee fairness and high throughput. In addition, complex policies may lead to unintended interactions such as priority inversion and convoys. Priority inversion can happen when a low-priority and high-priority process share a lock, which when acquired by the low-priority process can prevent the high-priority process from making progress. A long convoy can form when many high-priority processes are waiting for a low-priority process that acquires a shared lock; once a convoy has formed it can persist for long time. To avoid these kinds of problems additional mechanisms are necessary in sophisticated schedulers.

Sleep and wakeup are a simple and effective synchronization method, but there are many others. The first challenge in all of them is to avoid the "lost wakeups" problem we saw at the beginning of the chapter. The original Unix kernel's sleep simply disabled interrupts, which sufficed because Unix ran on a single-CPU system. Because xv6 runs on multiprocessors, it adds an explicit lock to sleep. FreeBSD's msleep takes the same approach. Plan 9's sleep uses a callback function that runs with the scheduling lock held just before going to sleep; the function serves as a last minute check of the sleep condition, to avoid lost wakeups. The Linux kernel's sleep uses an

thundering herd signal+code

explicit process queue instead of a wait channel; the queue has its own internal lock.

Scanning the entire process list in wakeup for processes with a matching chan is inefficient. A better solution is to replace the chan in both sleep and wakeup with a data structure that holds a list of processes sleeping on that structure. Plan 9's sleep and wakeup call that structure a rendezvous point or Rendez. Many thread libraries refer to the same structure as a condition variable; in that context, the operations sleep and wakeup are called wait and signal. All of these mechanisms share the same flavor: the sleep condition is protected by some kind of lock dropped atomically during sleep.

The implementation of wakeup wakes up all processes that are waiting on a particular channel, and it might be the case that many processes are waiting for that particular channel. The operating system will schedule all these processes and they will race to check the sleep condition. Processes that behave in this way are sometimes called a *thundering herd*, and it is best avoided. Most condition variables have two primitives for wakeup: signal, which wakes up one process, and broadcast, which wakes up all processes waiting.

Semaphores are another common coordination mechanism. A semaphore is an integer value with two operations, increment and decrement (or up and down). It is aways possible to increment a semaphore, but the semaphore value is not allowed to drop below zero: a decrement of a zero semaphore sleeps until another process increments the semaphore, and then those two operations cancel out. The integer value typically corresponds to a real count, such as the number of bytes available in a pipe buffer or the number of zombie children that a process has. Using an explicit count as part of the abstraction avoids the "lost wakeup" problem: there is an explicit count of the number of wakeups that have occurred. The count also avoids the spurious wakeup and thundering herd problems.

Terminating processes and cleaning them up introduces much complexity in xv6. In most operating systems it is even more complex, because, for example, the victim process may be deep inside the kernel sleeping, and unwinding its stack requires much careful programming. Many operating systems unwind the stack using explicit mechanisms for exception handling, such as longjmp. Furthermore, there are other events that can cause a sleeping process to be woken up, even though the event it is waiting for has not happened yet. For example, when a Unix process is sleeping, another process may send a signal to it. In this case, the process will return from the interrupted system call with the value -1 and with the error code set to EINTR. The application can check for these values and decide what to do. Xv6 doesn't support signals and this complexity doesn't arise.

Xv6's support for kill is not entirely satisfactory: there are sleep loops which probably should check for p->killed. A related problem is that, even for sleep loops that check p->killed, there is a race between sleep and kill; the latter may set p->killed and try to wake up the victim just after the victim's loop checks p->killed but before it calls sleep. If this problem occurs, the victim won't notice the p->killed until the condition it is waiting for occurs. This may be quite a bit later (e.g., when the IDE driver returns a disk block that the victim is waiting for) or never (e.g., if the victim is waiting from input from the console, but the user doesn't type any in-

Exercises

1. Sleep has to check lk != &ptable.lock to avoid a deadlock (2890-2893). Suppose the special case were eliminated by replacing

```
if(lk != &ptable.lock){
    acquire(&ptable.lock);
    release(lk);
}
with
    release(lk);
acquire(&ptable.lock);
```

Doing this would break sleep. How?

- 2. Most process cleanup could be done by either exit or wait, but we saw above that exit must not free p->stack. It turns out that exit must be the one to close the open files. Why? The answer involves pipes.
- 3. Implement semaphores in xv6. You can use mutexes but do not use sleep and wakeup. Replace the uses of sleep and wakeup in xv6 with semaphores. Judge the result.
- 4. Fix the race mentioned above between kill and sleep, so that a kill that occurs after the victim's sleep loop checks p->killed but before it calls sleep results in the victim abandoning the current system call.
- 5. Design a plan so that every sleep loop checks p->killed so that, for example, a process that is in the IDE driver can return quickly from the while loop if another kills that process.
- 6. Design a plan that uses only one context switch when switching from one user process to another. This plan involves running the scheduler procedure on the kernel stack of the user process, instead of the dedicated scheduler stack. The main challenge is to clean up a user process correctly. Measure the performance benefit of avoiding one context switch.
- 7. Modify xv6 to turn off a processor when it is idle and just spinning in the loop in scheduler. (Hint: look at the x86 HLT instruction.)
- 8. The lock p->lock protects many invariants, and when looking at a particular piece of xv6 code that is protected by p->lock, it can be difficult to figure out which invariant is being enforced. Design a plan that is more clean by perhaps splitting p->lock in several locks.