
## Chapter 10

Implementing Subprograms



ISBN 0- 0-321-49362-1

## Chapter 10 Topics

- The General Semantics of Calls and Returns
- Implementing "Simple" Subprograms
- Implementing Subprograms with Stack-Dynamic Local Variables
- Nested Subprograms
- Blocks
- Implementing Dynamic Scoping

## The General Semantics of Calls and Returns

- The subprogram call and return operations of a language are together called its subprogram linkage
- General semantics of calls to a subprogram
  - Parameter passing methods
  - Stack-dynamic allocation of local variables
  - Save the execution status of calling program
  - Transfer of control and arrange for the return
  - If subprogram nesting is supported, access to nonlocal variables must be arranged

## The General Semantics of Calls and Returns

- General semantics of subprogram returns:
  - Out mode and inout mode parameters must have their values returned
  - Deallocation of stack-dynamic locals
  - Restore the execution status
  - Return control to the caller

## Implementing "Simple" Subprograms

#### Call Semantics:

- Save the execution status of the caller
- Pass the parameters
- Pass the return address to the called
- Transfer control to the called

## Implementing "Simple" Subprograms (continued)

#### Return Semantics:

- If pass-by-value-result or out mode parameters are used, move the current values of those parameters to their corresponding actual parameters
- If it is a function, move the functional value to a place the caller can get it
- Restore the execution status of the caller
- Transfer control back to the caller

#### Required storage:

 Status information, parameters, return address, return value for functions, temporaries

## Implementing "Simple" Subprograms (continued)

- Two separate parts: the actual code and the non-code part (local variables and data that can change)
- The format, or layout, of the non-code part of an executing subprogram is called an <u>activation record</u>
- An activation record instance is a concrete example of an activation record (the collection of data for a particular subprogram activation)


# An Activation Record for "Simple" Subprograms

Local variables

**Parameters** 

Return address

## Code and Activation Records of a Program with "Simple" Subprograms



# Implementing Subprograms with Stack-Dynamic Local Variables


- More complex activation record
  - The compiler must generate code to cause implicit allocation and deallocation of local variables
  - Recursion must be supported (adds the possibility of multiple simultaneous activations of a subprogram)

## Typical Activation Record for a Language with Stack-Dynamic Local Variables

Parameters

Dynamic link

Return address




#### Implementing Subprograms with Stack-Dynamic Local Variables: Activation Record

- The activation record format is static, but its size may be dynamic
- The <u>dynamic link</u> points to the beginning/bottom of an instance of the activation record of the CALLER
- An activation record instance is dynamically created when a subprogram is called
- Activation record instances reside on the <u>run-time</u> <u>stack</u>
- The Environment Pointer (EP) must be maintained by the run-time system. It always points at the base of the activation record instance of the currently executing program unit

## An Example: C Function

```
void sub(float total, int part)
{
  int list[5];
  float sum;
  ...
}
```



#### Revised Semantic Call/Return Actions

#### Caller Actions:

- Create an activation record instance
- Save the execution status of the current program unit
- Compute and pass the parameters
- Pass the return address to the called
- Transfer control to the called

#### Prologue actions of the called subprogram:

- Save the old EP in the stack as the dynamic link and create the new value
- Allocate local variables

## Revised Semantic Call/Return Actions (continued)

#### Epilogue actions of the called subprogram:


- If there are pass-by-value-result or out-mode parameters, the current values of those parameters are moved to the corresponding actual parameters
- If the subprogram is a function, its value is moved to a place accessible to the caller
- Restore the stack top pointer by setting it to the value of the current EP-1 and set the EP to the old dynamic link
- Restore the execution status of the caller
- Transfer control back to the caller

### An Example Without Recursion

```
void fun1(float r) {
   int s, t;
   fun2(s); //point 2
   . . .
void fun2(int x) {
   int y;
   fun3(y); //point 3
void fun3(int q) {
void main() {
   float p;
   fun1(p); //point 1
```

```
main calls fun1
fun1 calls fun2
fun2 calls fun3
```

### An Example Without Recursion



ARI = activation record instance

### Dynamic Chain and Local Offset

- The collection of dynamic links in the stack at a given time is called the dynamic chain, or call chain
- Local variables can be accessed by their offset from the beginning of the activation record, whose address is in the EP. This offset is called the local\_offset
- The local\_offset of a local variable can be determined by the compiler at compile time

#### An Example With Recursion

The activation record used in the previous example supports recursion

#### Activation Record for factorial

**Functional value** 


**Parameter** 

 $\mathbf{n}$ 

Dynamic link


Return address

#### Stacks for calls to factorial



ARI = activation record instance

#### Stacks for returns from factorial



ARI = activation record instance

### Nested Subprograms

- Some non-C-based static-scoped languages (e.g., Fortran 95+, Ada, Python, JavaScript, Ruby, and Swift) use stack-dynamic local variables and allow subprograms to be nested
- All variables that can be non-locally accessed reside in some activation record instance in the stack
- The process of locating a non-local reference:
  - 1. Find the correct activation record instance
  - 2. Determine the correct offset within that activation record instance

### Locating a Non-local Reference

- Finding the offset is easy
- Finding the correct activation record instance
  - Static semantic rules guarantee that all nonlocal variables that can be referenced have been allocated in some activation record instance that is on the stack when the reference is made

### Static Scoping

- A static chain is a chain of static links that connects certain activation record instances
- The <u>static link</u> in an activation record instance for subprogram A points to one of the activation record instances of A's static **PARENT**
- The static chain from an activation record instance connects it to ALL of its static ancestors
- Static\_depth is an integer associated with a static scope whose value is the depth of nesting of that scope

### Static Scoping (continued)

- The chain\_offset or nesting\_depth of a nonlocal reference is the difference between the static\_depth of the reference and that of the scope when it is declared
- A reference to a variable can be represented by the pair:

```
(chain_offset, local_offset), where local_offset is the offset in the activation record of the variable being referenced
```

#### Example JavaScript Program

```
function main(){
 var x;
 function bigsub() {
  var a, b, c;
  function sub1 {
   var a, d;
   a = b + c; \leftarrow-----1
  } // end of sub1
  function sub2(x) {
   var b, e;
```

#### Example JavaScript Program (continued)


```
function sub3() {
    var c, e;
    sub1():
   e = b + a; \leftarrow -----2
   } // end of sub3 ...
  sub3();
   a = d + e; \leftarrow -----3
  } // end of sub2
  sub2(7);
} // end of bigsub
 bigsub();
} // end of main
```

#### Example JavaScript Program (continued)

Call sequence for main

```
main calls bigsub
bigsub calls sub2
sub2 calls sub3
sub3 calls sub1
```

# Stack Contents at Position 1



ARI = activation record instance

#### Static Chain Maintenance

- At the call,
  - The activation record instance must be built
  - The dynamic link is just the old stack top pointer
  - The static link must point to the most recent ARI (activation record instance) of the static parent
    - Two methods:
      - 1. Search the dynamic chain
      - 2. Treat subprogram calls and definitions like variable references and definitions

#### **Evaluation of Static Chains**

- Problems:
  - 1. A nonlocal reference is slow if the nesting depth is large
  - 2. Time-critical code is difficult:
    - a. Costs of nonlocal references are difficult to determine
    - b. Code changes can change the nesting depth, and therefore the cost

#### Blocks

- Blocks are user-specified local scopes for variables
- An example in C

```
{int temp;
  temp = list [upper];
  list [upper] = list [lower];
  list [lower] = temp
}
```

- The lifetime of temp in the above example begins when control enters the block
- An advantage of using a local variable like temp is that it cannot interfere with any other variable with the same name

## Implementing Blocks

#### • Two Methods:

- 1. Treat blocks as parameter-less subprograms that are always called from the same location
  - Every block has an activation record; an instance is created every time the block is executed
- 2. Since the maximum storage required for a block can be statically determined, this amount of space can be allocated after the local variables in the activation record


## Implementing Dynamic Scoping

- Deep Access: non-local references are found by searching the activation record instances on the dynamic chain
  - Length of the chain cannot be statically determined
  - Every activation record instance must have variable names
- Shallow Access: put locals in a central place
  - One stack for each variable name
  - Central table with an entry for each variable name

# Using Shallow Access to Implement Dynamic Scoping

```
void sub3() {
  int x, z;
  x = u + v;
void sub2() {
  int w, x;
void sub1() {
  int v, w;
void main() {
  int v, u;
```

```
main calls sub1 sub1 calls sub1 calls sub2 sub2 calls sub3
```



(The names in the stack cells indicate the program units of the variable declaration.)

#### Summary

- Subprogram linkage semantics requires many action by the implementation
- Simple subprograms have relatively basic actions
- Stack-dynamic languages are more complex
- Subprograms with stack-dynamic local variables and nested subprograms have two components
  - actual code
  - activation record

## Summary (continued)

- Activation record instances contain formal parameters and local variables among other things
- Static chains are the primary method of implementing accesses to non-local variables in static-scoped languages with nested subprograms
- Access to non-local variables in dynamicscoped languages can be implemented by use of the dynamic chain or through some central variable table method