Numerical Analysis notes

Foundations of matrix analysis

Numerical Analysis is the "art of approximating". Quoting Wikipedia:

An approximation is an inexact representation of something that is still close enough to be useful. Although approximation is most often applied to numbers, it is also frequently applied to such things as mathematical functions, shapes, and physical laws.

Approximations should be used when incomplete information prevents use of exact representations. Many problems in physics are either too complex to solve analytically, or impossible to solve using the available analytical tools. Thus, even when the exact representation is known, an approximation may yield a sufficiently accurate solution while reducing the complexity of the problem significantly.

The type of approximation used depends on the available information, the degree of accuracy required, the sensitivity of the problem to this data, and the savings (usually in time and effort) that can be achieved by approximation.

In this course we focus on three main aspects:

- Methodologies (or approximation algorithms)
- Analysis (estimate errors and convergence properties)
- Implementation (through Python and numpy notebooks)

Approximation is a matter of

- Representation (floating point values VS real numbers, finite dimensional spaces VS infinite dimensional ones, etc.)
- Measure of the Error (how do we know that we did a good job in approximating?)

In general, we will end up working with \mathbb{R}^n .

Matrices

Denoting by A_{ij} the matrix of order n-1 obtained from A by eliminating the i-th row and the j-th column, we call the **complementary minor** associated with the entry a_{ij} the determinant of the matrix A_{ij} . We call the k-th principal (dominating) minor of A, d_k , the determinant of the principal submatrix of order k, $A_k = A(1:k,1:k)$.

The computational cost is O (ops) and can be constant, linear, polynomial, exponential, factorial, etc.

$$\textit{Total error: } f(x) - \hat{f}\left(\hat{x}\right) = \underbrace{\hat{f}\left(\hat{x}\right) - f(\hat{x})}_{\text{computational error } e_c = e_t + e_r} + \underbrace{f(\hat{x}) - f(x)}_{\text{propagated data error (independent from } f)}$$

Example: finite difference approximation $f'(x) = \lim_{h \to 0} rac{f(x-h) - f(x)}{h}$

- ullet truncation error (obtained through Taylor) $\sim rac{1}{2} |f''(x)| h + O(h^2)$
- ullet rounding error $\sim rac{2arepsilon}{h}$, with arepsilon = machine precision

The optimal h is thus $h=2\sqrt{rac{arepsilon}{|f''(x)|}}.$

Norms of vectors, matrices and functions

Given a vector space V over the field of real $\mathbb R$ or complex numbers $\mathbb C$ (V might be infinite dimensional), a **semi-norm** on V is a function $|\cdot|:V\to\mathbb C$ satisfying:

- 1. |cf| = |c||f|, for all $c \in \mathbb{C}$ [homogeneity];
- 2. $|f+g| \le |f| + |g|$ [triangle inequality].

As it can be easily seen (1)–(2) imply that the norm is always non-negative:

$$0 = 0 \cdot |f| = |0 \cdot f| = |(1 - 1)f| = |f - f| \le |f| + |(-1)f| = 2||f|.$$

The semi-norm becomes a **norm** if in addition to (1)–(2) we have also that for all $f \in V$

$$|f| = 0$$
 if and only if $f = 0$.

A vector space is said to be **complete** if every Cauchy sequence in that space converges to one of the space's elements.

A complete vector space with a norm is called a **Banach space**.

A scalar product is a function $(\cdot,\cdot):V\times V\mapsto\mathbb{C}$ which is:

- 1. symmetric: $(f,g) = \overline{(g,f)}$;
- 2. linear:
 - $\circ \ (\alpha f,g)=\alpha (f,g) \text{ for all } \alpha \in \mathbb{C};$
 - \circ (f+g,h)=(f,h)+(g,h);

equivalent to

- $\circ \ (\alpha_1 f + \alpha_2 g, h) = \alpha_1 (f, h) + \alpha_2 (g, h)$
- 3. **positive definite**: $(f, f) \ge 0$ and (f, f) = 0 if and only if f = 0.

The norm is then defined as $||f||^2 = (f, f)$. That this is a norm (i.e. satisfies the triangle inequality) is proved by using the **Cauchy-Schwarz** inequality

$$|(f,g)| \leq \sqrt{(f,f)(g,g)}.$$

A Banach space with a scalar product and a norm induced by it is called a Hilbert space.

Example: Some norms in Banach spaces

$$\|x\|_p = \left(\sum_{i=1}^n |x_i|^p
ight)^{rac{1}{p}}, \quad 1 \leq p < \infty, \qquad \|x\|_1 = \sum_{i=1}^n |x_i| \ \|x\|_2 = \sqrt{x_1^2 + x_2^2} \quad ext{[Euclidean norm]} \qquad \|x\|_\infty = \sup_{1 \leq i \leq n} |x_i|.$$

Definition: Two norms $||\cdot||_p$, $||\cdot||_q$ on a vector space V are **equivalent** if there exist two positive constants c_1 and c_2 such that:

$$|c_1||x||_q \le ||x||_p \le |c_2||x||_q \quad \forall x \in V$$

In a finite-dimensional normed vector space (the dimension is given by the number of vectors in the basis) all norms are equivalent.