

Department of Physics, Computer Science & Engineering

CPSC 410 – Operating Systems I

Virtualizing Memory: Smaller Page TAbles

Keith Perkins

Adapted from "CS 537 Introduction to Operating Systems" Arpaci-Dusseau

Questions answered in this lecture:

- Review: What are problems with paging?
- Review: How large can page tables be?
- How can large page tables be avoided with different techniques?
 - segmentation + paging, multilevel page tables
- What happens on a TLB miss?

Disadvantages of Paging

Additional memory reference to look up in page table

- Very inefficient
- Page table must be stored in memory
- MMU stores only base address of page table
- Avoid extra memory reference for lookup with TLBs (previous lecture)

2. Storage for page tables may be substantial


- Simple page table: Requires PTE for all pages in address space
 - Entry needed even if page not allocated
- Problematic with dynamic stack and heap within address space (today)

QUIZ: How big are page Tables?

- 1. PTE's are **2 bytes**, and **32** possible virtual page numbers 32 * 2 bytes = 64 bytes
- 2. PTE's are **2 bytes**, virtual addrs are **24 bits**, pages are **16** bytes
 - 2 bytes * $2^{(24 \lg 16)} = 2*(s^2)$ bytes (2 MB)
- 3. PTE's are 4 bytes, virtual addrs are 32 bits, and pages are 4 KB 4 bytes * $2^{(32-lg 4K)} = 4*2^{20}$ bytes (4 MB)
- 4. PTE's are **4 bytes**, virtual addrs are **64 bits**, and pages are **4 KB** 4 bytes * $2^{(64-1g)} = 4 \times 2^{(64-12)} = 2^{54}$ bytes

How big is each page table?

Why ARE Page Tables so Large?



Need 1 entry per physical frame But you are using very few of the entries

Many invalid PT entries

Format of linear page tables:

how to avoid storing these?

PFN v	alid	protection
10	1	r-x
-	0	_
23	1	rw-
-	1 0 0 0	-
-	0	-
-	0	-
-	0	-
manj	y more	invalid
-	0	-
-	0	-
-	0	-
-	0 0 0 1	_
28 4	1	rw-
4	1	rw-
	†	

Invalid pages are not used but still are in page table

Avoid simple linear Page Table

Use more complex page tables, instead of just big array Any data structure is possible with software-managed TLB

- Hardware looks for vpn in TLB on every memory access
- If TLB does not contain vpn, TLB miss
 - Trap into OS and let OS find vpn->ppn translation
 - OS notifies TLB of vpn->ppn for future accesses

Other Approaches

- 1. Segmented Pagetables
- 2. Multi-level Pagetables
 - Page the page tables
 - Page the page tables of page tables...

valid Ptes are Contiguous

how	to	av	roid
torin	a t	he	se?

10	1	r-x
-	0	-
23	1	rw-
-	0	-
-	0	-
-	0	-
-	0	-
man	ny more in	valid
-	0	-
-	0	-
-	0	-
-	0	-
28	1	rw-
4	1	rw-

prot

PFNvalid

Note "hole" in addr space: valids vs. invalids are clustered

How did OS avoid allocating holes in phys memory?

Segmentation

Combine Paging and Segmentation

Divide address space into segments (code, heap, stack)

Segments can be variable length

Divide each segment into fixed-sized pages Logical address divided into three portions

```
seg #
(4 bits) page number (8 bits) page offset (12 bits)
```

Implementation

- Each segment has a page table
- Each segment track base (physical address) and bounds of **page** table for that segment

Quiz: Paging and Segmentation

seg # (4 bits) page number (8 bits)

page offset (12 bits)

seg	base	bounds	R W
0	0x002000	0xff	1 0
1	0x000000	0x00	0 0
2	0x001000	0x0f	1 1

 0×002070 read: 0×004070

0x202016 read: 0x003016

0x104c84 read: err bound=0

0x010424 write: err 0x004 +424>0xff

0x210014 write: err 0x003 + 014>0x0f

0x203568 read: 0x02a568

• • •
0x01f
0x011
0x003
0x02a
0x013
• • •
0 00

0x00c

0x007

0x004

0x00b

0x006

0x002000

0x001000

Advantages of Paging and Segmentation

Advantages of Segments

- Supports sparse address spaces
 - Decreases size of page tables
 - If segment not used, not needed for page table

Advantages of Pages

- No external fragmentation
- Segments can grow without any reshuffling
- Can run process when some pages are swapped to disk (next lecture)

Advantages of Both

- Increases flexibility of sharing
 - Share either single page or entire segment
 - How?

Disadvantages of Paging and Segmentation

Potentially large page tables (for each segment)

- Must allocate each page table contiguously
- More problematic with more address bits
- Page table size?
 - Assume 2 bits for segment, 18 bits for page number, 12 bits for offset

Each page table is:

- = Number of entries * size of each entry
- = Number of pages * 4 bytes
- $= 2^18 * 4$ bytes $= 2^20$ bytes = 1 MB!!!

Other Approaches


- 1. Segmented Pagetables
- 2. Multi-level Pagetables
 - Page the page tables
 - Page the pages of page tables...

3) Multilevel Page Tables

Goal: Allow each page tables to be allocated non-contiguously Idea: Page the page tables

- Creates multiple levels of page tables; outer level "page directory"
- Only allocate page tables for pages in use
- Used in x86 architectures (hardware can walk known structure)

30-bit address: outer page (8 bits) (10 bits) page offset (12 bits) base of page directory



Quiz: Multilevel

page directory page of PT (@PPN:0x3) page of PT (@PPN:0x92)

PPN	valid	PPN	valid	PPN	valid	
0x3	1	0x10	1	-	0	
-	0	0x23	1	-	0	
-	0	-	0	-	0	translate 0x01ABC
-	0	-	0	-	0	
-	0	0x80	1	-	0	0x23ABC
-	0	0x59	1	-	0	tl-t- 00000
-	0	-	0	-	0	translate 0x00000
-	0	-	0	-	0	0x10000
-	0	-	0	-	0	OXIOOO
-	0	-	0	-	0	
-	0	-	0	-	0	translate 0xFEED0
-	0	-	0	-	0	0x55ED0
-	0	-	0	-	0	OXOOEDO
-	0	-	0	0x55	1	
0x92	1	-	0	0x45	1	

20-bit address:

outer page	inner page	page offset (12 bits)
(4 bits)	(4 bits)	page offset (12 bits)

QUIZ: Address format for multilevel Paging

30-bit address:

outer page

inner page

page offset (12 bits)

How should logical address be structured?

How many bits for each paging level?

Goal?

- Each page table fits within a page
- PTE size * number PTE = page size
 - Assume PTE size = 4 bytes
 - Page size = 2^12 bytes = 4KB
 - 2^2 bytes * number PTE = 2^12 bytes
 - \rightarrow number PTE = 2^10
- → # bits for selecting inner page = 10

Remaining bits for outer page:

• 30 - 10 - 12 = 8 bits

Problem with 2 levels?

Problem: page directories (outer level) may not fit in a page **64-bit** address:

Solution:

outer page?

inner page (10 bits)

page offset (12 bits)

- Split page directories into pieces
- Use another page dir to refer to the page dir pieces.

VPN

PD idx 0 PD idx 1

PT idx

OFFSET

How large is virtual address space with 4 KB pages, 4 byte PTEs, each page table fits in page given 1, 2, 3 levels?

4KB / 4 bytes → 1K entries per level

1 level: $1K * 4K = 2^2 = 4MB$

2 levels: $1K * 1K * 4K = 2^32 \approx 4 \text{ GB}$

3 levels: $1K * 1K * 1K * 4K = 2^42 \approx 4 TB$

QUIZ: FULL SYSTEM WITH TLBS

On TLB miss: lookups with more levels more expensive

How much does a miss cost?

ASID	VPN	PFN	Valid
211	0xbb	0x91	1
211	0xff	0x23	1
122	0x05	0x91	1
211	0x05	0x12	0

Assume 3-level page table

Assume 256-byte pages

Assume 16-bit addresses

Assume ASID of current process is 211

How many physical accesses for each instruction? (Ignore previous ops changing TLB)

(a) 0xAA10: movl 0x1111, %edi 0xaa: (TLB miss -> 3 for addr trans) + 1 instr fetch

0x11: (TLB miss -> 3 for addr trans) + 1 movl

(b) 0xBB13: addl \$0x3, %edi

0xbb: (TLB hit -> 0 for addr trans) + 1 instr fetch from 0x9113 (c) 0x0519: movl %edi, 0xFF10

0x05: (TLB miss -> 3 for addr trans) + 1 instr fetch

0xff: (TLB hit -> 0 for addr trans) + 1 movl into 0x2310

Total: 8

Total: 1

Total: 5

Summary: Better PAGE TABLES

Problem:

Simple linear page tables require too much contiguous memory

If Hardware handles TLB miss, page tables must follow specific format

- Multi-level page tables used in x86 architecture
- Each page table fits within a page

Next Topic:

What if desired address spaces do not fit in physical memory?