

How to use Kling Studio


Paste one prompt, get the still frames, check them, turn them into video. This is everything from installing it to collecting the finished clips — for Windows and for Mac.

Frames drawn by **Nano Banana 2** Video by **Kling 3.0** Both billed through **your own kie.ai account**

THE SHAPE OF IT

Two buttons, in order

Every clip is made twice: first as a still picture, then as five seconds of video built from that picture. You look at the stills in between, which is the whole point — a bad frame is cheap to redo, a bad video is not.



1 Run the Setup file

Double-click `KlingStudio-Setup-3.9.1.exe` from your Downloads folder.

2 Get past the blue box

Windows stops apps it hasn't seen before. Click **More info**, then **Run anyway**. It is not a virus warning — it means the app has no paid signing certificate.

3 Click through the installer

It reads you a short page of notes, then installs into your own user folder. No administrator password, no IT ticket.

4 Open it from the Start menu

Search for **Kling Studio**. The same blue box may appear once more on first launch — same answer.

Windows protected your PC

Microsoft Defender SmartScreen prevented an unrecognized app from starting. Running this app might put your PC at risk.

App: KlingStudio-Setup-3.9.1.exe
Publisher: Unknown publisher

Run anyway

Don't run

Expected. "Run anyway" only appears after you click **More info** first.

1 Open the .dmg

Double-click `KlingStudio-3.9.1-mac.dmg`. A window opens with the app and an Applications shortcut.

2 Drag it to Applications

Drop **Kling Studio** onto the Applications folder in that window, then eject the disk image.

3 Right-click to open, the first time only

In Applications, **right-click Kling Studio** → **Open**, then **Open** again in the box. Double-clicking it the normal way will just be refused until you've done this once.

4 Still blocked?

System Settings → Privacy & Security, scroll down, and click **Open Anyway** next to the Kling Studio message.



"Kling Studio" can't be opened because Apple cannot check it for malicious software

This software needs to be updated. Contact the developer for more information.

OK

Move to Trash

Expected. Right-click → Open replaces this box with one that has an **Open** button.

STEP TWO

Connect your kie.ai key

The app doesn't have an account of its own — it runs on yours. That means the credits are yours, the history is yours, and nobody shares a login.

1 Sign in at kie.ai

Go to [kie.ai](#), sign in, and open the API key page from your dashboard.

2 Copy the key


It's a long string of letters and numbers. Copy the whole thing.

3 Paste it into Settings

In Kling Studio, click **Settings** in the bottom-left corner, paste into **kie.ai API key**, and press Save. On a fresh install the app asks for it straight away.

4 Put credits on the account

Top up on kie.ai. If the balance runs out mid-batch the app stops immediately, keeps everything already paid for, and says so on the batch page.



Settings, with the key already saved. It is never shown again after you save it — only the last four characters, so you can tell which key is in there.


Your key stays on your own machine. It is not sent anywhere except kie.ai, and it is not in the app's code or on GitHub.

STEP THREE

Get the master prompt from Claude

You never type the prompt block by hand. When the script is final, run the skill in your Claude chat and it writes the whole thing.

Type `/kling-studio` in the chat. It reads the shots you've been working on, asks you for a batch name, and prints one block. Select it, copy it, done — no files, no setup, nothing to upload.




Four kinds of line, and that's the lot.

LINE	WHAT IT DOES
batch:	Names the batch, its folder, and every clip inside it (<code>c150_clip01</code> and so on).
image:	What the still picture shows. This is what Nano Banana 2 draws.
motion:	What moves. This is what Kling 3.0 animates, using the frame above it.
ref: frame 1	Keeps a face or product identical across clips — frame 1 is drawn first, then reused as the reference.
ref: needed	The app will stop and ask <i>you</i> for a picture for that clip before it draws anything.
settings:	Optional. Only appears when something differs from 9:16 · 5s · Pro · sound off · 2K.

STEP FOUR


Paste it in and make the frames

Paste into the big box on the New batch screen. The app reads the block back to you immediately, so a mistake turns up before it costs anything.



Green dots mean the app understood that part. A line it can't place is listed underneath as ignored rather than dropped quietly.

Press the big button. If any clip was marked **ref: needed**, a window opens for that clip first and waits for a picture — drop a file on it, pick one, or reuse another clip's frame. Then you get one confirmation for the whole run:



Cancel sends nothing. While it runs you can close the window — the batch keeps going and the files still download.

CONSISTENCY

Keeping the same face across clips

Nano Banana 2 draws each frame from scratch, so left alone it invents a slightly different person every time. The **References** panel at the top of a batch is where you stop that — and the anchor is the strongest tool in it.

- 1

Describe the character, not a scene

In the anchor box, write the portrait you want locked: *studio portrait of the woman, plain grey background, neutral expression*. It is never one of your clips, so keep the scene out of it.
- 2

Draw just the anchor

Generate anchor costs one frame — 8 credits at 1K — and nothing else is drawn. It appears beside the box a few seconds later.
- 3

Look at it. Redraw until it's right

Wrong face? Change the wording and press **Redraw anchor**. You're only ever risking one frame, not the whole batch. Or press **Use my picture** and skip drawing entirely.
- 4

Lock it

Lock → **use on every frame** pins it. From then on every frame in the batch is drawn with the anchor attached, so the same person carries through all of them. Unlock at any time.

A style reference

One picture applied to

EVERY

frame in the batch — your avatar, the product, a look you want matched. Add it once and it goes on all of them.

ADD STYLE REFERENCE

An anchor frame

No portrait to lock? Nominate one of your own clips instead: it is drawn first and the rest are built from it.

ANCHOR FRAME


One picture, many clips

When several clips ask for a picture, the popup offers

Use it for all clips waiting

— upload once, it covers the lot.

IN THE POPUP




The anchor is drawn and approved on its own before any scene frame exists. A style reference goes on every frame too — anchor plus style is the most consistent setting there is.

 A clip that has its own picture keeps it — setting an anchor never overwrites a reference you attached by hand. Uploading the same picture twice doesn't happen either: it is stored once and pointed at from every clip that uses it.

STEP FIVE

Check the frames, fix what's wrong

This is the part worth slowing down for. Six fingers, a third arm, a mug floating in mid-air — fix it here while it's still a 12-credit picture, not after Kling has lovingly animated it.



Three states at once: done, working, and rejected by kie.ai. A failed card prints the reason underneath so you know what to change.

Button	What it does	Cost
Prompts	Reword the image or motion prompt. Only changes the text — nothing is made.	Free
Frame	Redraw just that frame, with the prompt open for a tweak first.	12
Video	Re-render just that video from the frame it already has.	90
Use my picture	Put your own image in as the frame. Dragging a file straight onto the card does the same.	Free
Play	Watch the finished clip, or open it in your video player.	Free
Delete	Removes the whole batch folder — frames, videos, everything. Asks first, can't be undone.	Free

STEP SIX

Make the videos

Same button, second step. Only clips that already have a frame can be animated, and the credits are confirmed again separately.

When everything is finished the button stops being a button — it turns into a green **All done** marker, and each card plays its clip when you hover it. **Open folder** shows you the files:

```
c150/ frames/ c150_clip01.png, c150_clip02.png ... videos/ c150_clip01.mp4, c150_clip02.mp4 ... refs/ reference pictures you attached
job.json the prompts and settings for this batch state.json what is done, what failed activity.log everything shown under Activity
```

Three things you can set per clip

Most batches never need these — every clip takes the batch's settings and that is the end of it. They earn their place when an ad has to line up with narration or play as one continuous shot.

In the master prompt	What it does
duration: 7	Gives that one clip its own length in seconds, so it lands exactly on its line of narration. Kling takes 3 to 15 seconds. Everything without the line takes the batch's length.
end: next	The clip finishes on the picture the <i>next</i> clip opens with, so the two join with no visible cut. Kling is given both frames, not one. end: frame 4 names a specific one instead. Leave it off when the ad is meant to cut.
anchor: ...	Written once above the clips: the character the batch locks onto. It arrives already filled into Draw one , so you press the button instead of retyping the description.

When someone has to speak on camera

Kling cannot lip-sync. For a talking head, switch **Model** at the top of the Videos card from **Kling** to **Veo** — it generates its own speech and matches the mouth to it. The app asks you to confirm first, because three things change:

- The audio is the point, and it is experimental.** Google says so themselves — some clips come back silent and have to be re-rolled.
- Clips are 4, 6 or 8 seconds.** Kling's 5 and 10 are not on offer, and any per-clip length you wrote snaps to the nearest of the three.
- It is billed per clip, not per second** — 65 credits at its Fast · 1080p default — so an 8-second clip costs the same as a 4-second one. Mode and sound do not apply, and the card hides them.

 Six clips take a few minutes. You can close the window while it works — the batch carries on and the files still arrive.

MONEY

What it costs

Everything is priced per item, in kie.ai credits, and the app always shows the total before it spends anything.


WHAT	MODEL	CREDITS	NOTES
One frame	nano-banana-2 · 1K	8	12 at 2K, 18 at 4K — same price for a redraw
One 5-second video	kling-3.0 · Pro	90	18 credits per second — a 10-second clip is 180, and Std is 14/s
The same, with sound on	kling-3.0 · Pro	135	27 credits per second. Kling's own audio is usually thrown away
One talking-head clip	veo · Fast · 1080p	65	Billed per clip, not per second: 4, 6 or 8 seconds all cost the same
A 6-clip batch	both	588	48 of 1K frames + 540 of video, start to finish
Checking on a running job	—	0	Polling, re-checks and retries of downloads are free
Your own picture as a frame	—	0	Drag it in and skip the drawing step entirely

⚠ These are estimates, shown before anything is sent. The moment a job finishes the app asks kie.ai what it *actually* charged and corrects the batch's running total to that figure — so the number you end up looking at is theirs, not ours. If their prices move before the app catches up, put a figure in **Settings → Credits per frame**; leave it empty to use the published ones.

KEEPING CURRENT

Updates arrive on their own

The app checks for a new version a few seconds after it starts, and every six hours after that. You'll see a green chip above the sidebar buttons.



Clicking it shows the list of changes and an **Install and restart** button.

On WindowsONE CLICK

Press **Install and restart**. The app downloads the new build, checks it against a published checksum, closes, swaps itself over and reopens. No admin rights. SmartScreen may ask once more after the swap — **More info** → **Run anyway**.

On macOSONE DRAG

Press **Release page**, download the new `.dmg`, and drag the app into Applications over the old one. macOS won't let an app replace itself, so this part stays manual.

REFERENCE

When it goes wrong

Every failure prints its reason on the clip card. Here is what each one means and what to do about it.

WHAT IT SAYS	WHAT HAPPENED	WHAT TO DO
kie.ai failed it	The model rejected the prompt — usually content moderation, occasionally a wording it can't parse.	Edit the prompt, then press Frame or Video on that card. <code>costs that one clip</code>
Timed out / Check failed / Download failed	The work may well be finished at kie.ai — the app just lost track of it.	The big button offers a free re-check. <code>Free</code>
Couldn't send	The request never reached kie.ai, so nothing was charged.	The big button sends it again.
Needs a reference	The prompt said <code>ref: needed</code> and no picture has been supplied yet.	Add the picture in the popup, or reuse another clip's frame. <code>Free</code>
Reference missing	This clip copies from a frame that never arrived.	Fix that frame first, then this one.
The run stopped early	A rejected API key or an empty balance. Everything already paid for is kept.	Check the key in Settings, or top up on kie.ai, then press the big button again.



Still stuck? Open the batch folder and send **activity.log** and anything inside **responses/** — that's the raw answer kie.ai gave, and it says exactly what went wrong.