Operating Systems - Processes

Mridul Sankar Barik

Jadavpur University


2024

Slide Credits

 Most of the slides are adapted from the companion lecture slides for the text book by Avi Silberschatz, Peter Baer Galvin, Greg Gagne


Process Concept

- Process is a program in execution
- A process includes
 - Program code (text section)
 - Program counter and other processor registers
 - Defines the current state of the process
 - Stack: contains temporary data
 - Function parameters, return addresses, local variables
 - Data section: contains global data
 - Heap: contains memory dynamically allocated during run time
- A Program is a passive entity stored on disk (executable file), whereas process is an active entity



Process States

- New: The process is being created
- Running: Instructions are being executed
- Waiting: The process is waiting for some event to occur
- Ready: The process is waiting to be assigned to a processor
- Terminated: The process has finished execution




Process Control Block (PCB)

- Each process is represented in the OS by a PCB
 - Process State
 - Program Counter
 - CPU Registers
 - CPU Scheduling Information
 - process priority
 - pointer to scheduling queues etc.
 - Memory Management Information
 - · values of base, limit registers
 - page table or segment table etc.
 - Accounting Information
 - amount of CPU and real time used
 - time limits
 - job or process numbers etc.
 - I/O Status Information
 - list of I/O devices allocated to this process
 - list of open files etc.



CPU Switch From Process to Process




Threads

- So far, process has a single thread of execution
- Consider having multiple program counters per process
 - Multiple locations can execute at once
 - $\bullet \ \ \mathsf{Multiple} \ \mathsf{threads} \ \mathsf{of} \ \mathsf{control} \Rightarrow \mathsf{threads} \\$
- Must then have storage for thread details, multiple program counters in PCB

Process Scheduling I


- Maximize CPU use, quickly switch processes onto CPU for time sharing
- Processes scheduler selects among available processes for next execution on CPU
- Maintains scheduling queues of processes
 - Job queue set of all processes in the system
 - Ready queue set of all processes residing in main memory, ready and waiting to execute
 - Device queues set of processes waiting for an I/O device
- Processes migrate among the various queues



8 / 12

Process Scheduling II

- A new process is initially put in the ready queue, waits there until it is selected for execution
- Once a process executes it may
 - Issue an I/O request, and be placed in an I/O queue
 - Create a new process and wait for its termination
 - Be removed forcibly from the CPU as a result of an interrupt




Schedulers I

- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
 - Sometimes the only scheduler in a system
 - Short-term scheduler is invoked frequently (milliseconds) (must be fast)
- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
 - Long-term scheduler is invoked infrequently (seconds, minutes) (may be slow)
 - The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts
- Long-term scheduler strives for good process mix

Schedulers II

- Medium-term scheduler can be added if degree of multiple programming needs to decrease
 - Remove process from memory, store on disk, bring back in from disk to continue execution: swapping



Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process is represented in the PCB of a process
- Context-switch time is pure overhead
 - The system does no useful work while switching
 - The more complex the OS and the PCB ⇒ the longer the context switch
- Context switch time is dependent on hardware support
 - Sun UltraSPARC provides multiple sets of registers
 - Context switch simply requires changing the pointer to the current register set