CS120: Computer Networks

Lecture 18. Congestion Control 2

Zhice Yang

Congestion Control

- Host-based Congestion Control
  - Packet Loss
  - ➢Delay
- Router-based Congestion Control
  - Queuing

Avoid Congestion

- Feedback: Network Delay





cwnd



Source 1

throughput



throughput

Queue Size

Destination

Queue

Router

100-Mbps Ethernet

Source 2

cwnd increases but rate is flat
when network approach congestion

TCP Vegas

- Idea: TCP source uses RTT as the sign to avoid network congestion
  - Compare RTT with BaseRTT
- Method:
  - Reduce rate when congestion is about to happen
    - If Actual RTT >> Base RTT
  - Recover rate soon after bandwidth is available
    - if Actual RTT > Base RTT
    - Keep certain pressure on network

TCP Vegas Algorithm

- BaseRTT: the reference for increases in RTTs
  - The minimum RTT
    - If RTT < BaseRTT
      - BaseRTT = RTT
- ExpectRate:
  - CongestionWindow/BaseRTT
- ActualRate:
  - ActualRTT: according to timestamps
  - ActualRate=CongestionWindow/ActualRTT

TCP Vegas Algorithm

- Source compares ActualRate with ExpectRate
  - if ExpectRate - ActualRate < α
    - cwnd++
  - if α <ExpectRate - ActualRate < β
    - cwnd = cwnd
  - if β <ExpectRate - ActualRate
    - cwnd --

TCP Vegas



Top, congestion window; bottom, expected (colored line) and actual (black line) throughput. The shaded area is the region between the α and β threshold

Two Places to Handle Network Congestion

- End hosts
- ➢Routers



Congestion Control

- Host-based Congestion Control
  - Packet Loss
  - Delay
- Router-based Congestion Control
  - ➢Queuing

Queuing Discipline

- Why ?
  - Queuing discipline in routers determines how packets are transmitted (or dropped)
- Router Resource
  - Bandwidth
    - Which packets get transmitted
  - Queue Buffer
    - Which packets get discarded

Queuing Discipline

- First-In-First-Out (FIFO)



Drop Policy
Simplest one: Tail
Drop if FIFO is full



Queuing Discipline

- Problems in FIFO
  - Too simple to provide resource allocation polices (to avoid congestion)
  - Hard to enforce every network source/flow to follow the same behavior
    - eg. yellow src does not follow congestion control (UDP), can occupy more network source



Queuing Discipline

- First-In-First-Out (FIFO) with Priority



Always dequeue the queue with higher priority unless it is empty
Problem: starvation

Queuing Discipline

- Fair Queuing (FQ)
  - Each flow gets 1/4 output bandwidth



Queuing Discipline

- Fair Queuing (FQ)
  - Each flow gets 1/3 output bandwidth



Queuing Discipline

- Weighted Fair Queuing (FQ)
  - Flows with higher weight get more output bandwidth (2/7, 3/7, 1/7, 1/7)



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow
  - Finish time is virtually calculated in bit-level round robin, eg, $F_i^1 < F_i^2 < F_i^3 < F_{i+1}^2 < F_i^4$



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow
  - Finish time is virtually calculated in bit-level round robin, eg, $F_i^1 < F_i^2 < F_i^3 < F_{i+1}^2 < F_i^4$



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow
  - Finish time is virtually calculated in bit-level round robin, eg, $F_i^1 < F_i^2 < F_i^3 < F_{i+1}^2 < F_i^4$



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow
  - Case: when one queue is idle, idle time also count



Queuing Discipline

- Bit-Level Fair Queuing (FQ)
  - Schedule according to earliest finish time
  - Finish time of packet i: $F_i = \max(F_{i-1}, A_i) + P_i$
  - P_i is the transmitting duration of packet i, A_i is the arriving time of packet i, F_{i-1} is the finish time of packet i-1 of the same flow
  - Case: when one queue is idle, idle time also count



Congestion Control

- Host-based Congestion Control
  - Packet Loss
  - Delay
- Router-based Congestion Control
  - Queuing
    - DECbit
    - Explicit congestion notification (ECN)
    - Random Early Detection (RED)

DECbit

- Developed for the Digital Network Architecture (DNA)
  - Before TCP/IP was “standardized”
- Idea: let routers explicitly indicate congestion
- Approach:
  - Router set congestion bit in passing packets if there is congestion
  - Destination echoes bit back to source through acks
  - Source adjusts cwnd according to congestion bit

DECbit

- Routers determine congestion
  - Monitor average queue length over last busy+idle cycle
  - If average queue length > th
    - set congestion bit



DECbit

- Source reacts to congestion bit
  - If < 50% of last window's packets had bit set
    - cwnd++
  - If > 50% of last window's packets had bit set
    - cwnd*0.875

Explicit congestion notification (ECN)

- RFC 3168
  - Two bits in IP header (ECN in IP's ToS field) marked by network router to indicate congestion
  - Mechanism is similar to DECbit
  - Destination sets ECE bit (in TCP Header) on ACK segment to notify sender of congestion



This slide is adapted from http://www-net.cs.umass.edu/kurose_ross/ppt.htm by Kurose Ross

Random Early Detection (RED)

- Another way to offload a part of congestion control function to routers
- Idea: let routers implicitly indicate congestion
  - Router notices that the queue is getting backlogged
  - Router randomly drops packets to signal congestion
  - Source adjusts cwnd



RED Algorithm

- Compute Average Queue Length
  - Moving average
    - AvgLen = (1 - Weight) * AvgLen + Weight * SampleLen



RED Algorithm

- Two queue length thresholds
  - if AvgLen <= MinThreshold
    - Enqueue the packet
  - if MinThreshold < AvgLen < MaxThreshold
    - Drop arriving packet with probability P
  - if MaxThreshold <= AvgLen then drop arriving packet





RED Algorithm

- Computing probability P
  - TempP = MaxP * (AvgLen - MinThreshold)/(MaxThreshold - MinThreshold)
  - P = TempP/(1 - count * TempP)
    - Count: number of continuously queued packets without drop
- Why?
  - Drops are spaced out in time
    - Count == 0 => P=TempP
    - Count is large => P=1

Reference

- Textbook 6.4