

(b) ac generator

### 6. MAXWELL'S EQUATIONS IN TIME-VARYING FIELDS

7e Applied EM by Ulaby and Ravaioli

### Chapter 6 Overview

#### **Chapter Contents**

Dynamic Fields, 282
Faraday's Law, 282
Stationary Loop in a Time-Varying Magnetic Field, 284
The Ideal Transformer, 288
Moving Conductor in a Static Magnetic Field, 289
EMF Sensors, 292
The Electromagnetic Generator, 294
Moving Conductor in a Time-Varying Magnetic
Field, 296
Displacement Current, 297
Boundary Conditions for Electromagnetics, 299
Charge-Current Continuity Relation, 299
Free-Charge Dissipation in a Conductor, 302
Electromagnetic Potentials, 302
Chapter 6 Summary, 307
Problems, 308

#### Objectives

Upon learning the material presented in this chapter, you should be able to:

- Apply Faraday's law to compute the voltage induced by a stationary coil placed in a time-varying magnetic field or moving in a medium containing a magnetic field.
- 2. Describe the operation of the electromagnetic generator.
- Calculate the displacement current associated with a timevarying electric field.
- 4. Calculate the rate at which charge dissipates in a material with known  $\epsilon$  and  $\sigma$ .

### Maxwell's Equations

**Table 6-1:** Maxwell's equations.


Reference	Differential Form	Integral Form	
Gauss's law	$\nabla \cdot \mathbf{D} = \rho_{\mathbf{v}}$	$\oint_{S} \mathbf{D} \cdot d\mathbf{s} = Q$	(6.1)
Faraday's law	$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$	$\oint_C \mathbf{E} \cdot d\mathbf{l} = -\int_S \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s}$	(6.2)*
Gauss's law for magnetism	$\nabla \cdot \mathbf{B} = 0$	$\oint_{S} \mathbf{B} \cdot d\mathbf{s} = 0$	(6.3)
Ampère's law	$\nabla \times \mathbf{H} = \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t}$	$\oint_C \mathbf{H} \cdot d\mathbf{l} = \int_S \left( \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t} \right) \cdot d\mathbf{s}$	(6.4)
*For a stationary surface <i>S</i> .			

In this chapter, we will examine Faraday's and Ampère's laws

### **Electromotive Force**

Electromotive force (voltage) induced by time-varying magnetic flux:

$$V_{\text{emf}} = -N \frac{d\Phi}{dt} = -N \frac{d}{dt} \int_{S} \mathbf{B} \cdot d\mathbf{s} \qquad (V)$$



**Figure 6-1:** The galvanometer (predecessor of the ammeter) shows a deflection whenever the magnetic flux passing through the square loop changes with time.

Magnetic fields can produce an electric current in a closed loop, but only if the magnetic flux linking the surface area of the loop changes with time. The key to the induction process is change.

### Three types of EMF

- 1. A time-varying magnetic field linking a stationary loop; the induced emf is then called the *transformer emf*,  $V_{\text{emf}}^{\text{tr}}$ .
- 2. A moving loop with a time-varying surface area (relative to the normal component of **B**) in a static field **B**; the induced emf is then called the *motional emf*,  $V_{\rm emf}^{\rm m}$ .
- **3.** A moving loop in a time-varying field **B**.

The total emf is given by

$$V_{\rm emf} = V_{\rm emf}^{\rm tr} + V_{\rm emf}^{\rm m}, \tag{6.7}$$

# Stationary Loop in Time-Varying **B**

It is important to remember that  $\mathbf{B}_{\text{ind}}$  serves to oppose the change in  $\mathbf{B}(t)$ , and not necessarily  $\mathbf{B}(t)$  itself.


 $V_{\rm emf}^{\rm tr} = -N \int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s}$  (transformer emf),

The connection between the direction of ds and the polarity of  $V_{\rm emf}^{\rm tr}$  is governed by the following right-hand rule: if ds points along the thumb of the right hand, then the direction of the contour C indicated by the four fingers is such that it always passes across the opening from the positive terminal of  $V_{\rm emf}^{\rm tr}$  to the negative terminal.


$$I = \frac{V_{\text{emf}}^{\text{tr}}}{R + R_{\text{i}}} \,. \tag{6.9}$$

For good conductors,  $R_i$  usually is very small, and it may be ignored in comparison with practical values of R.

The polarity of  $V_{\text{emf}}^{\text{tr}}$  and hence the direction of I is governed by **Lenz's law**, which states that the current in the loop is always in a direction that opposes the change of magnetic flux  $\Phi(t)$  that produced I.




(a) Loop in a changing B field




(b) Equivalent circuit

Figure 6-2: (a) Stationary circular loop in a changing magnetic field  $\mathbf{B}(t)$ , and (b) its equivalent circuit.




(a) Loop in a changing B field




(b) Equivalent circuit

$$V_{\rm emf}^{\rm tr} = -N \int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s}$$
 (transformer emf),



(a) Loop in a changing B field



(b) Equivalent circuit

 $\mathbf{B}_{\text{ind}}$  serves to oppose the *change* in  $\mathbf{B}(t)$ , and not necessarily  $\mathbf{B}(t)$  itself

### Faraday's Law

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$
 (Faraday's law).


Establish a k between B and E

$$V_{\text{emf}}^{\text{tr}} = \oint_C \mathbf{E} \cdot d\mathbf{l}.$$
  $V_{\text{em}} = -N \int_S \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s}$ 

$$= -N \int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s} \qquad \oint_{C} \mathbf{E} \cdot d\mathbf{l} = -\int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s},$$

Integral form of Faraday's law

Stokes's theorem



$$\int_{\Gamma} d\mathbf{B} d\mathbf{B} = \int_{\Gamma} d\mathbf{B} d\mathbf{B}$$

$$\int_{S} (\nabla \times \mathbf{E}) \cdot d\mathbf{s} = -\int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s},$$

#### **Example 6-1: Inductor in a Changing Magnetic Field**

An inductor is formed by winding N turns of a thin conducting wire into a circular loop of radius a. The inductor loop is in the x-y plane with its center at the origin, and connected to a resistor R, as shown in Fig. 6-3. In the presence of a magnetic field  $\mathbf{B} = B_0(\hat{\mathbf{y}}2 + \hat{\mathbf{z}}3) \sin \omega t$ , where  $\omega$  is the angular frequency, find

- (a) the magnetic flux linking a single turn of the inductor,
- (b) the transformer emf, given that N = 10,  $B_0 = 0.2$  T, a = 10 cm, and  $\omega = 10^3$  rad/s,
- (c) the polarity of  $V_{\text{emf}}^{\text{tr}}$  at t = 0, and
- (d) the induced current in the circuit for  $R = 1 \text{ k}\Omega$  (assume the wire resistance to be much smaller than R).




Figure 6-3: Circular loop with N turns in the x-y plane. The magnetic field is  $\mathbf{B} = B_0(\hat{\mathbf{y}}2 + \hat{\mathbf{z}}3) \sin \omega t$  (Example 6-1).

cont.

### Example 6-1 Solution

(a) The magnetic flux linking each turn of the **Solution:** inductor is

$$\Phi = \int_{S} \mathbf{B} \cdot d\mathbf{s}$$

$$= \int_{S} [B_0(\hat{\mathbf{y}} \, 2 + \hat{\mathbf{z}} \, 3) \sin \omega t] \cdot \hat{\mathbf{z}} \, ds$$

$$= 3\pi a^2 B_0 \sin \omega t.$$

(b) To find  $V_{\rm emf}^{\rm tr}$ , we can apply Eq. (6.8) or we can apply is at a higher potential than terminal 1 and the general expression given by Eq. (6.6) directly. The latter approach gives

$$V_{\text{emf}}^{\text{tr}} = -N \frac{d\Phi}{dt}$$

$$= -\frac{d}{dt} (3\pi N a^2 B_0 \sin \omega t)$$

$$= -3\pi N \omega a^2 B_0 \cos \omega t.$$

For N = 10, a = 0.1 m,  $\omega = 10^3$  rad/s, and  $B_0 = 0.2$  T,

 $V_{\rm emf}^{\rm tr} = -188.5\cos 10^3 t$ 




Figure 6-3: Circular loop with N turns in the x-y plane. The magnetic field is  $\mathbf{B} = B_0(\hat{\mathbf{y}}2 + \hat{\mathbf{z}}3) \sin \omega t$  (Example 6-1).

(V).

(A).

(c) At t = 0,  $d\Phi/dt > 0$  and  $V_{\text{emf}}^{\text{tr}} = -188.5 \text{ V}$ . Since the flux is increasing, the current I must be in the direction shown in Fig. 6-3 in order to satisfy Lenz's law. Consequently, terminal 2

 $V_{\rm emf}^{\rm tr} = V_1 - V_2$ 

 $= 0.19 \cos 10^3 t$ 

$$= -188.5$$
(d) The current *I* is given by

 $I = \frac{V_2 - V_1}{R}$  $=\frac{188.5}{10^3}\cos 10^3 t$ 

#### Example 6-2: Lenz's Law

Determine voltages  $V_1$  and  $V_2$  across the 2- $\Omega$  and 4- $\Omega$  resistors shown in Fig. 6-4. The loop is located in the x-y plane, its area is 4 m<sup>2</sup>, the magnetic flux density is  $\mathbf{B} = -\hat{\mathbf{z}}0.3t$  (T), and the internal resistance of the wire may be ignored.

**Solution:** The flux flowing through the loop is

$$\Phi = \int_{S} \mathbf{B} \cdot d\mathbf{s} = \int_{S} (-\hat{\mathbf{z}}0.3t) \cdot \hat{\mathbf{z}} ds$$
$$= -0.3t \times 4 = -1.2t$$

and the corresponding transformer emf is

 $V_{\rm emf}^{\rm tr} = -\frac{d\Phi}{dt} = 1.2 \qquad (V).$ The total voltage of 1.2 V is distributed across two resistors in series. Consequently,  $I = \frac{V_{\text{emf}}^{\text{u}}}{R_1 + R_2}$ 

 $=\frac{1.2}{2+4}=0.2 \text{ A},$ 

Figure 6-4: Circuit for Example 6-2.


and

(Wb),

$$V_1 = IR_1 = 0.2 \times 2 = 0.4 \text{ V},$$
  
 $V_2 = IR_2 = 0.2 \times 4 = 0.8 \text{ V}.$ 

### Ideal transformer

Transformer is used to convert the AC voltage from one voltage to another. An ideal transformer has infinite permeability, and the magnetic flux is confined within the core.



The directions of the currents flowing in the two coils,  $I_1$  and  $I_2$ , are defined such that, when  $I_1$  and  $I_2$  are both positive, the flux generated by  $I_2$  is opposite to that generated by  $I_1$ . The transformer gets its name from the fact that it transforms currents, voltages, and impedances between its primary and secondary circuits, and vice versa.

$$V_1 = -N_1 \frac{d\Phi}{dt}$$
.  $V_2 = -N_2 \frac{d\Phi}{dt}$ .  $\frac{V_1}{V_2} = \frac{N_1}{N_2}$ .

$$P_1 = P_2. \frac{I_1}{I_2} = \frac{N_2}{N_1}.$$

$$R_{\rm in} = \frac{V_2}{I_2} \left(\frac{N_1}{N_2}\right)^2 = \left(\frac{N_1}{N_2}\right)^2 R_{\rm L}.$$

### **Motional EMF**

Magnetic force on charge q moving with velocity  $\mathbf{u}$  in a magnetic field  $\mathbf{B}$ :


$$\mathbf{F}_{\mathbf{m}} = q(\mathbf{u} \times \mathbf{B}).$$

This magnetic force is equivalent to the electrical force that would be exerted on the particle by the (motional) electric field Em given by

$$\mathbf{E}_{\mathrm{m}} = \frac{\mathbf{F}_{\mathrm{m}}}{a} = \mathbf{u} \times \mathbf{B}.$$

This, in turn, induces a voltage difference between ends 1 and 2, with end 2 being at the higher potential. The induced voltage is

$$V_{\text{emf}}^{\text{m}} = V_{12} = \int_{2}^{1} \mathbf{E}_{\text{m}} \cdot d\mathbf{l} = \int_{2}^{1} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}.$$



**Figure 6-7:** Conducting wire moving with velocity **u** in a static magnetic field.

For the conducting wire,  $\mathbf{u} \times \mathbf{B} = \hat{\mathbf{x}}u \times \hat{\mathbf{z}}B_0 = -\hat{\mathbf{y}}uB_0$  and  $d\mathbf{l} = \hat{\mathbf{y}} dl$ . Hence,

$$V_{\rm emf}^{\rm m} = V_{12} = -u B_0 l. ag{6.25}$$

E points from 1 to 2

### **Motional EMF**

In general, if any segment of a closed circuit with contour C moves with a velocity  $\mathbf{u}$  across a static magnetic field  $\mathbf{B}$ , then the induced motional emf is given by

$$V_{\text{emf}}^{\text{m}} = \oint_C (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$
 (motional emf). (6.26)

Only those segments of the circuit that cross magnetic field lines contribute to  $V_{\rm emf}^{\rm m}$ .

### Example 6-3: Sliding Bar

The rectangular loop shown in **Fig. 6-8** has a constant width l, but its length  $x_0$  increases with time as a conducting bar slides with uniform velocity  $\mathbf{u}$  in a static magnetic field  $\mathbf{B} = \hat{\mathbf{z}}B_0x$ . Note that  $\mathbf{B}$  increases linearly with x. The bar starts from x = 0 at t = 0. Find the motional emf between terminals 1 and 2 and the current I flowing through the resistor R. Assume that the loop resistance  $R_i \ll R$ .

Note that B increases with x  $\mathbf{B} = \hat{\mathbf{z}}B_0x$ 


$$V_{\text{emf}}^{\text{m}} = V_{12} = V_{43} = \int_{3}^{4} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$

$$V_{4} - V_{3}^{3}$$

$$= \int_{3}^{4} (\hat{\mathbf{x}}u \times \hat{\mathbf{z}}B_{0}x_{0}) \cdot \hat{\mathbf{y}} dl = -uB_{0}x_{0}l.$$

The length of the loop is related to u by  $x_0 = ut$ . Hence

$$V_{\rm emf}^{\rm m} = -B_0 u^2 lt \qquad (V).$$



How to define the polarity of  $V_{emf}$  in this condition?


### Example 6-3: cont.

Use Faraday's law

#### Note that B increases with x

$$\mathbf{B} = \hat{\mathbf{z}} B_0 x$$

$$\Phi = \int_{S} \mathbf{B} \cdot d\mathbf{s} = \int_{S} (\hat{\mathbf{z}} B_0 x) \cdot \hat{\mathbf{z}} \, dx \, dy$$
$$= B_0 l \int_{0}^{x_0} x \, dx = \frac{B_0 l x_0^2}{2}$$




$$V_{\text{emf}} = -\frac{d\Phi}{dt} = -\frac{d}{dt} \left( \frac{B_0 l u^2 t^2}{2} \right) = -B_0 u^2 l t \qquad (V)$$

The same as the result obtained by the motional emf expression

The rectangular loop shown in **Fig. 6-9** is situated in the x-y plane and moves away from the origin with velocity  $\mathbf{u} = \hat{\mathbf{y}}5$  (m/s) in a magnetic field given by

$$\mathbf{B}(y) = \hat{\mathbf{z}} \, 0.2 e^{-0.1y} \qquad (T).$$

If  $R = 5 \Omega$ , find the current I at the instant that the loop sides are at  $y_1 = 2$  m and  $y_2 = 2.5$  m. The loop resistance may be ignored.



$$V_{12} = \int_{2}^{1} [\mathbf{u} \times \mathbf{B}(y_1)] \cdot d\mathbf{l} = \int_{l/2}^{-l/2} (\hat{\mathbf{y}} 5 \times \hat{\mathbf{z}} 0.2e^{-0.2}) \cdot \hat{\mathbf{x}} dx$$
$$= -e^{-0.2}l = -2e^{-0.2} = -1.637 \qquad (V).$$

$$\mathbf{B}(y_1) = \hat{\mathbf{z}} \, 0.2 e^{-0.1 y_1} = \hat{\mathbf{z}} \, 0.2 e^{-0.2} \tag{T}.$$

$$V_{43} = -u B(y_2) l = -5 \times 0.2e^{-0.25} \times 2 = -1.558$$
 (V).

$$I = \frac{V_{43} - V_{12}}{R} = \frac{0.079}{5} = 15.8 \text{ (mA)}.$$

### **Example 6-5: Moving Rod Next to a Wire**

The wire shown in Fig. 6-10 carries a current I = 10 A. A 30-cm-long metal rod moves with a constant velocity  $\mathbf{u} = \hat{\mathbf{z}}5$  m/s. Find  $V_{12}$ .

$$\mathbf{B} = \hat{\mathbf{\Phi}} \frac{\mu_0 I}{2\pi r}$$

$$\mathbf{B} \odot$$

$$\mathbf{B} \odot$$

$$\mathbf{W} \text{ire}$$

$$\mathbf{B} \odot$$

$$\mathbf{W} \text{ire}$$

$$\mathbf{B} \odot$$

$$V_{12} = \int_{40 \text{ cm}}^{10 \text{ cm}} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$


$$= \int_{40 \text{ cm}}^{10 \text{ cm}} (\hat{\mathbf{z}} 5 \times \hat{\boldsymbol{\phi}} \frac{\mu_0 I}{2\pi r}) \cdot \hat{\mathbf{r}} dr$$

$$= -\frac{5\mu_0 I}{2\pi} \int_{40 \text{ cm}}^{10 \text{ cm}} \frac{dr}{r}$$

$$= -\frac{5 \times 4\pi \times 10^{-7} \times 10}{2\pi} \times \ln\left(\frac{10}{40}\right)$$


 $= 13.9 \quad (\mu V).$ 

# EM Motor / Generator Reciprocity



Motor: Electrical to mechanical energy conversion

Wires with current are subject to force exerted by magnetic field



Generator: Mechanical to electrical energy conversion

Time varying magnetic flux induces current in circuit

### **EM Generator EMF**

As the loop rotates with an angular velocity  $\omega$  about its own axis, segment 1–2 moves with velocity  $\mathbf{u}$  given by

$$\mathbf{u} = \hat{\mathbf{n}}\omega \, \frac{w}{2}$$

Also:

$$\hat{\mathbf{n}} \times \hat{\mathbf{z}} = \hat{\mathbf{x}} \sin \alpha$$

Segment 3-4 moves with velocity –**u**. Hence:

$$V_{\text{emf}}^{\text{m}} = V_{14} = \int_{2}^{1} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l} + \int_{4}^{3} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$

$$= \int_{-l/2}^{l/2} \left[ \left( \hat{\mathbf{n}} \omega \frac{w}{2} \right) \times \hat{\mathbf{z}} B_{0} \right] \cdot \hat{\mathbf{x}} dx$$

$$+ \int_{l/2}^{-l/2} \left[ \left( -\hat{\mathbf{n}} \omega \frac{w}{2} \right) \times \hat{\mathbf{z}} B_{0} \right] \cdot \hat{\mathbf{x}} dx.$$




Figure 6-12: A loop rotating in a magnetic field induces an emf.

$$V_{\text{emf}}^{\text{m}} = wl\omega B_0 \sin \alpha = A\omega B_0 \sin \alpha,$$
$$\alpha = \omega t + C_0,$$

$$V_{\rm emf}^{\rm m} = A\omega B_0 \sin(\omega t + C_0) \qquad (V)$$

# **Another Way**

$$\Phi = \int_{S} \mathbf{B} \cdot d\mathbf{s} = \int_{S} \hat{\mathbf{z}} B_{0} \cdot \hat{\mathbf{n}} ds$$

$$= B_{0} A \cos \alpha$$

$$= B_{0} A \cos(\omega t + C_{0})$$

$$V_{\text{emf}} = -\frac{d\Phi}{dt} = -\frac{d}{dt} [B_0 A \cos(\omega t + C_0)]$$
$$= A\omega B_0 \sin(\omega t + C_0),$$

# Moving Conductor in Time-Varying Magnetic Field

$$V_{\text{emf}} = V_{\text{emf}}^{\text{tr}} + V_{\text{emf}}^{\text{m}}$$

$$= \oint_{C} \mathbf{E} \cdot d\mathbf{l}$$

$$= -\int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s} + \oint_{C} (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}.$$
Equivalent

$$V_{\text{emf}} = -\frac{d\Phi}{dt} = -\frac{d}{dt} \int_{S} \mathbf{B} \cdot d\mathbf{s}$$
 (total emf).

# Example 6-6

$$\mathbf{B} = \hat{\mathbf{z}}B_0\cos\omega t$$

$$\Phi = B_0 A \cos \omega t$$
 From p. 20

$$\Phi = B_0 A \cos^2 \omega t$$

$$V_{\text{emf}} = -\frac{\partial \Psi}{\partial t}$$
$$= -\frac{\partial}{\partial t} (B_0 A \cos^2 \omega t)$$

 $=2B_0A\omega\cos\omega t\sin\omega t=B_0A\omega\sin2\omega t$ 




Figure 6-12: A loop rotating in a magnetic field induces an emf.

### Displacement Current

$$\nabla \times \mathbf{H} = \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t}$$
 (Ampère's law). (6.41)

Integrating both sides of Eq. (6.41) over an arbitrary open surface S with contour C, we have

$$\int_{S} (\nabla \times \mathbf{H}) \cdot d\mathbf{s} = \int_{S} \mathbf{J} \cdot d\mathbf{s} + \int_{S} \frac{\partial \mathbf{D}}{\partial t} \cdot d\mathbf{s}. \tag{6.42}$$
This term is This term must conduction represent a current  $I_{C}$  current

Application of Stokes's theorem gives:

$$\oint_C \mathbf{H} \cdot d\mathbf{l} = I_c + \int_S \frac{\partial \mathbf{D}}{\partial t} \cdot d\mathbf{s} \quad \text{(Ampère's law)}$$

### Displacement Current

$$\oint_C \mathbf{H} \cdot d\mathbf{l} = I_c + \int_S \frac{\partial \mathbf{D}}{\partial t} \cdot d\mathbf{s} \quad \text{(Ampère's law)}$$

Define the displacement current as:

$$I_{\rm d} = \int_{S} \mathbf{J}_{\rm d} \cdot d\mathbf{s} = \int_{S} \frac{\partial \mathbf{D}}{\partial t} \cdot d\mathbf{s}, \quad (6.44)$$

where  $\mathbf{J}_{d} = \partial \mathbf{D}/\partial t$  represents a *displacement current density*. In view of Eq. (6.44),

$$\oint \mathbf{H} \cdot d\mathbf{l} = I_{c} + I_{d} = I, \tag{6.45}$$

Conduction current density

$$J_{c} = \sigma E$$

Displacement current density

$$J_d = \varepsilon \frac{\partial E}{\partial t}$$

The displacement current does not involve real charges; it is an equivalent current that depends on  $\partial \mathbf{D}/\partial t$ 

# Capacitor Circuit

Given: Wires are perfect conductors and capacitor insulator material is perfect dielectric.

#### For Surface $S_1$ :

$$I_1 = I_{1c} + I_{1d}$$

$$I_{1c} = C \frac{dV_C}{dt} = C \frac{d}{dt} (V_0 \cos \omega t) = -C V_0 \omega \sin \omega t$$

$$I_{1d} = 0$$
 (**D** = 0 in perfect conductor)

 $I_1 = I_2$  ensures the continuity of total current flow through the circuit

Although the displacement current does not transport free charges, it behaves like a real current

#### For Surface $S_2$ :

 $I_1 = I_{1c}$ 

$$I_2 = I_{2c} + I_{2d}$$

$$I_{2\mathrm{c}}=0$$
 (perfect dielectric  $\sigma=0$ )

$$\mathbf{E} = \hat{\mathbf{y}} \; \frac{V_{\rm c}}{d} = \hat{\mathbf{y}} \; \frac{V_0}{d} \cos \omega t$$

$$I_{2d} = \int_{S} \frac{\partial \mathbf{D}}{\partial t} \cdot d\mathbf{s}$$

$$= \int \left[ \frac{\partial}{\partial t} \left( \hat{\mathbf{y}} \, \frac{\varepsilon V_0}{d} \cos \omega t \right) \right] \cdot (\hat{\mathbf{y}} \, ds)$$

$$= -\frac{\varepsilon A}{d} V_0 \omega \sin \omega t = -C V_0 \omega \sin \omega t$$

Conclusion: 
$$I_1 = I_2$$

$$C = \epsilon A/d$$

#### **Example 6-7: Displacement Current Density**

The conduction current flowing through a wire with conductivity  $\sigma = 2 \times 10^7$  S/m and relative permittivity  $\varepsilon_r = 1$  is given by  $I_c = 2 \sin \omega t$  (mA). If  $\omega = 10^9$  rad/s, find the displacement current.

**Solution:** The conduction current  $I_c = JA = \sigma EA$ , where A is the cross section of the wire. Hence,

$$E = \frac{I_{\rm c}}{\sigma A} = \frac{2 \times 10^{-3} \sin \omega t}{2 \times 10^{7} A}$$
$$= \frac{1 \times 10^{-10}}{A} \sin \omega t \qquad (\text{V/m}).$$

Application of Eq. (6.44), with  $D = \varepsilon E$ , leads to

$$I_{\rm d} = J_{\rm d}A$$
 where we us
$$= \varepsilon A \frac{\partial E}{\partial t}$$

$$= \varepsilon A \frac{\partial}{\partial t} \left( \frac{1 \times 10^{-10}}{A} \sin \omega t \right)$$

$$= \varepsilon \omega \times 10^{-10} \cos \omega t = 0.885 \times 10^{-12} \cos \omega t \quad (A),$$

where we used  $\omega = 10^9$  rad/s and  $\varepsilon = \varepsilon_0 = 8.85 \times 10^{-12}$  F/m. Note that  $I_c$  and  $I_d$  are in phase quadrature (90° phase shift between them). Also,  $I_d$  is about nine orders of magnitude smaller than  $I_c$ , which is why the displacement current usually is ignored in good conductors.

# **Boundary Conditions**

**Table 6-2:** Boundary conditions for the electric and magnetic fields.

Field Components	General Form	Medium 1 Dielectric	Medium 2 Dielectric	Medium 1 Dielectric	Medium 2 Conductor
Tangential E	$\hat{\mathbf{n}}_2 \times (\mathbf{E}_1 - \mathbf{E}_2) = 0$	$E_{1t} = E_{2t}$		$E_{1t} = E_{2t} = 0$	
Normal D	$\hat{\mathbf{n}}_2 \cdot (\mathbf{D}_1 - \mathbf{D}_2) = \rho_{\mathbf{s}}$	$D_{1n} - D_{2n} = \rho_{s}$		$D_{1n} = \rho_{\rm s}$	$D_{2n}=0$
Tangential H	$\hat{\mathbf{n}}_2 \times (\mathbf{H}_1 - \mathbf{H}_2) = \mathbf{J}_s$	$H_{1t} = H_{2t}$		$H_{1t} = J_{s}$	$H_{2t}=0$
Normal B	$\hat{\mathbf{n}}_2 \cdot (\mathbf{B}_1 - \mathbf{B}_2) = 0$	$B_{1n} = B_{2n}$		B <sub>1n</sub> =	$=B_{2n}=0$

Notes: (1)  $\rho_s$  is the surface charge density at the boundary; (2)  $\mathbf{J}_s$  is the surface current density at the boundary; (3) normal components of all fields are along  $\hat{\mathbf{n}}_2$ , the outward unit vector of medium 2; (4)  $E_{1t} = E_{2t}$  implies that the tangential components are equal in magnitude and parallel in direction; (5) direction of  $\mathbf{J}_s$  is orthogonal to  $(\mathbf{H}_1 - \mathbf{H}_2)$ .

# Charge Current Continuity Equation

Current I out of a volume is equal to rate of decrease of charge Q contained in that volume:

$$I = -\frac{dQ}{dt} = -\frac{d}{dt} \int_{V} \rho_{V} dV$$

$$\oint_{S} \mathbf{J} \cdot d\mathbf{s} = -\frac{d}{dt} \int_{V} \rho_{V} \, dV$$

$$\oint_{S} \mathbf{J} \cdot d\mathbf{s} = \int_{V} \nabla \cdot \mathbf{J} \, dV = -\frac{d}{dt} \int_{V} \rho_{V} \, dV$$

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{V}}{\partial t} , \quad (6.54)$$




Figure 6-14: The total current flowing out of a volume V is equal to the flux of the current density  $\mathbf{J}$  through the surface S, which in turn is equal to the rate of decrease of the charge enclosed in  $\mathcal{V}$ .

Volume current density

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t} , \qquad (6.54)$$

**Used Divergence Theorem** 


which is known as the *charge-current continuity relation*, or simply the *charge continuity equation*.

# Charge Current Continuity Equation

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t} , \qquad (6.54) \qquad \oint_{\mathbf{S}} \mathbf{J} \cdot d\mathbf{s} = -\frac{d}{dt} \int_{\mathbf{v}} \rho_{\mathbf{v}} \, d\mathbf{v}$$

$$\nabla \cdot \mathbf{J} = 0,$$

Net current flowing out of  $\Delta V$  is zero



$$\oint_{S} \mathbf{J} \cdot d\mathbf{s} = -\frac{d}{dt} \int_{V} \rho_{V} \, dV$$

$$\oint_{S} \mathbf{J} \cdot d\mathbf{s} = 0 \quad \text{(Kirchhoff's current law)}.$$

$$\sum_{i} I_{i} = 0 \quad \text{(Kirchhoff's current law)},$$

# Ampère's Law for Dynamic Fields

In case the charge density does not change with time

$$\nabla \times \mathbf{H} = \mathbf{J}$$

$$0 = \nabla \cdot \mathbf{J}$$

$$\nabla \cdot (\nabla \times \mathbf{H}) = \nabla \cdot \mathbf{J} = \mathbf{0}$$

In case the charge density changes with time

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t} , \qquad (6.54)$$

$$\nabla \cdot (\nabla \times \boldsymbol{H}) - \frac{\partial \rho_v}{\partial t} = \nabla \cdot \boldsymbol{J}$$

$$\nabla \cdot \mathbf{D} = \rho_{\mathbf{v}}$$

$$\nabla \cdot \mathbf{D} = \rho_{V}$$

$$\nabla \cdot (\nabla \times \mathbf{H}) - \frac{\partial (\nabla \cdot \mathbf{D})}{\partial t} = \nabla \cdot \mathbf{J}$$
Added by Maxwell

Need to add a term for dynamic field

$$\nabla \times \mathbf{H} = \mathbf{J} + \frac{\partial \mathbf{D}}{\partial t} \qquad \text{(Ampère's law)}.$$

### Charge Dissipation

Question 1: What happens if you place a certain amount of free charge inside of a material? Answer: The charge will move to the surface of the material, thereby returning its interior to a neutral state.

#### Question 2: How fast will this happen?

Answer: It depends on the material; in a good conductor, the charge dissipates in less than a femtosecond, whereas in a good dielectric, the process may take several hours.

Derivation of charge density equation:

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t} \ . \tag{6.58}$$

In a conductor, the point form of Ohm's law, given by Eq. (4.63), states that  $\mathbf{J} = \sigma \mathbf{E}$ . Hence,

$$\sigma \nabla \cdot \mathbf{E} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t} \,. \tag{6.59}$$

Next, we use Eq. (6.1),  $\nabla \cdot \mathbf{E} = \rho_{\rm v}/\varepsilon$ , to obtain the partial differential equation

$$\frac{\partial \rho_{\mathbf{v}}}{\partial t} + \frac{\sigma}{\varepsilon} \rho_{\mathbf{v}} = 0. \tag{6.60}$$

Cont.

### Solution of Charge Dissipation Equation

$$\frac{\partial \rho_{\rm v}}{\partial t} + \frac{\sigma}{\varepsilon} \rho_{\rm v} = 0$$

Given that  $\rho_{\rm v} = \rho_{\rm vo}$  at t=0, the solution of Eq. (6.60) is

$$\rho_{\rm v}(t) = \rho_{\rm vo} e^{-(\sigma/\varepsilon)t} = \rho_{\rm vo} e^{-t/\tau_{\rm r}} \qquad ({\rm C/m^3}), \qquad (6$$

where  $\tau_{\rm r} = \varepsilon/\sigma$  is called the *relaxation time constant*.

For copper:  $\tau_{\rm r} = 1.53 \times 10^{-19} {\rm s}$ 

For mica:  $\tau_r = 5.31 \times 10^4 \text{ s.} = 15 \text{ hours}$ 

#### Example 6-8: Relating E to H

In a nonconducting medium with  $\varepsilon = 16\varepsilon_0$  and  $\mu = \mu_0$ , the electric field intensity of an electromagnetic wave is

$$\mathbf{E}(z,t) = \hat{\mathbf{x}} \, 10 \sin(10^{10}t - kz) \qquad \text{(V/m)}. \tag{6.88}$$

Determine the associated magnetic field intensity  $\mathbf{H}$  and find the value of k.

**Solution:** We begin by finding the phasor  $\widetilde{\mathbf{E}}(z)$  of  $\mathbf{E}(z,t)$ . Since  $\mathbf{E}(z,t)$  is given as a sine function and phasors are defined in this book with reference to the cosine function, we rewrite Eq. (6.88) as

$$\mathbf{E}(z,t) = \hat{\mathbf{x}} \, 10 \cos(10^{10}t - kz - \pi/2) \qquad \text{(V/m)}$$
$$= \Re \left[ \widetilde{\mathbf{E}}(z) \, e^{j\omega t} \right], \qquad (6.89)$$

with  $\omega = 10^{10}$  (rad/s) and

$$\widetilde{\mathbf{E}}(z) = \hat{\mathbf{x}} \, 10e^{-jkz} e^{-j\pi/2} = -\hat{\mathbf{x}} j \, 10e^{-jkz}.$$
 (6.90)

Cont.

To find both  $\mathbf{H}(z)$  and k, we will perform a "circle": we will use the given expression for  $\mathbf{\tilde{E}}(z)$  in Faraday's law to find  $\mathbf{\tilde{H}}(z)$ ; then we will use  $\mathbf{\tilde{H}}(z)$  in Ampère's law to find  $\mathbf{\tilde{E}}(z)$ , which we will then compare with the original expression for  $\mathbf{\tilde{E}}(z)$ ; and the comparison will yield the value of k. Application of Eq. (6.87) gives

$$\nabla \times \widetilde{\mathbf{E}} = -j\omega\mu\widetilde{\mathbf{H}}$$

$$\widetilde{\mathbf{H}}(z) = -\frac{1}{j\omega\mu} \nabla \times \widetilde{\mathbf{E}}$$

$$= -\frac{1}{j\omega\mu} \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ \frac{\partial}{\partial x} & \frac{\partial}{\partial y} & \frac{\partial}{\partial z} \\ -j10e^{-jkz} & 0 & 0 \end{vmatrix}$$

$$= -\frac{1}{j\omega\mu} \left[ \hat{\mathbf{y}} \frac{\partial}{\partial z} (-j10e^{-jkz}) \right]$$

$$= -\hat{\mathbf{y}} j \frac{10k}{\omega\mu} e^{-jkz}. \tag{6.91}$$

# Example 6-8 cont.

So far, we have used Eq. (6.90) for  $\mathbf{E}(z)$  to find  $\mathbf{H}(z)$ , but kremains unknown. To find k, we use  $\mathbf{H}(z)$  in Eq. (6.86) to find

 ${}^{36}\widetilde{\mathbf{E}}(z)$ :

$$\widetilde{\mathbf{E}}(z) = \frac{1}{j\omega\varepsilon} \nabla \times \widetilde{\mathbf{H}} \qquad \nabla \times \widetilde{\mathbf{H}} = j\omega\varepsilon \widetilde{\mathbf{E}}$$

$$= \frac{1}{j\omega\varepsilon} \left[ -\hat{\mathbf{x}} \frac{\partial}{\partial z} \left( -j \frac{10k}{\omega\mu} e^{-jkz} \right) \right]$$

$$= -\hat{\mathbf{x}} j \frac{10k^2}{\omega^2 \mu\varepsilon} e^{-jkz}. \qquad (6.92)$$

(6.93)

Equating Eqs. (6.90) and (6.92) leads to

$$k^2 = \omega^2 \mu \varepsilon,$$

$$\widetilde{\mathbf{E}}(z) = \hat{\mathbf{x}} \, 10e^{-jkz} e^{-j\pi/2} = -\hat{\mathbf{x}} j \, 10e^{-jkz}$$
(6.90)

or

$$k = \omega \sqrt{\mu \varepsilon}$$

$$= 4\omega \sqrt{\mu_0 \varepsilon_0}$$

$$= \frac{4\omega}{\varepsilon} = \frac{4 \times 10^{10}}{3 \times 10^8} = 133 \quad \text{(rad/m)}.$$

Cont.

# Example 6-8 cont.

With k known, the instantaneous magnetic field intensity is then given by

$$\mathbf{H}(z,t) = \mathfrak{Re}\left[\widetilde{\mathbf{H}}(z) e^{j\omega t}\right]$$

$$= \mathfrak{Re}\left[-\hat{\mathbf{y}}j \frac{10k}{\omega\mu}e^{-jkz}e^{j\omega t}\right]$$

$$= \hat{\mathbf{y}} 0.11 \sin(10^{10}t - 133z) \qquad (A/m). \qquad (6.94)$$

We note that k has the same expression as the phase constant of a lossless transmission line [Eq. (2.49)].

# Summary

#### **Chapter 6 Relationships**

#### Faraday's Law

$$V_{\text{emf}} = -\frac{d\Phi}{dt} = -\frac{d}{dt} \int_{S} \mathbf{B} \cdot d\mathbf{s} = V_{\text{emf}}^{\text{tr}} + V_{\text{emf}}^{\text{m}}$$

#### Transformer

$$V_{\text{emf}}^{\text{tr}} = -N \int_{S} \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{s}$$
 (N loops)

#### Motional

$$V_{\rm emf}^{\rm m} = \oint_C (\mathbf{u} \times \mathbf{B}) \cdot d\mathbf{l}$$

#### **Charge-Current Continuity**

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho_{\mathbf{v}}}{\partial t}$$

#### **EM Potentials**

$$\mathbf{E} = -\nabla V - \frac{\partial \mathbf{A}}{\partial t}$$
$$\mathbf{B} = \nabla \times \mathbf{A}$$

#### **Current Density**

Conduction 
$$J_c = \sigma E$$

Displacement  $J_d = \frac{\partial D}{\partial t}$ 

#### **Conductor Charge Dissipation**

$$\rho_{\rm v}(t) = \rho_{\rm vo}e^{-(\sigma/\varepsilon)t} = \rho_{\rm vo}e^{-t/\tau_{\rm r}}$$