A Literate Approach for Improving the Verifiability, Reusability and Reproducibility of Scientific Computing Software

Spencer Smith, Jacques Carette, Dan Szymczak, Steven Palmer

Computing and Software Department
Faculty of Engineering
McMaster University

CAIMS 2017, Third Canadian Symposium in Numerical Analysis and Scientific Computing (CSNASC): Simulation, July 18, 2017

Abstract

- **Goal** – Improve quality of {SCS}
- **Idea** – Adapt ideas from SE
- **Document Driven Design**
  - Good – improves quality
  - Bad – “manual” approach is too much work
- **Solution**
  - Capture knowledge
  - Generate all things
  - Avoid duplication
  - Traceability
- **Showing great promise**
  - Significant work yet to do
  - Looking for examples/partners

Glass

Physical Science










CERTIFIED

Motivation: Improve Quality



"Faked" Rational Design Process



SWHS example at https://github.com/smiths/swhs

The Challenge

- Documentation provides advantages
  - Improves verifiability, reusability, reproducibility, etc.
  - From **?**
    - easier reuse of old designs
    - better communication about requirements
    - more useful design reviews
    - etc.
  - New doc found 27 errors (**?**)
  - Developers see advantage (**?**)
- But documentation is felt to be ...
  - Too long
  - Too difficult to maintain
  - Not amenable to change
  - Too tied to waterfall process
  - Reports counterproductive (**?**)
- **The Solution?**


GENERATE
ALL THE THINGS!
memegenerator.net

Knowledge Capture

Drasil


SRS (*LaTeX*)
SRS (*html*)
MG
SRS (*verbose*)
Makefile
MIS
Test cases
Matlab
C Code
Recipes
$-\nabla \cdot \mathbf{q} + q''' = \rho C \frac{\partial T}{\partial t}$
uncertainty, typical values etc.
h_c is the heat transfer coeff between clad and coolant
W = J/s = kg m^2 s^{-3}
$L > 0$


Chunk
id : String
is-a
is-a
NamedIdea
term : Sentence
getA : Sentence +1
SymbolForm
symbol : Symbol
is-a
is-a
CommonIdea
abrv : Sentence +1
Concept
defn : Sentence
cdom : Concept c => [c]
may have
may have
is-a
Unit
unit : USymb
Quantity
typ : Space
get-symb : SymbolForm s => s +1
get-unit : Unit u => u +1
is-a
is-a
is-a
Unitary
unit : Unit u => u
Constrained
constraints : [Constraint]
reasVal : Expr +1
UncertainQuantity
uncert : Double +1

J_{tol} in SRS.pdf

Refname	**DD:sdf.tol**
Label	J_{tol}
Units	
Equation	$J_{tol} = \log\left(\log\left(\frac{1}{1-P_{btol}}\right)\frac{\left(\frac{a}{1000}\frac{b}{1000}\right)^{m-1}}{k\left((E*1000)\left(\frac{h}{1000}\right)^2\right)^m * LDF}\right)$
Description	J_{tol} is the stress distribution factor (Function) based on Pbtol P_{btol} is the tolerable probability of breakage a is the plate length (long dimension) b is the plate width (short dimension) m is the surface flaw parameter k is the surface flaw parameter E is the modulus of elasticity of glass h is the actual thickness LDF is the load duration factor

J_{tol} in SRS.tex

```
\noindent \begin{minipage}{\textwidth}
\begin{tabular}{p{0.2\textwidth} p{0.73\textwidth}}
\toprule \textbf{Refname} & \textbf{DD:sdf.tol}
\phantomsection
\label{DD:sdf.tol}
\\ \midrule \\
Label & $J_{tol}$
\\ \midrule \\
Units &
\\ \midrule \\
Equation & $J_{tol}$ = $\log\left(\log\left(\frac{1}{1-P_
    {btol}}\right)\frac{\left(\frac{a}{1000}\frac{b
    }{1000}\right)^{m-1}}{k\left(\left(E*1000\right)\left
    (\frac{h}{1000}\right)^{2}\right)^{m}*LDF}\right)$
\\ \midrule \\
Description & $J_{tol}$ is the stress distribution factor
     (Function) based on
              Pbtol\newline$P_{btol}$ is the tolerable
                 probability of breakage ...
\end{minipage}\\
```

J_{tol} in SRS.html

```
<a id="">
<div class="equation">
<em>J<sub>tol</sub></em> = log(log(<div class="fraction">
<span class="fup">
1
</span>
<span class="fdn">
1 &minus; <em>P<sub>btol</sub></em>
</span>
</div>)<div class="fraction">
<span class="fup">
(<div class="fraction">
<span class="fup">
<em>a</em>
</span>
<span class="fdn">
1000
</span>
</div><div class="fraction">
...
```

J_{tol} in Python

```
def calc_j_tol(inparams):
    j_tol = math.log((math.log(1.0 / (1.0 - inparams.
        pbtol))) * ((((inparams.a / 1000.0) * (inparams.b
         / 1000.0)) ** (inparams.m - 1.0)) / ((inparams.k
         * (((inparams.E * 1000.0) * ((inparams.h /
        1000.0) ** 2.0)) ** inparams.m)) * inparams.ldf))
        )
    return j_tol
```

J_{tol} in Java

```
public static double calc_j_tol(InputParameters inparams)
     {
         double j_tol = Math.log((Math.log(1.0 / (1.0 -
             inparams.pbtol))) * ((Math.pow((inparams.a /
             1000.0) * (inparams.b / 1000.0), inparams.m -
              1.0)) / ((inparams.k * (Math.pow((inparams.E
              * 1000.0) * (Math.pow(inparams.h / 1000.0,
             2.0)), inparams.m))) * inparams.ldf)));
         return j_tol;
     }
```

J_{tol} in Drasil (Haskell)

```
stressDistFac = makeVC "stressDistFac" (nounPhraseSP
  $ "stress distribution" ++ " factor (Function)") cJ

sdf_tol = makeVC "sdf_tol" (nounPhraseSP $
  "stress distribution" ++
  " factor (Function) based on Pbtol")
  (sub (stressDistFac ^. symbol) (Atomic "tol"))

tolStrDisFac_eq :: Expr
tolStrDisFac_eq = log (log ((1) / ((1) - (C pb_tol)))
  * ((Grouping (((C plate_len) / (1000)) * ((C
      plate_width) / (1000)))) :^
  ((C sflawParamM) - (1)) / ((C sflawParamK) *
  (Grouping (Grouping ((C mod_elas) * (1000)) *
  (square (Grouping ((C act_thick) / (1000))))
  )) :^ (C sflawParamM) * (C loadDF))))

tolStrDisFac :: QDefinition
tolStrDisFac = mkDataDef sdf_tol tolStrDisFac_eq
```

J_{tol} without Unit Conversion

```
tolStrDisFac_eq :: Expr
tolStrDisFac_eq = log (log ((1) / ((1) - (C pb_tol)))
  * ((Grouping ((C plate_len) * (C plate_width))) :^
  ((C sflawParamM) - (1)) / ((C sflawParamK) *
  (Grouping ((C mod_elas) * (square (C act_thick)))) :^ (
     C sflawParamM) * (C loadDF))))
```

Traceability Graph



Verifiability

Var	Constraints	Typical Value	Uncertainty
L	$L > 0$	1.5 m	10%
ρ_P	$\rho_P > 0$	1007 kg/m^3	10%

$$E_W = \int_0^t h_C A_C (T_C - T_W(t))dt - \int_0^t h_P A_P (T_W(t) - T_P(t))dt$$

- If wrong, wrong everywhere
- Sanity checks captured and reused
- Generate guards against invalid input
- Generate test cases
- Generate view suitable for inspection
- Traceability for verification of change

Reusability

- De-embed knowledge
- Reuse throughout document
  - Units
  - Symbols
  - Descriptions
  - Traceability information
- Reuse between documents
  - SRS
  - MIS
  - Code
  - Test cases
- Reuse between projects
  - Knowledge reuse
  - A family of related models, or reuse of pieces
  - Conservation of thermal energy
  - Interpolation
  - Etc.

Reproducibility

- Usual emphasis is on reproducing code execution
- However, **?** show reproducibility challenges due to undocumented:
  - Assumptions
  - Modifications
  - Hacks
- Shouldn't it be easier to independently replicate the work of others?
- Require theory, assumptions, equations, etc.
- Drasil can potentially check for completeness and consistency

NO

Future Work


ASTM F2248-09
10.00
1.00
3-Second duration equivalent design pressure (kPa)
6
60
Standoff distance (m)
W = 4.50 kg
W = 9.10 kg
W = 14.0 kg
W = 18.0 kg
W = 23.0 kg
W = 27.0 kg
W = 32.0 kg
W = 36.0 kg
W = 41.0 kg
W = 45.0 kg
W = 91.0 kg
W = 140 kg
W = 180 kg
W = 230 kg
W = 270
W = 320 kg
W = 360 kg
W = 410 kg

Drasil Framework for LSS

- SCS has the opportunity to lead other software fields
- Document driven design is feasible
- Requires an investment of time
- Documentation does not have to be painful
- Develop/refactor via practical case studies
- Ontology may naturally emerge





References I