

z/OS SDSF Hidden Treasures

August 17, 2023 Gary Puchkoff (presenting) Ken Jonas and Rob Scott authors

puchkoff@us.ibm.com

Agenda



- General Tips
- Tables
- Slash command
- Browse (next, prev, defaults, findlim)
- Using sectrace
- REXX (rgen, stems)



GENERAL TIPS

General Tips



- Use SET DISPLAY ON to show current settings of your prefix and owner
- Use SET ACTION ON|SHORT to display valid action characters
- Use PREFIX ** and OWNER userid to default to your own jobs
 - PREFIX ** is a special case so the H panel will display all jobs
- Use SET SCREEN to change display attributes

Display Values



- Use SET DISPLAY ON to show your current prefix and owner
- Saved in ISPF profile

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 713-718 (718)
COMMAND INPUT ===> set display
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
NP JOBNAME JobID
                                Prty Queue
                                                C Pos
                                                        SAff ASys Status
                      Owner
                                   1 PRINT
                                                    558
    SUBRTE
             STC05594 SUBJCL
    PRDUTLO4 JOBO5595 SUBJCL
                                   1 PRINT
                                                    559
    VTDRS86
             JOBO5586 SUBJCL
                                   1 PRINT
                                                    560
    SUBRTE
             STC05596 SUBJCL
                                   1 PRINT
                                                    561
```

Tip: **ON** is the default

Display Action Characters



- Use SET ACTION ON | OFF | SHORT to display valid action characters for the panel
- Saved in the ISPF profile

```
Display Filter View Print Options Search Help
SDSF HELD OUTPUT DISPLAY ALL CLASSES LINES 236.536
                                                       LINE 522-531 (531)
COMMAND INPUT ===> set action
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,//-Block,%-RunExec,?-JDS,=-Repeat,A-Release,C-Cancel,
ACTION=H-Hold, JS-JobStep, L-List, LL-ListLong, O-Release, OK-ReleaseKeep, P-Purge,
ACTION=Q-OutDesc,S-Browse,Sn-BrowseLocDS,SB-ISPFBrowse,SE-ISPFEdit,SJ-JCLEdit,
ACTION=X Print, XC-PrintClose, XD-PrintDS, XDC-PrintDSClose, XF-PrintFile,
ACTION=XFC-PrintFileClose.XS-PrintSysout.XSC-PrintSysoutClose
     JOBNAME JobID
                       Owner
                                Prty C ODisp Dest
                                                                   REC-Cnt PAGE
                                 144 K HOLD LOCAL
     SUBJCL
              STC05584 SUBJCL
                                                                       56
     SUBRTE
              STC05588 SUBJCL
                                 144 K HOLD
                                             LOCAL
                                                                       54
     LOGWRTR STC05587 SUBJCL
                                 144 K HOLD LOCAL
  Display Filter View Print Options Search Help
SDSF HELD OUTPUT DISPLAY ALL CLASSES LINES 236,536
                                                       LINE 522-531 (531)
                                                              SCROLL ===> HALF
COMMAND INPUT ===> set action short
PREFIX=** DEST=(ALL) OWNER=* SYSNAME=*
@CTION=+,/,//,%,?,=,A,C,H,JS,L,LL,O,OK,P,Q,S,Sn,SB,SE,SJ,X,XC,XD,XDC,XF,XFC,X$
ACTION=XSC
     JOBNAME
                                Prtv C ODisp Dest
                                                                  REC-Cnt PAGE
              JobID
                       Owner
     SUBJCL
              STC05584 SUBJCL
                                 144 K HOLD LOCAL
                                                                       56
     SUBRTE
              STC05588 SUBJCL
                                 144 K HOLD LOCAL
                                                                       54
     LOGWRTR STC05587 SUBJCL
                                 144 K HOLD
                                             LOCAL
```



TABLES

Table Tips



- Fast filter rows (SELECT command)
- Position to start of column (LOCATE command)
- Reorder columns and change width (ARRANGE command)
- Show contents of row (/ action)
- Advanced filter rows (FILTER command)
- Printing and copying a table (SNAP command)
- Block and repeat overtypes (// and = actions)
- Overtype multiple values in same column (+ overtype)
- Run REXX exec against row (% action)
- Change NP column width (+ action or ARRANGE command)
- Actions and overtypes from the command line
- Point-and-shoot
- Searching data set lists (SRCH)

Fast Path Select



- Probably the best hidden treasure in the product!
- SELECT | S pattern1 [pattern2]
 - Use S with no operands to reset
- Temporary filter while accessing table
- Not saved in profile or across commands
- Usually names a fixed field pattern
 - Operands vary based on panel
- Overrides prefix and owner is authorized
 - Use instead of changing your PREFIX when you want to filter jobs

Fast Path Select



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-26 (572)
COMMAND INPUT ===> s r*
                                                               SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=*
     JOBNAME
             JobID
                                Prty Queue
                                                C Pos
                                                        SAff
                                                              ASys Status
                       Owner
     TS5485
              TSU05627 TS5485
                                  15 EXECUTION
                                                              RS85
     BPXAS
              STC05353 BPXAS
                                  15 EXECUTION
                                                         R586
                                                              R586
     SYSLOG
              STC05354 +MASTER+
                                  15 EXECUTION
                                                         R586
                                                              R586
     VTAM
              STC05355 VTAM
                                  15 EXECUTION
                                                         R586
                                                              RS86
```

Filters all jobs that start with R

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-15 (15)
COMMAND INPUT ===>
                                                               SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=*
     JOBNAME JobID
                                                C Pos
                                                         SAff
                                                              ASys Status
                       Owner
                                Prty Queue
              STC05420 RACF
     RACF
                                  15 EXECUTION
                                                         RS86
                                                              RS86
     RACF
              STC05510 RACF
                                  15 EXECUTION
                                                         RS85
                                                              RS85
     RMF
              STC05514 RMF
                                  15 EXECUTION
                                                              RS85
```

Fast Path Select by Job Number



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 1-26 (563)
COMMAND INPUT ===> s 5522
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
    JOBNAME JobID
                                               C Pos
                                                             ASys Status
                      Owner
                               Prty Queue
    TS5485
             TSU05627 TS5485
                                 15 EXECUTION
                                                             RS85
    BPXAS
             STC05353 BPXAS
                                 15 EXECUTION
                                                       R586
                                                             R586
    SYSLOG
             STC05354 +MASTER+
                                 15 EXECUTION
                                                             R586
                                                       R586
    VTAM
             STC05355 VTAM
                                 15 EXECUTION
                                                       R586
                                                             R586
                                                            Select by job
                                                               number
 Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 1-1 (1)
COMMAND INPUT ===>
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
    JOBNAME JobID
                     ⊿0wner
                               Prty Queue
                                               C Pos
                                                       SAff ASys Status
    SUBRTE
             STC05522 SUBJCL
                                  1 PRINT
                                                   376
```

Fast Path Select Override



```
Display Filter View Print Options Search Help
                                                       LINE 1-14 (14)
SDSF STATUS DISPLAY ALL CLASSES
COMMAND INPUT ===> s rmf
                                                              SCROLL ===> HALF
PREFIX=TS5485 DEST=(ALL) OWNER=*
                                   SYSNAME=*
             JobID
                      Owner
                                               C Pos
                                                        SAff
                                                             ASys Status
                               Prty Queue
                                 15 EXECUTION
                                                             RS85
     TS5485
             TSU05627 TS5485
                                                        RS85
                                  1 PRINT
                                                                   PRIVILEGED
    TS5485
             TSU04454 TS5485
                                   1 PRINT
    TS5485
             TSU04596 TS5485
```

Override prefix and owner and select all RMF jobs

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-5 (5)
COMMAND INPUT ===>
                                                              SCROLL ===> HALF
PREFIX=TS5485
             DEST=(ALL) OWNER=* SYSNAME=*
                                               C Pos
    JOBNAME
             JøbID
                      Owner
                               Prty Queue
                                                        SAff
                                                             ASys Status
             STC05514 RMF
                                 15 EXECUTION
                                                        RS85
                                                             RS85
              STC04883 RMF
                                  1 PRINT
                                                    212
     RMF
             STC05042 RMF
                                  1 PRINT
                                                    215
```

Fast Path Select Override Examples



Panel	Operands
DA, I, O, ST, H, AS	jobname [jobid] jobname [jobnumber] jobnumber
JDS	ddname [stepname] ddname [dsid] dsid
Job Dependency	Jobname [jobid] May match JOBNAME (jobid) or DJobName (DJobID) columns
Job Device	fixedfield (dataset, crstructurename, ipaddr)
Job Group	groupname [groupid]
Job Step	stepname [procstep]

Locate Column



- LOCATE | L column-name
- Used to position to a column
- Instead of left/right scrolling
- Aligns the column first just after fixed field
- Specify enough characters to uniquely name column
- If name not unique, positions to first column name that matches

Locate Column



```
Display Filter View Print Options Search Help
                                                      LINE 711-718 (718)
SDSF STATUS DISPLAY ALL CLASSES
COMMAND INPUT == > locate tgpct
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
                                               C Pos
                                                       SAff ASys Status
    JOBNAME JobID
                      Owner
                                Prty Queue
     SMFSWTCH STC05592 SMFDMP
                                   1 PRINT
                                                    556
    LOGREC86 JOB05593 SUBJCL
                                   1 PRINT
                                                   557
    SUBRTE
             STC05594 SUBJCL
                                  1 PRINT
                                                    558
```

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 711-718 (718)
COMMAND INPUT =>=>
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL)
                      OWNER=* SYSNAME=*
                                                          Offs Max-RC
     JOBNAME
               TGPct OrigNode ExecNode Device
                                                                          SrvC1
     SMFSWTCH
                0.00 LOCAL
                              LOCAL
                                                               CC 0000
     LOGREC86
                0.00 LOCAL
                              LOCAL
                                                               CC 0000
     SUBRTE
                0.00 LOCAL
                              LOCAL
                                                               CC 0000
```

Tgpct column is positioned first

Arrange Columns



- Use arrange command to re-order columns (saved in ISPF profile)
- arr? to display pop-up (most commands use? to display the pop-up)
- Use command for quick changes
 - arr column-name first
 - arr column-name last
 - arr column-name1 a column-name2 (after)
 - arr column-name1 b column-name2 (before)
 - arr default (to reset to default arrangement)
- Use special column name .end to hide columns
 - arr .end a saff (All columns after SAff will be hidden)
- Can also change column widths (arr column-name nn)
- Specify enough characters in column-name to make it unique

Arrange first



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 711-715 (715)
COMMAND INPUT ===>(arr phasename first
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
     JOBNAME JobID
                                                        SAff ASys Status
                      Owner
                                Prty Queue
                                                C Pos
     SMFSWTCH STC05592 SMFDMP
                                    PRINT
                                                    556
     LOGREC86 JOBO5593 SUBJCL
                                   1 PRINT
                                                   557
             STC05594 SUBJCL
                                   1 PRINT
     SUBRTE
                                                    558
  Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 711-715 (715)
COMMAND INPUT ===>
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=*
                                   JobID
                                                                     C Pos
     JOBNAME PhaseName
                                            Owner
                                                     Prty Queue
                                                        1 PRINT
     SMFSWTCH AWAITING OUTPUT
                                   STC05592 SMFDMP
                                                                         556
     LOGREC86 AWAITING OUTPUT
                                   JOBO5593 SUBJCL
                                                        1 PRINT
                                                                         557
                                   STC05594 SUBJCL
                                                                         558
     SUBRTE
             AWAITING OUTPUT
                                                        1 PRINT
```

Phasename column has been arranged after fixed field


Arrange after



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 711-715 (715)
COMMAND INPUT === /> arr max-rc a
                               jobid
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
    JOBNAME JobID Owner
                               Prty Queue
                                               C Pos
                                                       SAff ASys Status
    SMFSWTCH STC05592 SMFDMP
                                  1 PRINT
                                                   556
    LOGREC86 JOBO5593 SUBJCL
                                  1 PRINT
                                                   557
 Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 711-715 (715)
COMMAND INPUT ===>
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
    JOBNAME JobID
                      Max-RC
                                 Owner
                                          Prty Queue
                                                          C Pos SAff ASys S
                                                              556
     SMFSWTCH STC05592 CC 0000
                                 SMFDMP
                                             1 PRINT
    LOGREC86 JOB05593 CC 0000
                                 SUBJCL
                                             1 PRINT
                                                             557
```

Arrange Hidden Columns






Show Contents of Row



- Action to show all columns for single row in vertical scrollable table
- Enter / in NP against table row
 - Not to be confused with the primary slash command for operator commands
- ISPF Pop-up panel displayed showing title and value for all columns in scrollable area
 - Locate available
 - Can suppress null/blank columns

Show Row Contents







- Use filter command to select rows to be displayed
 - Applied after prefix, owner, dest, sysname
 - Filters are saved in ISPF profile
- Use pop-up when entering multiple filters
- Simplified command
 - Single column
 - Operator is EQ
- For example, fil jobn bpx* will filter jobs starting with bpx
 - Use enough characters to make column name unique
- Use fil off to turn off filtering



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                     LINE 1-26 (563)
COMMAND INPUT ===>(fil jobn bpx*
                                                            SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
                                              C Pos
    JOBNAME
             JobID
                               Prty Queue
                                                            ASys Status
                                                      SAff
    TS5485
                                                            RS85
             TSU05627 TS5485
                                 15 EXECUTION
                                                      RS85
    BPXAS
             STC05353 BPXAS
                                 15 EXECUTION
                                                      R586
                                                            R586
                                                                              Least characters to make
    SYSLOG
             STC05354 +MASTER+
                                 15 EXECUTION
                                                      R586
                                                            R586
                                                                            column name unique and EQ
                                                                                        omitted
```

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                        LINE 1-26 (50)
                                                               SCROLL ===> HALF
COMMAND INPUT ===>
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=*
                                           FILTERS=1
                                                         SAff ASys Status
     JOBNAME
              JobID
                       Owner
                                Prty Queue
                                  15 EXECUTION
     BPXAS
              STC05353 BPXAS
                                                         R586
                                                              R586
     BPXAS
              STC05389 BPXAS
                                  15 EXECUTION
                                                         RS86
                                                               R586
     BPXAS
              STC05390 BPXAS
                                  15 EXECUTION
                                                         RS86
                                                              RS86
     BPXAS
              STC05498 BPXAS
                                  15 EXECUTION
                                                         RS85
                                                               RS85
```

Panel being filtered

Only jobs passing filter are shown



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-26 (50)
COMMAND INPUT ===> fil off
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=* FILTERS=1
     JOBNAME
              JobID
                       Owner
                                Prty Queue
                                                        SAff
                                                              ASys Status
     BPXAS
                                  15 EXECUTION
              STC05353 BPXAS
                                                        R586
                                                              R586
     BPXAS
              STC05389 BPXAS
                                  15 EXECUTION
                                                        R586
                                                              R586
              STC05390 BPXAS
     BPXAS
                                  15 EXECUTION
                                                        R586
                                                              R586
```

Turn filters off

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 1-26 (563)
COMMAND INPUT ===> fil
                                                              SCROLL ===> HALF
PREFIX=** DEST⊨(ALL)
                      OWNER=*
                                SYSNAME=*
     JOBNAME
            JOBID
                                                C Pos
                                                        SAff
                                                              ASys Status
                                Prty Queue
             TSU05627 TS5485
     TS5485
                                  15 EXECUTION
                                                        RS85
                                                              RS85
     BPXAS
              STC05353 BPXAS
                                  15 EXECUTION
                                                        R586
                                                              RS86
```

Show filters pop-up



Display	Filter View Print Options Search Help					
SDSF STA COMMAND PREFIX=*	Filter Row 1 to 9 of 25	ALF				
NP JOB TS5 BPX SYS VTA HZS	Type filter criteria. Press F4/16 in the Column or Oper field for values, or in the Value field for system symbols. Press F11/23 to clear all filter criteria. Filtering is OFF AND/OR between columns AND (AND/OR) AND/OR within a column OR (AND/OR)					
INI INI INI						
INI INI INI	Column Oper Value (may include * and %) JOBNAME EQ BPX*					
INI INI INI						
INI INI INI						
INI INI	! _ _ 					

Filter pop-up retains prior filters. Press enter to restore or change filters.

Printing and Copying a Table



- Use SNAP command to capture a table
 - Print the table
 - Edit the table and save for another application
- SNAP formats all rows and columns of the table
 - Optionally change the editor using SNAP S | SB | SE | SV
 - Change edit default using SET SNAP S | SB | SE | SV

Printing a Table



<u>D</u> isplay <u>F</u> i	lter <u>V</u> iew	<u>Print Op</u>	tions §	earch <u>H</u> e	1p	
SDSF STATUS D					LINE 1-2	26 (563) SCROLL ===> HALF
PREFIX=** DE NP JOBNAME	ST=(ALL) C JobID C TSU05627	DWNER=* SY Dwner Pr TS5485 BPXAS	SNAME=* ty Queue 15 EXECU 15 EXECU 15 EXECU	C P UTION UTION	os SAff A	ASys Status 1585 1586

Use SDSF browse

<u>D</u> isplay <u>F</u> ilter	<u>V</u> iew <u>P</u> rint <u>O</u> ptions	<u>S</u> earch <u>H</u> elp	
SDSF OUTPUT DISPLA COMMAND INPUT ===>	• _	LINE O	COLUMNS 02- 81 SCROLL ===> HALF
JOBNAME JobID O TS5485 TSU05627 T BPXAS STC05353 B SYSLOG STC05354 +	Owner Prty Queue FS5485 15 EXECUTION BPXAS 15 EXECUTION	C Pos	SAff ASys St RS85 RS85 RS86 RS86 RS86 RS86

SDSF browse window with each row as a line

Tip: Use the **PRINT** command to copy the data set or any edit command if using SE

Block and Repeat Overtypes



- Block command (//) applies an action to multiple rows
 - For example //p ... // applies the p action to a block of rows
- Repeat command (=) repeats last action against the current row
- Block and repeat work for overtypes too!
 - Enter // in NP column on first row
 - Overtype data in column on first row
 - Enter // in NP column on last row
 - The overtype will be applied to all rows within the block

Block and Repeat Overtypes



```
Display Filter View Print Options Search
                                                  Help
SDSF OUTPUT ALL CLASSES ALL FORMS
                                      LINES 73
                                                        LINE 1-3 (3)
COMMAND INPUT ===>
                                                                SCROLL ===> HALF
PREFIX=** DEST=(ALL)
                       OWNER=TS5485
                                      SYSNAME=*
     JOBNAME
              JobID
                                       Forms
                                                                       Tot-Rec
                       Owner
                                                 Dest
     TS5485
              TSU22565 TS5485
                                 150
                                       STD
                                                 LOCAL
                                                                            10
                                                                            55
     TS5485B
              JOB22800 TS5485
                                  144
                                      K STD
                                                 LOCAL
     TS54850
              JOB21521 TS5485
                                      火 STD
                                                 LOCAL
                                 144
```

Block change priority to 150

```
Display Filter View Print Options Search Help
SDSF OUTPUT ALL CLASSES ALL FORMS
                                      LINES 73
                                                         3 COMMANDS ISSUED
COMMAND INPUT ===>
                                                                SCROLL ===> HALF
PREFIX=** DEST=(ALL)
                       OWNER=TS5485
                                      SYSNAME=*
     JOBNAME
              JobID
                       Owner
                                Prty\C Forms
                                                                       Tot-Rec
                                                 Dest
     TS5485
              TSU22565 TS5485
                                  150
                                     F STD
                                                 LOCAL
                                                                            10
     TS5485B
              JOB22800 TS5485
                                  150 R STD
                                                 LOCAL
                                                                            55
              JOB21521 TS5485
     TS54850
                                  150 K STD
                                                 LOCAL
                                                                             8
```

Overtype Extension



- Used to overtype long values
 - When value is too long for column width
 - Column must be completely visible for it to be overtyped
- Used to overtype multiple values
- Enter + in the overtypeable column
 - Must be only value in column
 - Erase any residual data for + to be recognized

Overtype Extension



```
Display Filter View Print Options Search Help
                                                        LINE 1-26 (563)
SDSF STATUS DISPLAY ALL CLASSES
COMMAND INPUT ===>
                                                               SCROLL ===> HALF
PREFIX=** DEST=(ALL)
                       OWNER=*
                                 SYSNAME=*
     JOBNAME
             JobID
                                 SAff
                                      Prty Queue
                       Owner
                                                       C Pos
                                                               ASys Status
     TS5485
                                         15 EXECUTION
                                                               R585
              TSU05627 TS5485
                                         15 EXECUTION
     BPXAS
              STC05353 BPXAS
                                 R586
                                                               R586
                                R586
                                                               R586
     SYSLOG
              STC05354 +MASTER+
                                         15 EXECUTION
     VTAM
              STC05355 VTAM
                                         15 EXECUTION
                                                               R586
  Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                        LINE 1-26 (563)
COMMAND INPUT ===>
                                                               SCROLL ===> HALF
PREFIX=**
     JOBNAM
                     Overtype Extension
                                                       C Pos
                                                               ASys Status
     TS5485
                                                               RS85
     BPXAS
              Column SAff
                                                               R586
              Maximum length 5
     SYSLOG
                                                               R586
                                                               RS86
     VTAM
     HZSPRO
              Type values or use blanks to
                                                               R586
     INIT
              erase values.
                                                               RS86
     INIT
              ===> RS85
                                                               RS86
     INIT
                                                               RS86
     INIT
                                                               R586
     INIT
                                                               RS86
     INIT
                                                               R586
     INIT
                                                               RS86
     INIT
                                                               R586
     INIT
                                                               RS86
     INIT
                                                               RS86
     INIT
                                                    Ν
                                                               RS86
     INIT
              F1=Help F12=Cancel
                                                    Ν
                                                               RS86
     INIT
                                                               RS86
```

Enter + in SAff column to display overtype extension pop-up

Running REXX against a row



- Use %execname action character
 - Concatenate execname to //SYSPROC or //SYSEXEC
- Exec is passed parameters including the row token
 - Use row token to derive attributes of row
- Use pop-up to specify arguments or long execname
- Use arrange command to increase size of NP column
 - Allow enough room for execname
 - Temporary change with + in NP

Running REXX Against a Row



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 1-26 (563)
                                                             SCROLL ===> HALF
COMMAND INPUT ===>
PREFIX=** DEST=(ALL)
                      OWNER=*
                               SYSNAME=*
    JOBNAME JobID
                               SAff Prty Queue
                      Owner
                                                     C Pos
                                                             ASys Status
    TS5485
                                       15 EXECUTION
                                                              RS85
             TSU05627 TS5485
    BPXAS
             STC05353 BPXAS
                               RS86
                                       15 EXECUTION
                                                              R586
```


Run exec and pass arg

```
<u>Display Filter View Print Options Search Help</u>
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-26 (563)
COMMAND INPUT ===>
                                                               SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                                SYSNAME=*
     JOBNAME JobID
                                SAff Prty Queue
                                                      C Pos
                       Owner
                                                               ASys Status
  TS5485
              TSU05627 TS5485
                                RS85
                                        15 EXECUTION
                                                               RS85
     BPXAS
              STC05353 BPXAS
                                R586
                                        15 EXECUTION
                                                               RS86
```

Display pop-up

Running REXX Against a Row






Specify name and arguments

Increase Width of NP (Permanent)



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                     LINE 1-26 (563)
COMMAND INPUT =≠> arr ?
                                                            SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
             Jobio Owner
                               SAff Prty Queue
    JOBNAME
                                                            ASys Status
                                                    C Pos
             TSU05627 TS5485
     TS5485
                               RS85
                                       15 EXECUTION
                                                            R585
    BPXAS
             STC05353 BPXAS
                               RS86
                                       15 EXECUTION
                                                            R586
```

Show arrange pop-up



Type a new value

Increase Width of NP (Temporary)



```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                      LINE 1-26 (563)
COMMAND INPUT ===>
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
    JOBNAME JobID
                               SAff Prty Queue
                                                     C Pos
                                                             ASys Status
                      Owner
   ◆TS5485
             TSU05627 TS5485
                                       15 EXECUTION
                                                             RS85
    BPXAS
             STC05353 BPXAS
                               R586
                                       15 EXECUTION
                                                             R586
```

Use + operator to expand NP width

```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                       LINE 1-26 (563)
COMMAND INPUT ===>
                                                              SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=* SYSNAME=*
         JOBNAME
                 JobID
                          Owner
                                    SAff
                                          Prtv Oueue
                                                          C Pos
                                                                  ASvs Status
         TS5485
                 TSU05627 TS5485
                                    RS85
                                            15 EXECUTION
                                                                  RS85
         BPXAS
                  STC05353 BPXAS
                                    R586
                                            15 EXECUTION
                                                                  R586
         SYSLOG
                 STC05354 +MASTER+ RS86
                                            15 EXECUTION
                                                                  RS86
```

Width increased to 8 characters until panel is reaccessed or RESET

Actions and Overtypes on the Command Line



- Access rows by row number
 - SET ROWNUM (ON|OFF)
- Specify action character or range on command line
 - 5-8 12 c
 - Issues **c** action against rows 5 through 8 and 12
- Specify column name and value on command line
 - 1 prty=100
 - Overtypes the PRTY column for row 1 to 100

Actions and Overtypes from the Command Line



```
Display Filter View Print Options Search Help
SDSF HELD OUTPUT DISPLAY ALL GLASSES LINES 123,931
                                                          LINE 1-26 (231)
COMMAND INPUT ===> set rownum
                                                                 SCROLL ===> HALF
PREFIX=**
           DEST=(ALL)
                        OWNER=*
                                 SYSNAME=
     JOBNAME
              JobID
                                             Prty C ODisp Dest
                                                                                 RE
                                   Owner
                                              144 K HOLD
     MYGROUP
              G0006757 JCL ERROR
                                   TS5485
                                                          LOCAL
     SUBRTE
              STC07327 CC 0000
                                    SUBJCL
                                              144 K HOLD
                                                          LOCAL
     BPXAS
              STC07311 CC 0000
                                    BPXAS
                                              144 K HOLD
                                                          LOCAL
     BPXAS
              STC07329 CC 0000
                                    BPXA5
                                              144 K HOLD
                                                          LOCAL
                                                                                               Turn on row
     BPXAS
              STC07331 CC 0000
                                    BPXA5
                                              144 K HOLD
                                                          LOCAL
     BPXAS
              STC07330 CC 0000
                                    BPXAS
                                              144 K HOLD
                                                          LOCAL
                                                                                                numbering
     OOPSLIST
              J0B07335 CC 0000
                                    PDZTEAM
                                              144 X HOLD
                                                          LOCAL
     TS5485
              TSU07337 ABEND 5522
                                   TS5485
                                              144 K HOLD
                                                          LOCAL
     SMFDUMP
              STC07338 CC 0012
                                    SMFDMP
                                              144 K HOLD
                                                          LOCAL
     SUBJCL
              STC07341 CC 0000
                                    SUBJCL
                                              144 K HOLD
                                                          LOCAL
                                              144 K HOLD
     LOGWRTR
              STC07343 CC 0000
                                    SUBJCL
                                                          LOCAL
     SUBRTE
              STC07344 CC 0000
                                    SUBJCL
                                              144 K HOLD
                                                          LOCAL
     IOS050
              J0B07346 CC 0000
                                   SUBJCL
                                              144 X HOLD
                                                          LOCAL
              STC07348 CC 0000
                                    SUBJCL
                                              144 K HOLD
                                                          LOCAL
     SUBJCL
     SMFSWTCH
              STC07347 CC 0000
                                    SMFDMP
                                              144 X HOLD
                                                          LOCAL
              STC07347 CC 0000
                                    SMFDMP
                                              144 K HOLD
                                                          ŁOCAL
     SMFSWTCH
                                              144 K HOLD
     SUBRTE
              STC07350 CC 0000
                                    SUBJCL
                                                          LOCAL
  <u>Display Filter View Print Options</u>
                                           Search Help
SDSF HELD OUTPUT DISPLAY ALL CLASSES LINES 123,931
                                                          LINE 1-26 (231)
COMMAND INPUT ===> 5-8 12 c
                                                                 SCROLL ===> HALF
PREFIX=**
           DEST=(ALL) OWNER=* SYSNAME=
          JOBNAME
                                                  Prty C ODisp Dest
                             Max-RC
                                         Owner
          MYGROUP
                    G0006757 JCL ERROR
                                         TS5485
                                                   144 K HOLD
                                                                LOCAL
          SUBRTE
                    57C07327 CC 0000
                                         SUBJCL
                                                                                         Cancel jobs on rows
                                                   144 K HOLD
                                                                LOCAL
          BPXAS
                    STC07311 CC 0000
                                         BPXAS
                                                   144 K HOLD
                                                                LOCAL
          BPXAS
                    STC07329 CC 0000
                                         BPXA5
                                                                LOCAL
                                                   144 K HOLD
                                                                                          5 through 8 and 12
        5
          BIPXA5
                    STC07331 CC 0000
                                         BPXAS
                                                   144 K HOLD
                                                                LOCAL
          BPXAS
                                         BPXAS
                    STC07330 CC 0000
                                                   144 K HOLD
                                                                LOCAL
                    J0B07335 CC 0000
                                         PDZTEAM
                                                         HOLD
                                                                LOCAL
          OOPSLIST
                                                   144 X
           TS5485
                    TSU07337 ABEND 5522
                                         TS5485
                                                   144 K HOLD
                                                                LOCAL
           $MFDUMP
                    STC07338 CC 0012
                                         SMFDMP
                                                   144 K HOLD
                                                                LOCAL
          SUBJCL
                    STC07341 CC 0000
                                         SUBJCL
                                                   144 K HOLD
                                                                LOCAL
          LOGWRTR
                    STC07343 CC
                                0000
                                         SUBJCL
                                                   144 K
                                                         HOLD
                                                                LOCAL
       12/ SUBRTE
                    STC07344 CC 0000
                                         SUBJCL
                                                   144 K HOLD
                                                                LOCAL
```

Point-and-shoot



- SDSF supports various point-and-shoot functions
 - NP
 - Invoke browse (or not) depending on SET BROWSE
 - Fixed field
 - Invoke default action for the column
 - Example is JDS for JOBNAME on DA, H, I, ST and O panels
 - Can be toggled with SET PAS ON | HIDE | OFF
 - Alias of SET FFPS
 - SET PAS HIDE enables fixed field for point-and-shoot
 - Fixed field will not be conditioned turquoise
 - Conditioned same as row highlighting
 - Memory address fields
 - Invokes SDSF memory browse on the 31bit or 64bit address
 - Inherits the ASID and SYSNAME from the row (if present)


Searching Data Set Lists



- Starting with z/OS 2.3, SDSF includes several displays that show lists of various types of data set
 - APF Authorized Load Libraries
 - Link List LNK
 - LPA Link Pack Area List
 - PARM Logical PARMLIB
 - PROC JES2 Proclibs
 - JDD Job Allocated Data Sets (action on DA and other panels)
- Use the SRCH command to search the list using a member name pattern
 - SRCH member pattern [F | NF | ALL]
 - Member name pattern can include standard * and % masking characters
 - Optionally restrict results by:
 - Data sets containing member (F)
 - Data sets not containing member (NF)

Searching Data Set Lists







SLASH COMMAND

Slash Command



- Slash command tips:
 - End your command with trailing + to continue command using pop-up
 - Enter / with no text to recall last command using pop-up
 - Use the pop-up for mixed case command text
 - Use full screen mode to enable insert mode for command text
 - Categorize your slash commands using command groups

Slash Command Extension



	olay <u>F</u> ilter										
SDSF S COMMAN PREFIX NP	STATUS DISPL ND INPUT === (=** DEST=(JOBNAME TS5485 BPXAS SYSLOG	ALL) OWN	ASSES s an incom ER=* SYSN Owner TS5485 BPXAS +MASTER+	AME="	rty Oue	ue.	C Pos				
Disp	olay Filter	· View P	rint Opti	ons Se	earch H	elp					
SDSF STATUS DISPLAY ALL CLASSES LINE 1-26 (563) COMMAND INPUT ===> /THIS IS AN INCOMPLETE COMMAND+ SCROLL ===> HAL PR									HALF		
NP _	Edit Options Help										
		System Command Extension									
===> THIS IS AN INCOMPLETE COMMAND											
İ	Comment						ST	ORELIMI			
=	=> RO R586, => V E000,0 => RO R586, => RO R586, => RO R586,	ONSOLE C U=TS548	B 5 5	afe .		(F4	for lis		-		

Command propagated to input area so it can be completed

Slash Command Groups



- Slash command pop-up allows you to:
 - Associate a command with a group
 - Associate a comment with a command
 - Display commands based on group pattern
 - Lists all groups
 - Save a command without issuing it
 - Delete a single command, group of commands, or all recent commands
 - View details about a command

Slash Command Groups



- To add a command to a group
 - Access slash command pop-up (/ with no operands)
 - Type command in input area
 - Enter a group name (any name provided by you)
 - Optionally enter a comment
 - Hit enter to issue the command or PF10 to save the command without issuing it
- Enter a show pattern to display commands by group in the recent list
 - Asterisk shows all commands
 - Up to 20 commands shown in recent list
 - Other than Asterisk will show the last 20 commands that match

Slash Command Groups





Recalling Commands



- Commands are saved in recent list
 - Scroll to desired command
 - Put cursor under command
 - Hit enter to recall command to input area
- Command recalled along with group and comment
 - Comments are not shown in the recent list
 - Group not shown but listed based on show pattern

Recalling commands



```
Display Filter View Print Options Search Help
                   RSPLEXOG RS86
                                                     LINE 1-26 (50)
SDSF MENU V2R3MO
COMMAND INPUT ===> /
                                                            SCROLL ===> HALF
      Edit Options Help
                          System Command Extension
     ===> F SDSF,D
                                                             STORELIMIT
    Comment Display SDSF status
                             Show *
    Group
                                                            More:
        D M=CPU
        V E000, CONSOLE
        RO RS88,S SDSF
        D U,UR,,,100
        D U,UR,,OFFLINE
        R 8, CANCEL
        $da
        5 WTOR
    F5=FullScr F6=Details F7=Up F8=Down F10=Save F11=Clear F12=Cancel
    NC
             Network connections
                                     Network
```

Put cursor under command to be recalled and press enter

Tip: recent list does not show group or comment. Recall the command or press F6 for detail view

Tip: Use Group and Show to get a list of all the commands matching

Recalling commands



```
Display Filter View Print Options Search Help
                RSPLEXOG RS86
                                    LINE 1-26 (50)
SDSF MENU V2R3MO
COMMAND INPUT ===> /
                                                 SCROLL ===> HALF
      Edit Options Help
NP
                       System Command Extension
                                                       STORELIMIT
    Comment Display JES active jobs
                Show * (F4 for list)
    Group
                                                      More:
       F SDSF,D
       $DA
       D M=CPU
    => V E000, CONSOLE
    => RO R588,5 SDSF
       D U,UR,,,100
       D U,UR,,OFFLINE
    => R 8,CANCEL
       d t
       $da
       D A
       S WTOR
    F5=FullScr F6=Details F7=Up F8=Down F10=Save F11=Clear F12=Cancel
            Network connections
    NC
                                  Network
```

Command recalled

Removing Commands



- Commands are saved in recent list
- Last command issued is moved to the top
- You can remove a single command
 - Put cursor under command
 - Hit F11 to remove it from list

Removing Commands



STORELIMIT

LINE 1-26 (50)

Di	splay F	ilter	View	Print	Options	Search	Help					
COMM	MENU V2 MAND INPU				586					===> HALF		
PR . NP	Edit	Optio	ns He	lp qf						i		
		System Command Extension										
	===>											
	===>								STOREL	IMIT		
į	Comment									İ		
į	Group	JES2			Show *			(F4 for	list) More:	+		
	=> F S S S D M => V E => D M => D M => D M => D M => D M => D M => S W => S W F5=Full	ECPU 000,CO RS88,5 ,UR,,, ,UR,,,	SDSF 100 FFLINE L		p F8=Dowr	ı F10=Sav	re F11=	=Clear F	12=Cance	1		
	NC	Netw	ork co	nnectio	ns N	Network		$\overline{}$				
							ı					

Command removed from

Display Filter View Print Options Search Help

System Command Extension

recent list

ails F7=Up F8=Down F10=Save F11=Clear F12=Cancel

SDSF MENU V2R3MO RSPLEXOG RS86

Edit Options Help

V E000, CONSOLE RO RS88,5 SDSF D U,UR,,OFFLINE R 8, CANCEL

COMMAND INPUT ===> /

=> F SDSF,D \$DA => D M=CPU

> \$da 5 WTOR panelid

Clear complete

Put cursor under command to be removed and press F11


Removing All Recent Commands



- Type the show pattern for the groups to be displayed
- Hit enter to display the recent commands
- Position cursor outside of the recent list
- Hit F11 (Clear)
- Select an option
 - Recent commands matching show pattern
 - All commands matching show pattern
 - Selected commands from list
- The confirmation shows the number of commands that will be processed

Removing All Recent Commands





With cursor outside of recent list, press F11

Removing All Recent Commands



```
Display Filter View Print Options Search Help
                    RSPLEXOG RS86
SDSF MENU V2R3MO
                                                          LINE 1-26 (50)
COMMAND INPUT ===> /
       Edit Options Help
                              Select Clear Option
         Select an option to clear commands. The number of commands
         affected is shown in parentheses.

    Recent matching the value for Show (20)
    All matching the value for Show (29)

             3. From list...
         F1=Help F12=Cancel
         V E000, CONSOLE
         RO RS88,S SDSF
         D U,UR,,,100
         D U,UR,,OFFLINE
         R 8,CANCEL
         $da
         5 WTOR
     F5=FullScr F6=Details F7=Up F8=Down F10=Save F11=Clear F12=Cancel
     NC
              Network connections
                                         Network
```

Select option for commands to be removed

Using Full Screen Mode



- You can toggle the slash command pop-up between full screen and pop-up mode
- ISPF prevents insert mode from flowing to next line in pop-up mode
 - Due to attributes used to draw the pop-up frame
- Use full screen mode to enable insert mode in the text area
 - Toggle with F5
- Mode (pop-up or fullscreen) saved in ISPF profile

Using Full Screen Mode




```
Display Filter View Print Options Search Help
SDSF STATUS DISPLAY ALL CLASSES
                                                  LINE 1-26 (563)
                                                         SCROLL ===> HALF
COMMAND INPUT ===> /
      Edit Options Help
                        System Command Extension
                                                          STORELIMIT
    Comment Display queue
           JES2 Show JES2 (F4 for list)
                                                         More:
        $da
    =>
    =>
    =>
    =>
    F5=FullScn F6=Details F7=Up F8=Down F10=Save F11=Clear F12=Cancel
```

Toggle to full screen mode

Using Full Screen Mode





Single input area spanning two lines

Toggle to pop-up mode



BROWSE

Browse Tips



- Skip data sets (NEXT and PREV commands)
- Browse default (SET BROWSE command)

Browse Next and Prev



- Use NEXT and PREV commands to jump to next or previous data set
 - Alternative to scrolling
 - Positions to start of data set
- Tip: when browsing a job under JES2, use N 3 to position to first application data set
- Also sn and s-n action characters

Browse Next



```
<u>D</u>isplay <u>Filter View Print Options S</u>earch <u>H</u>elp
SDSF OUTPUT DISPLAY TS5485
                            TSU05631 DSID
                                              2 LINE O
                                                             COLUMNS 02- 81
COMMAND INPUT ==> n 3
                                                            SCROLL ===> HALF
     ***********************
                       JES2 JOB LOG -- SYSTEM RS85 --
20.59.45 TSU05631 ---- THURSDAY, 15 FEB 2018 ----
20.59.45 TSU05631 $HASP373 TS5485
       1 //TS5485
                   JOB 'ACCT#'
                       REGION=80000K
       2 //ROCKPROC EXEC ROCKPROC
                 ROCKET COMMON ISPF LOGON PROCEDURE FOR ALL VM GUESTS
         XX* PLEASE DO NOT MAKE CHANGES TO THIS PROC. ALL ISPF CHANGES
         XX* ARE NOW DONE USING LIBDEF SERVICES. IF YOU ARE UNCERTAIN HOW
         XX* TO ACCOMPLISH THIS, PLEASE ASK FIRST. THANKS, BRUCE
         XX* 03/20/07 LWB ADD SYS1.SBPXEXEC TO SYSEXEC
         XX* 07/28/05 BCW NEW VERSION OF SHARED ROCKPROC UTILIZING LIBDEF
       3 XXROCKPROC EXEC PGM=IKJEFT01,REGION=OM,DYNAMNBR=175,PARM='%LOGINIT'
```

Skip 3 data sets

Browse Next Action Character



```
Display Filter View Print Options Search Help
                                                      LINE 1-26 (564)
SDSF STATUS DISPLAY ALL CLASSES
COMMAND INPUT ===>
                                                             SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=*
                               SYSNAME=*
                               SAff Prty Queue
                                                             ASys Status
    JOBNAME
            JobID
                      Owner
                                                     C Pos
    TS5485
             TSU05631 TS5485
                               RS85
                                       15 EXECUTION
                                                             RS85
  BPXA5
             STC05353 BPXAS
                               R586
                                       15 EXECUTION
                                                             R586
```

Browse and skip 4 data sets

Browse Default



- Use browse default to invoke browse by placing cursor in NP area and hitting enter
 - Rather than typing S action character
- SET BROWSE S | SB | SE | NONE
 - Controls whether browse default is used and default action to be taken
- Use SET CURSOR to control cursor placement after an action
 - SET CURSOR (ON|TOP|OFF|?)
 - ON keep cursor on last row you worked with
 - TOP scroll table to last line you worked with and move cursor to command line
 - OFF return cursor to command line

Change FINDLIM



- Findlim controls number of records searched using find command
 - Default is 5000 records
- Hit repeat find when findlim reached to continue
- Change limit with findlim command
- findlim number | ?
 - *number* is 1000 to 9999999
- findlim 100000
 - Searches 100000 recors before stopping

Operlog Color



- Control color and highlighting in operlog
- SET SCREEN command
- By default, messages are colorized in operlog as they were first issued
- You can change attributes based on descriptor code

```
Display Filter View Print Options Search Help
                                      Set Screen Characteristics
SDSF MENU V2R3MO
COMMAND INPUT ===> SET SCR
PREFIX=**
          DEST=(ALL) OWN
                            Select the elements that you want to customize.
    NAME
             Description
                                1. Basic settings and tabular panels
     DA
             Active users
     I
             Input Queue
                                OPERLOG panel
             Output Queue
             Held output
             Status of jo
                            F1=Help F12=Cancel
     JG
             Job aroups
             System symbols
     SYM
                                      System
```

Operlog Color



```
Display Filter View Print Options Search Help
SDSF MENU V2R3MO
                    RSPLEX I
                                       Set Screen Characteristics
COMMAND
PREFIX=
                    Set Screen Characteristics: OPERLOG Panel
    NA
     DA
                                                            More:
         Use color and highlighting
     I
                                        1 1. Yes
                                                     2. No
     О
     н
          Type values to override the original color and highlighting.
         Press F5/17 to see changes.
     ST
     JG
                                                    Highlight Intensity
     SY
          Descriptor code
                                           Color
     LO
          1 - System failure
          2 - Immediate action required
     SR
           3 - Eventual action required
     MA
           4 - System status
     JC
     SE
           5 - Immediate command response
     RE
           6 - Job status
     ΕN
           7 - Task-related
                                           RED
           8 - Out of line
     PS
     SY
           9 - Operator's request
     ΕN
          10 - Not defined
     DY
          11 - Critical eventual action
         12 - Important information
     A5
          F1=Help F5=Refresh F6=Default F11=Cuaattr F12=Cancel
```



SECTRACE

Security Trace (Sectrace)



- Traces all SAF calls made by SDSF
 - Messages written to ULOG or WTP
- Simplifies diagnosing authorization problems
 - Resource name, access level, and class

Using Sectrace



```
Display Filter View Print Options Search Help
                                                       LINE 1-26 (49)
SDSF MENU V2R3MO
                    RSPLEXOG RS85
COMMAND INPUT ===> set sectrace
                                                              SCROLL ===> HALF
PREFIX=**
          DEST=(ALL) OWNER=*
                                SYSNAME=*
              Description
    NAME
                                       Group
                                                Status
    DA
              Active users
                                       Jobs
    T
              Input Queue
                                       Jobs
    0
              Output Queue
                                       Output
    н
              Held output Queue
                                       Output
              Status of jobs
     ST
                                       Jobs
                                                                              Enable sectrace
     JG
              Job groups
                                       JES
     SYM
              System symbols
                                       System
```

```
Display Filter View Print Options Search Help
SDSF MENU V2R3MO
                    RSPLEXOG RS85
                                                       LINE 1-26 (49)
COMMAND INPUT ===> st
                                                              SCROLL ===> HALF
PREFIX=**
          DEST=(ALL) OWNER=*
                                SYSNAME=*
    NAME
              Description
                                       Group
                                                Status
    DA
              Active users
                                       Jobs
    I
              Input Queue
                                       Jobs
    0
              Output Queue
                                       Output
              Held output Queue
                                       Output
```

Perform scenario (command, action, overtype, etc.)

Using Sectrace



```
Display Filter View Print Options Search Help
SDSF ULOG CONSOLE TS5485
                                              LINE O
                                                         COLUMNS 44- 123
COMMAND INPUT ===>
                                                         SCROLL ===> HALF
ISF045W Unable to open table library ISFTABL, number of saved commands may be l
ISF050I USER=TS5485 GROUP=ISFSPROG PROC=ROCKPROC TERMINAL=S85TCP04
ISF051I SAF Access allowed SAFRC=0 ACCESS=READ CLASS=SDSF RESOURCE=ISFCMD.DSP.S
ISF051I SAF Access allowed SAFRC=0 ACCESS=READ CLASS=SDSF RESOURCE=ISFCMD.DSP.S
ISF051I SAF Access allowed SAFRC=0 ACCESS=UPDATE CLASS=SDSF RESOURCE=ISFATTR.JO
ISF051I SAF Access allowed SAFRC=0 ACCESS=UPDATE CLASS=SDSF RESOURCE=ISFATTR.JO
ISF051I SAF Access allowed SAFRC=0 ACCESS=UPDATE CLASS=SDSF RESOURCE=ISFATTR.JO
ISF051I SAF Access allowed SAFRC=0 ACCESS=READ CLASS=SDSF RESOURCE=ISFCMD.ODSP.
ISF031I CONSOLE TS5485 ACTIVATED
         ******************* BOTTOM OF DATA ****************
```

Results of access calls are added to ULOG

Early Sectrace



- Use WTP option to view sectrace messages during SDSF initialization
 - Useful when diagnosing group assignment problems
- Invoke SDSF using option S
 - s.sectrace(wtp)
- Add sectrace option to SDSF command (from option 6 or TSO ready)
 - sdsf sectrace(wtp)
- Enabling via the existence of special DDs
 - alloc fi(isfsectw) dummy reus sectrace issued as WTP
 - alloc fi(isfsectr) dummy reus sectrace written to ULOG



SDSF/REXX

SDSF/REXX



- Have you used SDSF/REXX yet?
 - Simple way to access SDSF panel data using REXX
 - Automated tasks
 - Search job output for events
 - Verify result of test cases
 - One time tasks
 - Modify groups of jobs
 - Search syslog for specific messages
- Start with simple exec and build up
 - Address SDSF "isfexec st"
 - Address SDSF "isfact st token(""token"") parm(np d)"

SDSF/REXX Tips



- Generate REXX execs using RGEN
- Use nomodify option to suppress creation of row tokens
- Use stem notation for isfact to process multiple rows
- Use verbose option to debug execs
- Use isfquery() to query environment settings
- **REXXHELP | REXXH** command to display SDSF/REXX documentation
- COLSHELP | COLSH command to display column names valid for panel

RGEN Command




- Generate starter exec you can modify
- Select from a list of examples or generate exec based on current context
 - Generates all commands to navigate to the panel you are on
- Starter exec is generated in an ISPF temporary data set
 - Be sure to copy the exec to a permanent data set prior to editing !!
- Generated exec contains ISPF note lines for tips and hints
 - Notes are not saved to the data set being edited
 - Issue ISPF reset command to remove notes from the view




- Enter rgen x from any panel
 - Displays a pop-up with list of working SDSF/REXX examples
 - Select an example
- Copy the exec and modify as needed



Display Filter View Print Options Search Help







```
SDSF EDIT
                                                            Columns 00001 00072
             RGEN TS5485.RS86.SPFTEMP1.CNTL
Command ===>
                                                               Scroll ===> HALF
000001 /* REXX */
000002 Arg debug
000003
          Important: Copy this generated exec from temporary dataset
==MSG>
            TS5485.RS86.SPFTEMP1.CNTL
==MSG>
          and edit that copy to prevent your changes from being lost.
==MSG>
==MSG>
000004
000005 *
          SDSF RGEN Generated Example:
000006 *
000007 *
          Browse check output
000008 *
          This exec was generated by the SDSF RGEN command on
000009 *
          Wednesday 2017/07/19 at 15:01:55.67.
000010 *
000011 *
000012 *
          5650-Z0S
          SDSF level = z/0S 02.03.00 (HQX77B0)
000013 *
000014 *
          This sample uses function available since z/OS V1R9.
000015 *
000016 *
          For more information and examples, use the SDSF REXXHELP
          command. To search SDSF's help, use SEARCH search-string.
000017
000018
=NOTE= Tip: All SDSF/REXX execs must include the following statement:
000019 rc=isfcalls('ON')
```

RGEN generates a fully functional exec that you can modify



```
Address SDSF "ISFEXEC CK E (" verbose ")"
1rc=rc
call msgrtn "ISFEXEC CK" if lrc<>0 then /* If request failed */
 Exit 20
msgrtn: Procedure expose isfmsg isfmsg2.
Arg req
Tip: The isfmsg2. stem contains numbered messages
    associated with the request and isfmsg2.0 contains
    a count of the number of variables that follow.
do ix=1 to isfmsq2.0
 Say isfmsg2.ix
end
if isfmsg<>"" then /* If short message present */
   Say "** Short message associated with the request is:" isfmsq
 end
return
```

Inspect isfmsg2 stem after request

> rgen generated subroutine



Display Filter View Print Options Search Help REXX Examples Row 1 to 15 of 22 Command ===> Sort by type (F5) or description (F6). Description Type Cancel a job Action Action Cancel a set of jobs Action Invoke an EXEC with the % action character List action characters Action List job data sets Action Modify a value for a set of jobs Modify values for selected jobs (overtype) Action Action Browse a single data set with EXECIO Browse Browse a single data set with ISFBROWSE Browse Browse check output Browse Browse check output from check history Browse Browse check output with ISFBROWSE Browse Browse job output with EXECIO Browse Browse job output with ISFBROWSE Browse Browse job output with ISFBROWSE - groups of lines Browse

Display Filter View Print Options Search Help REXX Examples Row 16 to 22 of 22 Command ===> Sort by type (F5) or description (F6). Type Description Info Issue the WHO comand Operloa Work with the OPERLOG Print Print to SYSOUT Find a message in the SYSLOG Syslog Work with the SYSLOG Syslog Tabular Access a tabular panel and create column variables Access a tabular panel and create SDSFROW variable ******************************** Bottom of data **********************

Using NoModify Option



- Row tokens are generated by default
- Row token used to identify the row for a subsequent action
- Suppress generation when row will not be modified (i.e. no actions will be performed)
 - Improves performance
 - Reduces storage utilization
- Address SDSF "isfexec st (nomodify"
 - The **token.** stem will not be generated

Using Stem Notation for isfact



- Specifying isfact row token
 - Single row token
 - List of row tokens
 - Stem variable containing row tokens
- Stem variable useful when modifying multiple rows
 - Can be done in a single request
- Pair with isfexec
 - isfexec creates the token stem
 - isfact token((token.))
 - Note double parenthesis to show the variable is a stem

Using Verbose Option



- Add verbose option to list all SDSF special variables read or set
- Messages returned in the isfmsg2 stem
 - May cause many messages to be issued
- Helpful when you expect data to be returned in a variable but not found
 - Common problem when changing stem prefix
- Address SDSF "isfexec st (verbose"
- Enables verbose and sectrace via special DD
 - Does SAY for isfmsg2 and the WHO command
 - alloc fi(isfrxdbg) dummy reus or //ISFRXDBG DD DUMMY

Using Verbose Option



Address SDSF "ISFEXEC ST (VERBOSE"

```
isfmsg2.56 is: ISF147I REXX variable SDSFFILTER fetched, return code 00000001 value is ''
isfmsg2.57 is: ISF147I REXX variable ISFFILTER fetched, return code 00000001 value is ''.
isfmsq2.58 is: ISF147I REXX variable SDSFFILTERMODE fetched, return code 00000001 value is ''.
isfmsg2.59 is: ISF147I REXX variable ISFFILTERMODE fetched, return code 00000001 value is ''.
isfmsg2.60 is: ISF147I REXX variable SDSFSORT fetched, return code 00000001 value is ''.
isfmsg2.61 is: ISF147I REXX variable ISFSORT fetched, return code 00000001 value is ''.
isfmsg2.62 is: ISF146I REXX variable JNAME.1 set, return code 00000001 value is 'TS5485R'.
isfmsq2.63 is: ISF146I REXX variable TOKEN.1 set, return code 00000001 value is '6ysXMjwso5KjYfXxfPVBQNtl9eXA9W1A
isfmsg2.64 is: ISF146I REXX variable ROWACTIVE.1 set, return code 00000001 value is 'Y'.
isfmsg2.65 is: ISF146I REXX variable JOBID.1 set, return code 00000001 value is 'JOB07582'.
isfmsg2.66 is: ISF146I REXX variable OWNERID.1 set, return code 00000001 value is 'TS5485'.
isfmsq2.67 is: ISF146I REXX variable JPRIO.1 set, return code 00000001 value is '9'.
isfmsg2.68 is: ISF146I REXX variable QUEUE.1 set, return code 00000001 value is 'EXECUTION'.
isfmsq2.69 is: ISF146I REXX variable JCLASS.1 set, return code 00000001 value is 'A'.
```



WHAT'S NEW?

What's New Help



```
Display Filter View Print
                               Options Search
                                                 1 1. Help contents...
                 MCLXCF01 AQFT
SDSF MENU 3.1
COMMAND INPUT ===>
                                                                          CSR
                                                    2. What's new...
NΡ
    NAME
              Description
                                                    3. Web sites...
                                       Group
    DA
              Active users
                                       Jobs
                                                    4. REXX...
              Input queue
                                       Jobs
                                                    5. Panels...
              Status of jobs
                                                    6. About...
     ST
                                       Jobs
              Job groups
     JG
                                       JES
```

```
<u>D</u>isplay <u>F</u>ilter
                    <u>View Print Options Search Help</u>
SDSF HELP AOFT
                     SECTION MAIN
                                                           LINE 1-56 (174)
COMMAND INPUT ===>
                                                                   SCROLL ===> CSF
     Help-Text
     What's new in z/OS SDSF Version 3 Release 1
     Enhancements in previous releases
     SDSF Panels
     SDSF messages and codes
```

```
<u>Display Filter View Print Options Search Help</u>
                                                       LINE 1-56 (297)
SDSF HELP AOFT
                    SECTION NEWIN31
COMMAND INPUT ===>
                                                              SCROLL ===> CSR
    Help-Text
    Summary of changes for SDSF 3.1
    Changes made for SDSF 3.1 as updated .
    Summary of changes as updated
    New:
       o New panels
          - System information panels
            o The Coupling Facilities panel (CF) displays information about all
              of the coupling facilities that are defined in the sysplex.
```



Questions?



Thank You!

Your feedback is important!



Submit a session evaluation for each session you attend:

www.share.org/evaluation

