


CREATION VM AD2


- 1) Se connecter à proxmox
- 2) Appuyer create vm (en haut a droite sur proxmox)
- 3) Remplir les champs comme ci-dessous pour configurer la vm :



The screenshot shows the 'Create: Virtual Machine' window in Proxmox, with the 'General' tab selected. The fields are configured as follows:

- Node:** SRVDEPLOY-S3P1
- Resource Pool:** SIO2
- VM ID:** 202
- Name:** SRV-AD2
- Add to HA:** ☐
- Start at boot:** ☐
- Start/Shutdown order:** any
- Startup delay:** default
- Shutdown timeout:** default
- vCPU Architecture:** Default (Host Architecture)
- Tags:** No Tags (+)

At the bottom, there is a 'Help' icon, an 'Advanced' checkbox (checked), and 'Back' and 'Next' buttons.



The screenshot shows the 'Create: Virtual Machine' window in Proxmox, with the 'OS' tab selected. The fields are configured as follows:

- Use CD/DVD disc image file (iso):** ☒
- Storage:** local
- ISO image:** SERVER_EVAL_x64FR
- Guest OS:**
 - Type:** Microsoft Windows
 - Version:** 11/2022/2025
- Use physical CD/DVD Drive:** ☐
- Do not use any media:** ☐
- Add additional drive for VirtIO drivers:** ☐

At the bottom, there is an 'Advanced' checkbox (checked), and 'Back' and 'Next' buttons.

Create: Virtual Machine

General

OS

System

Disks

CPU

Memory

Network

Confirm

Graphic card: Default

Machine: q35

Firmware

BIOS: OVMF (UEFI)

Add EFI Disk: ☒

EFI Storage: local-vm

Format: Raw disk image (raw)

Pre-Enroll keys: ☒

SCSI Controller: VirtIO SCSI single

Qemu Agent: ☐

Add TPM: ☒

TPM Storage: local-vm

Format: Raw disk image (raw)

Version: v2.0

Help

Advanced ☒

Back

Next

Create: Virtual Machine

General

OS

System

Disks

CPU

Memory

Network

Confirm

sata0

Disk

Bandwidth

Bus/Device: SATA 0

Storage: local-vm

Disk size (GiB): 80

Format: Raw disk image (raw)

Cache: Default (No cache)

Discard: ☐

IO thread: ☐

SSD emulation: ☐

Read-only: ☐

Backup: ☒

Skip replication: ☐

Async IO: Default (io_uring)

Add

Import

Help

Advanced ☒

Back

Next

Create: Virtual Machine

General
OS
System
Disks
CPU
Memory
Network
Confirm

Sockets:
1

Cores:
2

Type:
Default (x86-64-v2-AES)

Total cores:
2

VCPUs:
2

CPU units:
100

CPU limit:
unlimited

Enable NUMA:
☐

CPU Affinity:
All Cores

Extra CPU Flags:

State	Value	Flag	Description	Supported On
Default	- ☐ ☒ ☐ +	nested-virt	Controls nested virtualization, namely 'svm' for AMD CPUs and 'vmx' for Intel CPUs. Live migration still only works if it's the same flag on both sides. Use a CPU model similar to the host, with the same vendor, not x86-64-vx!	SRVDEPLOY-S3P1
Default	- ☐ ☒ ☐ +	aes	Activate AES instruction set for HW acceleration.	SRVDEPLOY-S3P1
Default	☐ ☐ ☒ ☐	amd-ssbd	Improves Spectre mitigation performance with AMD	SRVDEPLOY-S3P1

☒ Only show flags supported by at least one node
Showing flags for KVM

? Help

Advanced ☒

Back

Next

Create: Virtual Machine

General
OS
System
Disks
CPU
Memory
Network
Confirm

Memory (MiB):
8000

Minimum memory (MiB):
8000

Shares:
Default (1000)

Ballooning Device:
☒

Allow KSM:
☒

? Help

Advanced ☒

Back

Next

Create: Virtual Machine

General OS System Disks CPU Memory **Network** Confirm

☐ No network device

Bridge: **vmbrSIO2** Model: **Intel E1000**

VLAN Tag: **no VLAN** MAC address: **auto**

Firewall: ☒

Disconnect: ☐ Rate limit (MB/s): **unlimited**

MTU: **Same as bridge** Multiqueue:

Help Advanced ☒ **Back** **Next**

Create: Virtual Machine

General OS System Disks CPU Memory Network **Confirm**

Key ↑	Value
bios	ovmf
cores	2
cpu	x86-64-v2-AES
efidisk0	local-lvm:1,efitype=4m,pre-enrolled-keys=1
ide2	local:iso/SERVER_EVAL_x64FRE_fr-fr.iso,media=cdrom
machine	q35
memory	8000
name	SRV-AD2
net0	e1000,bridge=vmbrSIO2,firewall=1
nodename	SRVDEPLOY-S3P1
numa	0
ostype	win11
pool	SIO2
sata0	local-lvm:80
scsihw	virtio-scsi-single

☐ Start after created

Advanced ☒ **Back** **Finish**

4) Appuyez sur « finish »

5) Faire double clic gauche sur la vm configuré

6) Choisir la langue française.

7 Appuyez sur "Installer maintenant".

8) Choisir : "Windows Server 2025 Standard Evaluation (Expérience utilisateur)"

9) Type d'installation : "Personnalisée"


10) Définir le mot de passe administrateur : « Azerty13. »

11) Aller dans Gestionnaire de serveur > Serveur local

12) Cliquer sur le nom de l'ordinateur > Modifier

13) Nouveau nom : SRV-AD2

14) Domaine : immosud.local



15) Entrer les identifiants

16) Redémarrer la VM


17) Appuyer sur Ethernet

18) Clic droit > propriétés

19) Désactiver le Protocole Internet v6.


20) Double-cliquer sur Protocole Internet v4

21) Configurer les adresses IP comme indiqué dans les captures




22) Appuyer sur valider


23) Activer le bureau à distance dans les propriétés système.




24) Désactiver la Configuration de sécurité renforcée d'Internet Explorer



25) Dans le *Gestionnaire de serveur*, cliquer sur *Gérer* > *Ajouter des rôles et fonctionnalités*




26) Installer le rôle Services AD DS



27) Une fois installé, cliquer sur le drapeau jaune en haut et choisir "Promouvoir ce serveur en contrôleur de domaine"

28) Sélectionner "Ajouter un contrôleur de domaine à un domaine existant"

29) Vérifier que le domaine est bien immosud.local



30) Suivre l'assistant (laisser les options par défaut : Serveur DNS, Catalogue Global)

31) Mettre mot de passe de restauration

The screenshot shows the 'Options du contrôleur de domaine' window. The left sidebar lists the steps: Configuration de déploiement, Options du contrôleur de domaine (selected), Options DNS, Options supplémentaires, Chemins d'accès, Examiner les options, Vérification de la configuration, Installation, and Résultats. The main area is titled 'Options du contrôleur de domaine' and 'SERVEUR CIBLE SRV-AD2.immosud.local'. It contains the following options:

- Spécifier les capacités du contrôleur de domaine et les informations sur le site:
 - ☒ Serveur DNS (Domain Name System)
 - ☒ Catalogue global (GC)
 - ☐ Contrôleur de domaine en lecture seule (RODC)
- Nom du site : Default-First-Site-Name (dropdown menu)
- Taper le mot de passe du mode de restauration des services d'annuaire (DSRM):
 - Mot de passe : [password field]
 - Confirmer le mot de passe : [password field]

At the bottom, there are buttons: < Précédent, Suivant >, Installer, and Annuler. A link 'En savoir plus sur les options pour le contrôleur de domaine' is also present.

32) Installer

The screenshot shows the 'Installation' window. The left sidebar is the same as in the previous window, but 'Installation' is now selected. The main area is titled 'Installation' and 'SERVEUR CIBLE SRV-AD2.immosud.local'. It contains the following options:

- État d'avancement:
 - ☒ Afficher les résultats détaillés de l'opération

At the bottom, there are buttons: < Précédent, Suivant >, Installer, and Annuler. A link 'En savoir plus sur les options d'installation' is also present.