Finding Change in Launch Angle

Motivation: When trying to change the launch angle of the cannon, one method is clicking and dragging the cannon up or down. Assuming the cannon is successfully clicked, the following argument lets us find how far up or down the angle of elevation of the cannon should be altered.

Consider the following diagram:




Figure 1: Overview of the whole cannon

Point B represents where the user would have clicked the cannon, and point C represents where the user would have dragged the mouse to. The general thought process is to find point E such that the CE has a length of μW , equal to the segment that passes through B and is perpendicular to AD. The angle between AE and AD, θ , is the change in angle of elevation.

Note that the value of μ would have been previously evaluated when deciding whether the user had clicked the cannon or not.

Let

$$\overrightarrow{OA} = \begin{pmatrix} a_1 \\ a_2 \end{pmatrix}, \ \overrightarrow{OB} = \begin{pmatrix} b_1 \\ b_2 \end{pmatrix}, \ \overrightarrow{OC} = \begin{pmatrix} c_1 \\ c_2 \end{pmatrix}, \ \overrightarrow{OD} = \begin{pmatrix} d_1 \\ d_2 \end{pmatrix} \ \text{and} \ \overrightarrow{OE} = \begin{pmatrix} e_1 \\ e_2 \end{pmatrix}$$

where O represents the origin point of our coordinate system. Also note that $a_1, a_2, b_1, b_2, c_1, c_2, d_1$ and d_2 are known.

Therefore,

$$\overrightarrow{AC} = \begin{pmatrix} c_1 - a_1 \\ c_2 - a_2 \end{pmatrix}$$

Let $\alpha = \angle CAE$ such that $\alpha \in [0, \frac{\pi}{2}]$ as per Figure 1. Therefore, $\sin \alpha = \frac{|\overrightarrow{CE}|}{|\overrightarrow{AC}|} = \frac{\mu W}{|\overrightarrow{AC}|}$ where $|\overrightarrow{AC}| = \sqrt{(c_1 - a_1)^2 + (c_2 - a_2)^2}$. Therefore we can conclude that $\alpha = \arcsin\left(\frac{\mu W}{|\overrightarrow{AC}|}\right)$.

Using Figure 1 again we can see that $|\overrightarrow{AE}| = |\overrightarrow{AC}| \cos \alpha$.

Now consider the following diagram:




Figure 2: Focusing on line segments AC and AE

Recall that α has already been defined as $\angle CAE$. We can also define β to be $\angle CAX$ and therefore infer that $\angle EAX = \beta - \alpha$ as indicated in Figure 2.

We can say that $\beta = \arctan\left(\frac{c_2 - a_2}{c_1 - a_1}\right)$ by inspecting Figure 2.

We can finally see that

$$\cos(\beta - \alpha) = \frac{e_1 - a_1}{|\overrightarrow{AE}|}$$

$$\implies e_1 = |\overrightarrow{AE}|\cos(\beta - \alpha) + a_1.$$

Similarly

$$e_2 = |\overrightarrow{AE}|\sin(\beta - \alpha) + a_2.$$

So we can say that
$$\overrightarrow{OE} = \begin{pmatrix} |\overrightarrow{AE}|\cos(\beta - \alpha) + a_1 \\ |\overrightarrow{AE}|\sin(\beta - \alpha) + a_2 \end{pmatrix}$$

Consider the dot product between \overrightarrow{AC} and \overrightarrow{AE} .

$$\overrightarrow{AC} \cdot \overrightarrow{AE} = |\overrightarrow{AE}| |\overrightarrow{AC}| \cos \theta$$

$$\implies \cos \theta = \frac{\overrightarrow{AC} \cdot \overrightarrow{AE}}{|\overrightarrow{AE}| |\overrightarrow{AC}|}$$

$$\implies \theta = \arccos \left(\frac{\overrightarrow{AC} \cdot \overrightarrow{AE}}{|\overrightarrow{AE}| |\overrightarrow{AC}|} \right).$$