实验六 OSPF协议配置

实验目的

- (1)掌握 OSPF 协议的配置方法:
- (2)掌握查看通过动态路由协议 OSPF 学习产生的路由;
- (3)熟悉广域网线缆的链接方式:

实验背景

假设校园网通过一台三层交换机连到校园网出口路由器上,路由器再和校园外的另一台路由器连接。现要做适当配置,实现校园网内部主机与校园网外部主机之间的相互通信。为了简化网管的管理维护工作,学校决定采用 OSPF 协议实现互通。

技术原理


OSPF 开放式最短路径优先协议,是目前网路中应用最广泛的路由协议之一。属于内部网管路由协议,能够适应各种规模的网络环境,是典型的链路状态协议。OSPF 路由协议通过向全网扩散本设备的链路状态信息,使网络中每台设备最终同步一个具有全网链路状态的数据库,然后路由器采用 SPF 算法,以自己为根,计算到达其他网络的最短路径,最终形成全网路由信息。

实验步骤

- (1)新建 packet tracer 拓扑图
- (2)在本实验中的三层交换机上划分 VLAN10 和 VLAN20, 其中 VLAN10 用于连接校园 网主机, VLAN20 用于连接 R1。
- (3)路由器之间通过 V35 电缆通过串口连接, DCE 端连接在 R1 上, 配置其时钟频率 64000。
- (4)主机和交换机通过直连线,主机与路由器通过交叉线连接。
- (5)在 S3560 上配置 OSPF 路由协议。
- (6)在路由器 R1、R2 上配置 OSPF 路由协议。
- (7)将 PC1、PC2 主机默认网关设置为与直连网路设备接口 IP 地址。
- (8)验证 PC1、PC2 主机之间可以互相同信;

实验设备

PC 2 台; Switch 3560 1 台; Router-PT 2 台; 直连线; 交叉线; DCE 串口线



PC1

IP: 192.168.1.2

Submask: 255.255.255.0 Gateway: 192.168.1.1 PC2 IP: 192.168.2.2 Submask: 255.255.255.0 Gateway: 192.168.2.1 S3560 en conf t hostname S3569 vlan 10 exit vlan 20 interface fa 0/10 switchport access vlan 10 exit int fa 0/20 switchport access valn 20 exit interface valn 10 ip address 192.168.1.1 255.255.255.0 no shutdown exit interface vlan 20 ip address 192.168.3.1 255.255.255.0 no shutdown

> end show ip route

conf t
ip routing
router ospf 1
network 192.168.1.0 0.0.0.255 area 0
network 192.168.3.0 0.0.0.255 area 0
end

R1

en conf t hostname R1 interface fa 0/0 no shutdown

show ip route

```
ip address 192.168.3.2 255.255.255.0 exit interface serial 2/0 no shutdown clock rate 64000 ip address 192.168.4.1 255.255.255.0 end show ip route conf t router ospf 1 network 192.168.3.0 0.0.0.255 area 0 network 192.168.4.0 0.0.0.255 area 0 end show ip route
```

R2

en
conf t
hostname R2
interface fa 0/0
no shutdown
ip address 192.168.2.1 255.255.255.0
exit

interface serial 2/0 no shutdown ip address 192.168.4.2 255.255.255.0 end show ip route

conf t router ospf 1 network 192.168.2.0 0.0.0.255 area 0 network 192.168.4.0 0.0.0.255 area 0 end show ip route