# DTM(Dynamic Task Manager) Version 4.0 Installation Guide (English)

November 1, 2014



# Procedure (Summary)


	Extract Download File	Files after extracting downloaded DTM Install Package
P1 – P7		DTM Installation Guide  DTM_Default  Files for Aras Import Tool  Import  Aras Import Package  DTM-4,0-setup,exe  DTM LicenseKeyRequest,exe  Create DTM License Key Request File  Execute Aras Import Tool (/Import/import.exe)  Aras Innovator connection, Manifest File (imports.mf) load/Import, Create Aras InnovatorICDTM Item  Modify Aras Innovator Screen Config (6 files)  - ProjectTree.htm  - projectTee_toolbar.xml  - projectTree_toolbar.xml  - projectTree_toolbar.xml  - itemsGrid.html
	Connect to Aras Innovator remote server	
	1. Modify Aras Innovator	
	1.1.Aras Innovator Item Import	
	1.2.Verify Aras Innovator Item Import	
	1.3.Aras Innovator File Modify	
		p. 6,650.1.100_100.00.1.1.111
P8 – P10	2.DTM Installation	Execute DTM Installer Input necessary information, Source Unpacking, Database Object
		Creation, Input configuration Info
P11	3.Deploy	DTM deploy DTM deploy on running Aras Web Server (IIS)
P12	4. DTM License Key request & set-up	
	4.1. Create DTM License Key Request File	
	4.2.Send Zionex DTM License Key Request File	
	4.3.Set up DTM License Key Request File	
P13 – P14	5. Verify execution of DTM	







1.1. Aras Innovator Item Import

- 1 Execute import.exe in Aras Import Package
  - Path:
    - ex) {DTM Install Package}¥Import



- Server: Input Server URL on which DTM Package apply
- Database: Select Database
- Username: Input Admin User ID ("root" or "admin")
- Password: Input password of the above User ID (Default: "innovator")
- 3 Login









# 1.1. Aras Innovator Item Import


- 4 TargetRelease: Input Aras targeted Release Version (Ex: 10.0 SP1)
- ⑤ Description: Input description which explain purpose of use (Ex:"Trial")

⑥ Manifest File: Search path which contains mf file in Import Package then specify imports.mf
DTM Install Package/DTM Default/ imports.mf

- Select all the list for import
- ® Type: Select Merge / Mode : Select "Thorough Mode"









1.2. Verify Aras Innovator Item Import

□ Contents

Administrator

Documents

Activity Issue List


♣ InBasket.
∰ Project Templetes


My Innovator


Templatas

- ① Verify that "DTM Default" is appropriately applied.
  - Login Aras Innovator and check TOC menu

- ② Verify that "Com.Aras.Innovator.Solution.Package" is appropriately applied
  - 1) Search Name="Activity2" in TOC>Administrator>Itemtype







DTM Menu



sub project plan start

# 1.3. Aras Innovator File Modify

Edit Aras Innovator Screen configuration files with text editor (1/4)

{Aras Innovator}¥Innovator¥Client¥Solutions¥Project¥scripts¥ProjectTree.htm

#### Add the red text below;

1-2

```
case 'show_gantt_chart':
showGantt();
break;

1-1 case 'show_scheduling_gantt_chart':
showGanttChartView();
break;
case 'execute_filter':
setFlagsAndExecuteFilterOrClearFilter();
break;
...
```

```
...
</body>
<script LANGUAGE='JavaScript' SRC='modal.js'></script>
<script LANGUAGE='JavaScript' SRC='ProjectTreeAdd.js'></script>
</html>
...
```



# 1.3. Aras Innovator File Modify

Edit Aras Innovator Screen configuration files with text editor (2/4)

Add the red text below;

① {Aras Innovator}¥Innovator¥Client¥Solutions¥Project¥xml(.language)¥projectTree\_toolbar.xml

```
2-1
Coutton image="../images/ProjectCollapseAll.svg" id="collapse_all" tooltip="Collapse All" text="Collapse All"/> 
Separator/>
Coutton image="icons/Project/20x20_GanttChart_new.gif" id="show_scheduling_gantt_chart" tooltip="Show Gantt Chart" text="Show Gantt Chart"/>
Coutton image="../images/GanttChart.svg" id="show_gantt_chart" tooltip="Show Gantt Chart" text="Show Gantt Chart"/>
...
```

②{ArasInnovator}¥Innovator¥Client¥Solutions¥Project¥xml(.language)¥projectTemplateTree\_toolbar.xml

- In case that other folder other than xml folder such as xml.ja, please edit the folder information which is created for localization, as well as xlm. The structure is same as xml folder.



# 1.3. Aras Innovator File Modify

Edit Aras Innovator Screen configuration files with text editor (3/4)

☆You can skip this if you do not use "Project Load Summary".

{Aras Innovator}¥Innovator¥Client¥scripts¥MainMenu.aspx

#### Add the red text below;

```
else if (cmdID == 'help_context') {
  top.aras.ShowContextHelp(itemTypeName);
}
else if (cmdID == 'show_projects_load_summary') {
    showLoadSummaryView();
}
else if (cmdID == 'current_session')
  onMySession();
...
```

```
onunload = function unload_handler() {
    aras.unregisterEventHandler("VariableChanged", window, window.onVariableChanged);
    aras.unregisterEventHandler("PreferenceValueChanged", window, window.onPreferenceValueChanged);
}
</script>
</script LANGUAGE='JavaScript' SRC='modal.js'></script>
</script LANGUAGE='JavaScript' SRC='MainMenuAdd.js'></script>
</head>
</html>
```

# 1.3. Aras Innovator File Modify

Edit Aras Innovator Screen configuration files with text editor (4/4)

☆You can skip this if you do not use "Project Load Summary".

Add the red text below;

#### {Aras Innovator}¥Innovator¥Client¥xml(.language)¥main\_toolbar.xml

```
...
<br/>
<button text="Logout" id="Logout" image="../images/Exit.svg" tooltip="Logout" statusmsg="Logout"/>
<separator/>
<button image="../images/20x20 DTMLoad.gif" id="show_projects_load_summary" tooltip="Show Projects Load Summary" text="Show Project Load Summary" disabled="true"/>
</toolbar>
<toolbar id="inbasket_toolbar">
...
```

#### {Aras Innovator}¥Innovator¥Client¥scripts¥itemsGrid.html

```
function onInitialize()
{
    setControlEnabledProjectsLoadSummary();
    currItemType = arasObj.getItemTypeDictionary(arasObj.getItemTypeName(itemTypeID));
    if (!currItemType || currItemType.isError())
    {
        currItemType = null;
        return false;
    }
}
```


# 2. DTM Installation



# 2. DTM Installation (1/3)

#### **Execute DTM-4.0-setup.exe**

- 1 Input Aras Innovator installation path
- 2 Destination Folder: Aras Innovator installation default path is preliminary setup ex) C:\(\mathbb{P}\)rogram Files (x86)\(\mathbb{A}\)ras\(\mathbb{I}\)Innovator
- ③ In case that Aras is installed in non-default path, please change path
- 4 Click [Next]







# 2. DTM Installation (2/3)

- ⑤ Select Aras Database on which you add-on DTM
- 6 Click [Next]

#### Input the information for Server configuration

- Input Web Alias of Aras Innovator.
  - ✓ Basically the Web Arias. Default is preliminary setup.
  - ✓ In case that Aras is installed in non-default path, please change path
- 8 Input ID/Password (Admin / innovator)
- 9 Input DTM Web Alias DTM. Default (DTM Server)is preliminary setup.
- ① Click [Next]








# 2. DTM Installation (3/3)

- **(1)** Input DTM Install Path
- ① Destination Folder: Default path is same as Aras Innovator installation path.
  - ex) C:\(\text{Program Files (x86)}\(\text{ZIONEX}\(\text{DTM}\)
- 12 In case you install non-default path, please change path
- (13) Click [Install]




#### Complete page





#### Progress page





# 3. Deploy



# 3. Deploy(1/1) Add Application Program

- ① Click Right mouse button > Select "Add Application Program"
- 2 Input the information in Popup window "Add Application program"
  - Name: Input DTM Web Alias ex) DTMServer
  - Application program pool: ASP.NET v4.0
  - Path: Input DTM Source path ex) C:\(\text{Program Files (x86)}\(\text{\text{ZIONEX\text{\text{YDTM\text{YDTM\text{YDTM\text{YDTM\text{YDTM\text{\text{YDTM\t
- 3 Click [OK]





# 4. DTM License Key request & set-up




# 4. DTM License Key request & set-up



- 1. Create DTM License Key Request File
  - Execute DTMLicenseKeyRequest.exe
  - ② Input your Company Name(Mandatory)
  - 3 Select option and click [Create] button
  - Confirm that dtm\_license.lic is created in the same folder
- 2. Please mail dtm\_license.lic to <a href="mailto:sales-j@zionex.com">sales-j@zionex.com</a> to request DTM License Key
- 3. Zionex will send you dtm\_license.lic with License Code
- Copy dtm\_license.lic in DTM installation folder

(ex)C:\(\texit{Program Files}\)(x86)\(\texit{\texit{ZIONEX\text{YDTM\text{YDTM}}}\)








# 5. Verify execution of DTM



# 5. Verify execution of DTM — Verify execution of Gantt Chart

#### Clear cash on the browser, restart Aras Innovator, then confirm the below 123

- 1 Open Aras Innovator Project
- 2 Click DTM Gantt Icon
- (3) Confirm that DTM Gantt Chart shows






# 5. Verify execution of DTM — Verify execution Project Load Summary Graph

In case you selected "Project Load Summary Graph", please confirm below;

- 1 Select Aras Innovator Project list
- 2 Click "Projects Load Summary Graph" Icon
- ③ Confirm that "Projects Load Summary Graph"



# **Trouble shooting in DTM execution**



### 1. Check web.config

- ① Open web.config with text editor
  (ex)C:\(\text{Program Files (x86)}\)\(\text{ZIONEX}\)\(\text{DTM}\)\(\text{DTM}\)\(\text{veb.config}\)
- 2 Check the configuration by DTM installation is correct
- 3 Please modify in case there are any incorrect description.

```
<!-- Start DTM Configlation Set -->
  <!-- For Aras Connection Info -->
  <add key="aras con info" value="http://localhost/InnovatorServer/Server/InnovatorServer.aspx"/>
  <add key="aras user info" value="admin"/>
  <add key="aras password info" value="innovator"/>
  <add key="aras_install_info" value="C:\\Program Files (x86)\\Aras\\Innovator\\"/>
  <!-- For DTM Connection Info -->
  <add key="dtm con info" value="/DTMServer/"/>
  <add key="dtm install info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\DTM"/>
  <add key="gantt define info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\DTM\\Gantt\\DTMGanttDef.xml"/>
  <add key="gantt temp define info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\Gantt\\DTMGanttTempDef.xml"/>
  <add key="gantt resource define info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\Gantt\\DTMResourceDef.xml"/>
  <add key="gantt projects define info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\DTM\\Gantt\\DTMProjectsDef.xml"/>
  <add key="gantt projects resource define info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\DTM\\Gantt\\DTMProjectsResourceDef.xml"/>
  <!-- For DTM Scheduling Logic Info-->
  <add key="dtm scheduling info" value="1"/>
  <!-- For DTM License Info -->
  <add key="dtm license info" value="C:\\Program Files (x86)\\ZIONEX\\DTM\\License\\dtm license.lic"/>
<!-- End DTM Configlation Set -->
```


#### ☆ Check the setting value on DTM execution

- aras\_con\_info : Aras Innovator URL
- aras user info : Admin ID
- aras\_password\_info : Admin Password
- aras\_install\_info : Aras installation path
- dtm\_con\_info : DTM Connetion path
- dtm\_install\_info : DTM installation path
- dtm\_license\_info : DTM License file path and file name



#### 2. Check DTM Load Function (Database)

- (1) Connect to Aras Database(Default: InnovatorSolutions) by DB tool such as SQL Server Management.
- 2 Check that there exist function as "DTM\_select\_dtm\_data", "DTM\_select\_holiday\_calendar\_data", "DTM\_select\_lead\_role\_leader\_data" in Programmability > Functions > Table-valued Functions
  - Check that there exist procedure as "DTM\_wbs\_rollup\_shed" in Programmability > Stored Procedures
- 4 In case there is no Function or Procedure, please execute SQL which is sql\_backup folder of DTM installation folder (ex)C:\(\text{Program}\) Files (x86)\(\pmazIONEX\(\pmaxDTM\)\(\pmaxDTM\)



- DTM Grid data Load Function

DTM\_select\_holiday\_calendar\_data:

DTM select lead role leader data:

- Aras leader, lead roll list DTM Load

- WBS alignment Function for data save



#### 3. Check IP address in case of Aras localhost installation

You may have trouble in connection between Aras and DTM function, in case of Aras localhost installation (ex>http://localhost/InnovatorServer). Aras connection requires IP address.

- ① Open {Aras Innovator}¥Innovator¥Client¥Solutions¥Project¥scripts¥ProjectTreeAdd.js with text editor
- 2 Check DTM URL by showGanttChartView() Function, modify IP address to Local host IP address.
  - XIP address is recommended like below;

(Ex)http://localhost/InnovatorServer ->http://123.123.123.123/InnovatorServer



End of Document