Instruction Set


Ram Sarkar

Instruction sets

Purpose: To **specify** an operation to be carried out & the set of operands/data to be used.

- -The operation is specified by a field called the **opcode**.
- The operand fields contain the addresses of storage locations in main memory or in the processor.

Most instructions specify a register transfer operation of the form $X_1 \leftarrow f(X_1, X_{2}, ..., X_n)$, which involves n operands.



- -To reduce the instruction size, specify m<n operands explicitly in the instruction, the remaining operands are implicit.
- Explicit address : Main memory
- Implicit address: Register
 - -It is called *m-address machine*
- Implicit input operands must be placed in locations known to CPU.

Machine Instructions

- A computer must have instructions capable of performing four types of operations:
 - Data transfers between the memory and the processor registers
 - Arithmetic and logic operations on data
 - Program sequencing and control
 - Input/Output (I/O) transfers

Data Transfers: Possible Locations

- Memory locations
- Processor registers
- Registers in the I/O subsystem
- In the instruction itself (immediate data)

Most of the time we identify a location by a symbolic name standing for its hardware binary address:

- Memory Locations: LOC, A, VAR2
- Processor register names: R0, R5, R10
- •I/O register names: DATAIN, OUTSTATUS

Data Transfers: Register Transfer Notation

[LOC] means the contents of the location LOC

R1 ← [LOC] means that the contents of memory location LOC are transferred into processor register R1

R3 ← [R1]+[R2] means that the sum of the contents of registers R1 and R2 is transferred into processor register R3

Data Transfers: Assembly Language Notation

Move LOC, R1

means that the contents of memory location LOC are transferred into processor register R1

This is equivalent to R1<- [LOC] in Register Transfer Notation

In the IBM PC the instruction MOV is equivalent to Move

Data Transfers: Assembly Language Notation

Move Source, Destination

means that the contents of memory location Source are transferred into memory location Destination.

As a result, the previous contents of memory location Destination will be replaced, but the contents of memory location Source will not be changed

The instruction Move copies the contents of one memory location to another one

Different Formats

Book:

Format

OPcode src, dst

IBM PC Assembly

Format

OPcode dst, src


MOV Instruction

In IBM PC you are talking about the contents of a variable (Move), not its memory address (←), hence, if:

X is a variable with memory address 10H and its contents are 24H

1)The instruction: MOV AX,X moves 24H into AX

2) The instruction MOV AX,[X] moves 87H into AX



Basic Instruction Types

C=A+B

How is this high-level language command implemented in the computer?

To carry out the action

$$C \leftarrow [A]+[B]$$

the contents of memory locations A and B are fetched from memory and transferred into the processor, where their sum is computed and then transferred to memory location C

Three-Address Instruction

General form: Operation Source1, Source2, Destination

Add A, B, C

Disadvantage: This form has 3 operands. If memory addresses were to be used to specify operands, the memory space would be very limited.

Example: if k=10 bits (enough for a memory of 1 KB), then 30 bits will be needed for the 3 operands.

Two-Address Instruction

General form: Operation Source, Destination

Add A, B performs the operation $B \leftarrow [A]+[B]$.

The result is sent to memory and stored in location B, replacing the original contents of this location.

 $C \leftarrow [A]+[B]$ can be implemented as

Move B, C

Add A, C

Even a 2-address instruction is **too large** for a processor with a 32-bit address space!

One-Address Instruction

General form: Operation Source

Examples:

Add A: Add the contents of memory location A to the contents of the accumulator register and place the sum back into the accumulator

Move A: Copy the contents of memory location A to the accumulator register

Store A means: Copy the contents of the accumulator register to memory location A

One-Address Instruction

Thus, $C \leftarrow [A]+[B]$ can be implemented as

(Assembly Language)

Move A

Add B

Store C

Notice that now the 32-bits will be use only to access 1 memory location and to denote the operation

which means (Register Notation):

Accumulator ← [A]

Accumulator ← [Accumulator] + [B]

C ← [Accumulator]

A two-operand instruction, how is it possible? One Register, One memory location

One-Address Instruction

In the IBM PC, $C \leftarrow [A]+[B]$ can be implemented as

Assembly Language Register Notation

 $MOV \quad AX,A \qquad ; [AX] \leftarrow [A]$

ADD AX,B ; $[AX] \leftarrow [AX] + [B]$

MOV C,AX ; $[C] \leftarrow [AX]$

Notice that in the IBM PC Assembly Language the operation "addition" is represented by the instruction "ADD".

The symbol ";" is used to indicate the start of comments.

Comments are useful to remind us what the program is doing, but they do NOT effect the behavior of it

Processor Registers

- Because the number of registers is relatively small, only a few bits are needed to specify, which register takes part in an operation
- For example, for 32 registers only 5 bits are needed to address them

Using Processor Registers for Arithmetic Operations

C=A+B that is, $C \leftarrow [A]+[B]$ can be implemented as

```
Move A, Ri
```

Move B, Rj

Add Ri, Rj

Move Rj, C

4 instructions

If we wanted to do it in this manner, for the IBM PC we would have:

MOV DX,A

MOV AX,B

ADD AX,DX

11/25/20**2/10V C,AX**

JUCSE

If One of the Arithmetic Operands is in Memory

C=A+B that is, $C \leftarrow [A]+[B]$ can be implemented as

Move A, Ri

Add B, Ri

3 instructions

Move Ri, C

For the IBM PC we would have:

MOV AX,A

ADD AX,B

MOV C,AX

Addressing Modes

Name	Assembler syntax	Addressing function
Immediate	#Value	Operand = Value
Register	R <i>i</i>	EA = Ri
Absolute (Direct)	LOC	EA = LOC
Indirect	(R <i>i</i>) (LOC)	EA = [Ri] EA = [LOC]
Index	X(R <i>i</i>)	EA = [Ri] + X
Base with index	(Ri,Rj)	$EA = \left[Ri\right] + \left[Rj\right]$
Base with index and offset	X(R i,Rj)	EA = [Ri] + [Rj] + X
Relative	X(PC)	EA = [PC] + X
Autoincrement	(R <i>i</i>)+	EA = [R <i>i</i>]; Increment R <i>i</i>
Autodecrement	-(R <i>i</i>)	Decrement Ri ; EA = $[Ri]$

EA = Effective address Value = a signed number

Addressing Modes

- Operand associates with data X.
- To execute, CPU needs the current value of X.
- It can be specified in several ways: *addressing modes*
- If the X is constant, then its value can be placed in the operand field;
- X is called *immediate operand* and the mode of operand specification is called <u>immediate</u> addressing.


- Corresponding operand field contains the address X of the storage location containing the required value.
- Operand value can be varied without modifying any instruction address: **Direct Addressing**
- It is frequently useful to change the location of X without changing the address fields of any instructions that refer to X. **Indirect Addressing**

- Direct Addressing requires one fetch operation to obtain an operand value, while Indirect Addressing requires two.

MOV A, B (A<-B)
Direct Addressing (register-to-register transfer)


MVI A, 99 (A<- 99) Immediate operand

- uses both Direct & Immediate addressing modes.



(b) Direct Addressing

LOAD W



Direct Addressing Mode

Immediate Addressing Mode

Address fields contains the effective address of operand

There is no address field as the operand is a part of the instruction.

It requires one reference to memory.

It does not require any reference to memory.

It is slower compared to immediate mode.

It is a faster process.

It has more range than in immediate mode.

It has a limited range.

Example: Add (1001)

Example: ADD 5

Orthogonality: The ability to use all relevant addressing modes in a uniform and consistent way with all opcodes of an instruction set.

- Simplifies programming both
- by reducing the number of opcodes needed &
- by simplifying the rules for operand address specification.

Absolute Addressing:- Simplest mode of (direct) address formation.

- Requires complex operand address to appear in the instruction operand field.
- Address is used without further modification to access the desired data item.

Relative Addressing:-

- Partial addressing information is included in the instruction.
- Complete address must be constructed by CPU.
- Operand field has a relative address or displacement D.

- Instruction can identifies storage locations R₁,R₂
- Effective address A is f(D,R₁,R₂,...,R_k)

In general, A = R + D, R may be PC.

Advantages:

1) Since all the address information need not be included, instruction length is reduced.

- 2) By changing the contents of R, CPU can change the absolute address referred to by a block of instruction B.
- Relocation of entire region becomes easier.
- R acts as a <u>base register</u>. (content is called base address)

- 3. Facilitates the process of indexed data
- R is called the **INDEX REGISTER**.
- Indexed terms X(0), X(1),...,X(n) are stored in the consecutive addresses of Main Memory.
- D contains the address of X(0)
- R contains the Index 'i'.
- X(i)=D+R; by changing the contents of R, a single instruction can be made to refer to any item X(i) in the list.

Issues:

- Extra logic circuits and extra processing time required for address computation.
- Indexed items are frequently accessed sequentially, a process called 'AUTOINDEXING' is required which automatically increments or decrements an address.

(A)- and (A)+: First one indicates that contents of A should be *decremented* automatically before the instruction is executed, whereas the latter one *increments* automatically after the current instruction has been executed.

- Autoindexing facilitates another addressing mode:
 - Stack addressing: Part of Main Memory

-Two options:

Push - stores a new item at the top of the stack

Pop - removes the item stored at the top

- -Controlled by the register called **STACK POINTER**.
- Automatically adjusted by the push/pop operation.
- Stack grows towards the *low address*.


O-Address machine: stores operands in a pushdown stack

ADD	It causes the top two operands to be removed from the stack and added. The sum is placed at the TOS
PUSH A	Transfer A to TOS
PUSH B	
MULT	Remove A and B from stack and replace by A*B
PUSH C	
PUSH C	
MULT	Remove C and C, and replace the TOS by C
ADD	$(C^*C) + (A^*B)$
POP X	Transfer the results from TOS to X

Specific Machine Levels

High-Level Language Level 5 Assembly Language Level 4 Operating System Level 3 Instruction Set Architecture Level 2 Microarchitecture Level 1 Digital Logic Level 0

Translating Languages



Queues / FIFOs


- □ First In First Out
 - Buffer data between two entities:
 - Keyboard => Processor
 - □ Processor => Printer
 - Processor1 => Processor2
 - Scheduling as well:
 - Printer queue
 - Queue of processes for multi-tasking
 - Queues may use priority ranking

Queues / FIFOs

- □ First In First Out
 - The two basic functions are:
 - APPEND an element on one end
 - REMOVE an element from the other
 - Frequently, one entity appends items to the queue and another removes it
 - Two moving pointers are needed:
 - IN: location for next APPEND
 - OUT: location for next REMOVE
 - Wrap-around is needed

Queues / FIFOs

- Pointers usually managed by hardware
- Overflow occurs when an element is appended to a full queue
- Underflow occurs when an element is removed from an empty queue
- May have Empty, Almost Full, Full flags



Stacks/LIFOs

- □ Last In First Out
 - Stacks are used to temporarily store items
 - The two basic functions are:
 - PUSH an element on the top
 - POP the top element from the stack
 - Frequently, the same entity that pushed the item on stack also pops it
 - In contrast to the queue
 - Only one pointer needed it points to the top element
 - PUSH and POP in different directions
 - Wrap-around is not needed

Stacks/LIFOs


Processor Stack

- Dedicated Stack Pointer (SP)
- SP may be a general-purpose register
- SP "grows" towards smaller addresses
- Implementation of stack operations:

```
PUSH: Move NewItem, -(SP)
SP <- [SP] - 1, [SP] <- NewItem
POP: Move (SP)+,TopItem
TopItem <- [[SP]]; SP <- [SP] + 1
```

Subroutines

Program segments may occur repeatedly:



Subroutines

Solution: Call a subroutine multiple times

ACTION 1: ACTION 2 (A) ACTION 2 (B)

```
ACTION 2 (P): ... on data P
```

- Problems:
 - Return address needs to be known!
 - How to pass parameters?
 - Where to keep local variables?

Subroutine Calling

Link register:

- Call SUB LR <- [PC]</p>
 - PC <- SUB
- Return PC <- [LR]</p>
- Address on stack:
 - Call SUB SP <- [SP] 1</p>
 - [SP] <- [PC]
 - PC <- SUB
 - Return PC <- [[SP]]</p>
 - SP <- [SP] + 1

Parameter Passing


Stored in a designated memory area:						
MAIN	Move	parX, A	AddSub	Move	A, R0	
	Move	parY, B		Add	B, R0	
	Call	AddSub		Move	R0, C	
	Move	C, Result		Return		
Stored in de						
MAIN	Move	parX, R0	AddSub	Move	R0, R2	
	Move	parY, R1		Add	R1, R2	
	Call	AddSub		Return		
	Move	R2, Result				
Using the st						
MAIN	Move	parX, -(SP)	AddSub	?		
	Move	parY, -(SP)				
	Call	AddSub		Return		
	Move	?, Result				

Parameter Passing through Stack

Simple Example Re-Using Parameter Space:						
MAIN	Move	PARAM1, -(SP)	; push Param1			
	Move	PARAM2, -(SP)	; push Param2			
	Call	SUBR	; call subroutine			
	Move	(SP), RESULT	; get return value			
	Add	#8, SP	; clean up stack			
SUBR	Move	8(SP), R0	; load Param 1			
	Add	4(SP), R0	; add Param 2			
	Move	R0, 4(SP)	; store result			
	Return		; Result = P1 + P2			

Parameter Addressing

Remember that Return Address is on the Stack too:
After entering SUBR After storing Result After leaving SUBR



Param 1: 8(SP) 4(SP)


Param 2: 4(SP) 4(SP) := Result (SP) = Result


Assumptions:

two 32-bit parameters, no temporary items on stack, result size is 32-bit, result replaces parameter

Subroutine Linkage


- Call instruction is used to call a subroutine
- Subroutine returns
 control to the
 calling program
 when it is done
- Stack is used to pass information





Subroutine Linkage

- Call pushes information onto stack
- Return pops information off of stack
- Stack pointer (SP)
 and Frame pointer
 (FP) used to
 access parameters
 and variables



Frame Pointer

- Each function has local memory associated with it to hold incoming parameters, local variables, and temporary variables.
- This region of memory is called a stack frame and is allocated on the process' stack.
- A frame pointer contains the base address of the function's frame.

Frame Pointer

- □ The code to access local variables within a function is generated in terms of offsets to the frame pointer.
- The stack pointer may change during the execution of a function as values are pushed or popped off the stack (such as pushing parameters in preparation to calling another function).
- The frame pointer doesn't change throughout the function.