ctys- $\mathbf{X}\mathbf{1}\mathbf{1}(1)$

May 19, 2010

Contents

| 1 | NAME | 2 |
|---|-------------|---|
| 2 | SYNTAX | 2 |
| 3 | DESCRIPTION | 2 |
| 4 | OPTIONS | 2 |
| 5 | SEE ALSO | 4 |
| 6 | AUTHOR | 4 |
| 7 | COPYRIGHT | 4 |

ctys-X11(1) 2/4

.

1 NAME

ctys-X11 - X11 Interface

2 SYNTAX

```
ctys -t X11 -a action[=<suboptions>] ...
ctys -T X11 -a action[=<suboptions>] ...
ctys -T ALL -a action[=<suboptions>] ...
```

3 DESCRIPTION

The X11-plugin starts a remote shell within a terminal emulation by default. Alternatively any X11 command with an arbitrary shell could be executed. When executing a command, the functionality is almost equivalent to the CLI plugin.

The primary application of X11 is to utilize the default behaviour of starting an Xsession within it's own terminal emulation on the desktop. Therefore the pre-configured choices are: XTERM, GTERM, and EMACS, which is started in "shell-mode".

4 OPTIONS

```
-a action[=<suboptions>]
     CANCEL
        Not applicable.
     CREATE
        CREATE=<machine-address>[,]
           [(REUSE|CONNECT|RECONNECT|RESUME)][,]
            (CONSOLE: XTERM | GTERM | EMACS | EMACSA)
            (CMD:<cmd>)
           ][,]
           [(CALLOPTS|C):<callopts>][,]
           [CD:<working-directory>][,]
           [(XOPTS|X):<xopts>][,]
           [(SHELL|S):<shell>][,]
           [(DH|SH)][,]
           [(TITLEKEY: <key-name-label> | NOTITLE)]
          <machine-address>
            The LABEL suboption is here the only supported and mandatory part.
          <callopts>
            Refer to common options parts description.
         CD:<working-directory>
            Change current working directory for the started command. This provides for example the pre-
```

configuration of specific work-sets, where each terminal could be opened for a specific directory.

ctys-X11(1) 3/4

CMD:<cmd>

Refer to common options parts description. The CMD could be provided alternatively to a fixed CONSOLE.

CONSOLE: (XTERM|GTERM|EMACS|EMACSA)

A fixed type of a CONSOLE, following types are supported.

CONSOLE:GTERM Starts the "gnome-terminal".

CONSOLE:XTERM Starts the Xterm.

CONSOLE:EMACS Starts an emacs and opens a "shell" buffer.

CONSOLE:EMACSA Starts an emacs and opens an "ansi-term" buffer.

(DH|SH)

Sets a double-hyphen or a single-hyphen for call arguments. Where the single hyphen e.g. is required for old style X11 utility options, the double-hyphen for new options style of Gnome.

NOTITLE

Suppresses the generation of title either from LABEL, or from default.

Be aware, that dynamic sessions like X11 without an LABEL visible by ps, are not - or just limited - recognized by LIST action. Thus the only reliable support for sessions started with this flag is the start itself.

USE|CONNECT|RECONNECT|RESUME

Not applicable.

SHELL|S:<shell>

Refer to common options parts description.

TITLEKEY:<title-name-key>

Alters the options keyword to be used to set the title of an Xwindow, which is set by default to "title". Some older applications, like Xclock support different, e.g. "name" as options keyword only. Due to the crucial role of the window title, which is the LABEL, this approach should be prefered when "title" is not supported. Do use NOTITLE only if definetly unavoidable.

<xopts>

<xopts>

Refer to common options parts description.

A specific exeception to the sysnchronous character of an CLI shell occurs, when multiple execution instaces are addressed by the arguments of current call. When the "-b off" option for background a.k.a asynchronous operations is selected, the standard synchronous foreground operation works quite well. The list of arguments is just executed sequentially as expected.

In current implementation the user is responsible for handling the appropriate values, which are assigned by default. The enforcement of resetting user defined values could be somewhat tricky due to permutation of bulk arguments, thus is shifted because of priorities. Resulting of this, the actual environment is a superposition of all previous executed target options with the global options.

ENUMERATE

Not applicable to CLI.

LIST

Almost the same output as common standard, with following changes in semantics.

id The PID of the first local call below of SSH termination point, which is the locally executed relay-instance of ctys and is the parent shell of actual running batch/interactive shell. Thus the topmost ctys-call.

pid PID of current ctys sessions top. The following values are not applicable: uuid, mac, dsp, cp, sp

-L (LOCALONLY|LO) | (DISPLAYFORWARDING|DF)

Even though a DISPLAY will actually not be used, this parameter also adopts the behavior of the execution to a providing environment, which is frequently for ctys true. So these are the only location parameters to be applied.

ctys-X11(1)

5 SEE ALSO

 $ctys(\textit{1}),\ ctys\text{-}uc\text{-}X\textit{1}\textit{1}(\textit{7}),\ ctys\text{-}plugins(\textit{1}),\ bash(\textit{1}),\ xterm(\textit{1})$

6 AUTHOR

Written and maintained by Arno-Can Uestuensoez:

 $Maintenance: \qquad < acue_sf1@sourceforge.net>$

 $\label{lower_solution} Homepage: & < http://www.UnifiedSessionsManager.org > \\ Sourceforge.net: & < http://sourceforge.net/projects/ctys > \\ \end{aligned}$

Berlios.de: http://ctys.berlios.de http://www.i4p.com

7 COPYRIGHT

Copyright (C) 2008, 2009, 2010 Ingenieurbuero Arno-Can Uestuensoez This is software and documentation from **BASE** package,

- for software see GPL3 for license conditions,
- for documents see GFDL for license conditions,

This document is created with: latex and text2tags