$\begin{array}{c} \text{ctys-}\mathbf{CLI}(1) \\ \mathbf{Command} \ \mathbf{Line} \ \mathbf{Interface} \end{array}$

May 19, 2010

Contents

1	NAME	2
2	SYNTAX	2
3	DESCRIPTION	2
4	OPTIONS	2
5	SEE ALSO	4
6	AUTHOR	4
7	COPYRIGHT	4

 $ext{ctys-CLI}(1)$ 2/4

.

1 NAME

ctys-CLI - Command Line Interface

2 SYNTAX

```
ctys -t CLI -a action[=<suboptions>] ...
ctys -T CLI -a action[=<suboptions>] ...
ctys -T ALL -a action[=<suboptions>] ...
```

3 DESCRIPTION

The CLI-plugin starts a remote shell from within a local shell. No specific default desktop functionality such as XTerm is supported, just a pure CLI access is performed. The handling of desktop windows such as XTerm or GTerm is supported by the X11-Plugin.

The execution of the interconnecting ssh-call is performed by setting the "-X" option for automatic X11-Portforwarding. Thus even though the CLI session itself is not GUI based, any X11 XClient could be started and will be displayed on the local caller's XServer by usage of the encrypted channel. A Xterm, gnome-terminal or any arbitray X11 tool could be started from within a CLI sub-option "CMD". Chained login by gateways with Overall-Display-Forwarding is supported by OpenSSH, thus by ctys too.

When executing CLI almost the same functionality as for an ordinary SSH session is supported. The main advance of using ctys instead of an ordinary ssh-call is the seamless integration. Resulting from this feature instead of an IP address the <machine-address> could be used. Thus the administration of address-to-target-mapping could be completely delegated to ctys and will be utilized by internal usage of the full scope of ctys-vhost. E.g. the **LABELS** defined within ctys could be used to open a remote shell to any "labeled" instance such as a VM or PM. Therefore internal CLI type CONSOLES only use the CLI plugin.

Another option might be the usage of UUIDs or MAC-Addresses for persistent definition of the handling of commands on frequently changing and reinstalled systems with reassigned IP-Addresses and DNS names.

The second important feature of CLI is the facility to start native remote commands as shell calls within any managed PM or VM instance. Therefore CLI is the working horse for native execution of GUI-less ctys-tasks. Similar to the call of a system command, any internal ctys library and plugins function could be called remotely by CLI sub-option "CMD".

The default shell used on the target instance is bash, which could be altered interactive by the sub-option "SHELL|S", or persistently by the variable CLI_SHELL_CMD_DEFAULT.

4 OPTIONS

```
-a action[=<suboptions>] CANCEL Not applicable.
```

 $ext{ctys-CLI}(1)$

CREATE

```
CREATE=[<machine-address>]
  [REUSE|CONNECT|RECONNECT|RESUME]
  [CONSOLE:<>]
  [(CALLOPTS|C):<callopts>]
  [CD:<working-directory>][,]
  [(XOPTS|X):<xopts>]
  [(SHELL|S):<shell>]
  [(CMD):<cmd>]
```

<machine-address>

See standard for syntax. Due to the limited attribute set of a completely dynamic CLI session without own persistent resources only the LABEL is applicable. The hosting OS has to be handled by it's own plugin. The LABEL sub-option is here mandatory.

<callopts>

Refer to common options description.

CD: < working-directory>

Change current working directory for the started command. This provides for example the preconfiguration of specific work-sets, where each terminal could be opened for a specific directory.

CMD:<cmd>

Refer to common options CMD description.

Not yet supported.

< xopts>

Refer to common options xopts description.

Not applicable.

```
(SHELL|S):<shell>
```

Refer to common options description.

A specific exception to the synchronous character of a CLI shell occurs, when multiple execution instances are addressed by the arguments of current call. When the "-b off" option for background a.k.a asynchronous operations is selected, the standard synchronous foreground operation works quite well. The list of arguments is just executed sequentially as expected. The CLI CREATE action sets implicitly the forced usage of a pseudotty. This is the same as using "-z pty,pty".

ENUMERATE

Not applicable.

LIST

Almost the same output as common standard, with following changes in semantics.

id The PID of the local SSH termination point, which is the locally executed relay-instance of ctys and is the parent shell of actual running batch/interactive shell. The CLI plugin does not support a cancel or connect|reconnect|reuse action, so the "id" is here a non-functional hint only.

pid PID of current ctys sessions top.

The following values are not applicable: uuid, mac, dsp, cp, sp

-L (LOCALONLY|LO) | (DISPLAYFORWARDING|DF)

Even though a DISPLAY will actually not be used, this parameter also adopts the behavior of the execution to a providing environment, which is frequently for ctys true.

These are the only location parameters to be applied.

 $ext{ctys-CLI}(1)$

5 SEE ALSO

ctys(1), ctys-uc-CLI(7)

6 AUTHOR

Written and maintained by Arno-Can Uestuensoez:

Maintenance: <acue sf1@sourceforge.net>

Homepage: http://www.UnifiedSessionsManager.org http://sourceforge.net/projects/ctys

Berlios.de: http://ctys.berlios.de http://www.i4p.com

7 COPYRIGHT

Copyright (C) 2008, 2009, 2010 Ingenieurbuero Arno-Can Uestuensoez This is software and documentation from **BASE** package,

- $\bullet\,$ for software see GPL3 for license conditions,
- for documents see GFDL for license conditions,

This document is created with: latex and text2tags