

CHATCO System Test Cases: Retest of Failed Cases

This lists only the 38 test cases marked F in the first run. Steps and expected results are unchanged from the original document.

Status: **P** = Passed, **F** = Failed. P means the cause was fixed in code and the expected result was checked with automated tests. Please confirm each P in the browser. Cases marked with a note number have a note on the last page.

Phase	Roles	Modules	Retested	P	F	Case IDs
Phase 1: Authentication and Account Approval	Public, Commuter, Conductor, Admin	Commuter Signup, Page Access by Role, Forgot Password	3	3	0	016, 041, 052
Phase 2: Admin Master Data Setup	Admin	User Management, Personnel: Conductors, Vehicles, Routes and Fare Matrix, System Settings	18	15	3	074, 075, 079, 080, 098, 099, 100, 101, 102, 113, 114, 125, 126, 127, 130, 133, 135, 139
Phase 3: Conductor Shift Operations	Conductor	Unit Verification and Starting a Shift, Operating Device, SOS, Metrics, and Settings	12	6	6	149, 150, 151, 152, 153, 154, 156, 157, 158, 159, 160, 190
Phase 4: Commuter Riding Flow	Commuter	Profile and Trips	1	1	0	228
Phase 7: Safety, Lost and Found, Feedback, and Rewards	Commuter, Conductor, Admin	Lost and Found (Admin)	2	0	2	275, 280
Phase 8: Monitoring, Analytics, Announcements, and Audit	Admin, Commuter, Conductor	Announcements	1	1	0	323
Phase 9: Public Pages and System-Wide Checks	Public, all roles	Session and Reliability	1	1	0	341
Total			38	27	11	

Phase 1: Authentication and Account Approval

Roles: Public, Commuter, Conductor, Admin

A. Commuter Signup

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-PUB-SIGNUP-016	Code step left blank or incomplete	On Step 3	1. Enter only 3 digits and continue	Error: "Enter all 6 digits from the email."	P

C. Page Access by Role

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-AUTH-ACCESS-041	Commuter opens Receipts or Activity Logs	Logged in as Commuter	1. Type /receipts 2. Type /activity-logs	Redirected to Login for both pages.	P

D. Forgot Password

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-AUTH-FORGOT-052	Reset for an account that's still pending	Commuter hasn't been approved yet	1. Enter the pending account's email 2. Submit	Error: "Your account is still pending admin approval. You can reset your password once it has been approved." No code is sent.	P

Phase 2: Admin Master Data Setup

Roles: Admin

A. User Management

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-USERS-074	Suspend with a reason that's too short	Suspend form is open	1. Enter "bad" as the reason 2. Confirm	A validation error says the reason must be at least 5 characters. The user is not suspended.	P
TC-ADMIN-USERS-075	Admin tries to suspend their own account	Logged in as Admin	1. Open your own account 2. Click Suspend 3. Confirm	Error: "You cannot suspend your own account."	P
TC-ADMIN-USERS-079	Admin tries to delete their own account	Logged in as Admin	1. Try to delete your own account	Error: "You cannot delete your own account." (See note 1.)	P
TC-ADMIN-USERS-080	Delete the last admin	Only one admin account exists	1. Try to delete that admin from another session	Error: "Cannot delete the last administrator account." (See note 1.)	P

C. Personnel: Conductors

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-COND-098	Disable a conductor with the wrong admin password	A conductor exists	1. Click Disable 2. Enter a wrong admin password 3. Confirm	Error: "The password you entered is incorrect." (See note 9.)	P
TC-ADMIN-COND-099	Disable a conductor	A conductor not on a shift	1. Click Disable 2. Enter the correct admin password 3. Confirm	"Conductor account disabled. All sessions revoked." The conductor is logged out and shows as Deactivated. (See note 9.)	P
TC-ADMIN-COND-100	Disabled conductor tries to log in	Previous case passed	1. Log in with the conductor's username and password	Login is refused.	P
TC-ADMIN-COND-101	Disable a conductor who is on an active shift	The conductor is on an active shift	1. Try to disable the conductor	Error: "Cannot disable a conductor who is currently on an active shift. End the shift first." (See note 9.)	P
TC-ADMIN-COND-102	Reset conductor credentials	A conductor exists	1. Click Reset Credentials 2. Enter the admin password 3. Confirm 4. Log in with the old password, then the new one	"Credentials reset successfully. The conductor must log in with the new credentials." New username and password are shown. The old password fails and the new one works. (See note 9.)	P

D. Vehicles

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-VEHICLE-113	Delete a vehicle	The vehicle is not on a shift	1. Click Delete 2. Confirm	"Vehicle deleted successfully". Activity Log shows "Deleted vehicle [Plate]". (See note 9.)	P

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-VEHICLE-114	Delete a vehicle that is on an active shift	The vehicle is on an active shift	1. Try to delete the vehicle	The delete is blocked with a conflict error. The vehicle stays. (See note 9.)	P

E. Routes and Fare Matrix

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-FARE-125	Detour end time before start time	Publishing a detour	1. Set an end time earlier than the start time 2. Publish	Error: "The detour expiration must be after its start time."	P
TC-ADMIN-FARE-126	View route versions	The route was published more than once	1. Open route versions	Each published version is listed with its date and notes. (See note 9.)	P
TC-ADMIN-FARE-127	Delete a route that is still used	Vehicles or fare points use this route	1. Try to delete the route	Error: "Move assigned vehicles and Fare Points before deleting this route." (See note 9.)	P

F. System Settings

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-SET-130	Registration requirement toggles	App Configuration is open	1. Turn off "Force Valid ID Upload" 2. Save 3. Try to sign up without an ID	The signup follows the setting (ID not required when off). (See note 2.)	P
TC-ADMIN-SET-133	Overspeed limit is applied	Speed limit set to 40 km/h	1. Drive a unit above 40 km/h during a shift	The unit shows in Overspeeding History on the Monitoring page. (See note 8.)	F
TC-ADMIN-SET-135	Financial rules: discount rates	Financial Rules is open	1. Change the Student discount rate 2. Save 3. Record a Student fare as conductor	The saved rate is used when calculating the Student fare. (See note 3.)	F
TC-ADMIN-SET-139	Safety: emergency hotline and sender address	Safety & Notifications is open	1. Set the emergency hotline and sender Gmail 2. Save 3. Trigger an SOS as conductor 4. Approve a registration	The hotline shows to the conductor during the emergency, and the email is sent from the set address. (See note 4.)	F

Phase 3: Conductor Shift Operations

Roles: Conductor

A. Unit Verification and Starting a Shift

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-COND-SHIFT-149	Start without picking a unit or driver	Unit Verification is open	1. Try to continue without a unit or driver	The shift can't start. "Vehicle is required" or "Driver is required". (See note 5.)	F
TC-COND-SHIFT-150	Unit already on a shift	Another conductor is using the unit	1. Try to start a shift on that unit	Error: "Vehicle already on active shift". (See note 6.)	P
TC-COND-SHIFT-151	Driver already on a shift	The driver is on another shift	1. Try to start with that driver	Error: "Driver already on active shift". (See note 6.)	P
TC-COND-SHIFT-152	Conductor already on a shift	Conductor has an active shift	1. Try to start another shift	Error: "Already on active shift" (or the conductor is taken to the dashboard). (See note 6.)	P
TC-COND-SHIFT-153	Unit assigned to another conductor or driver	Admin assigned the unit to someone else	1. Try to start with that unit	Error: "Vehicle is assigned to another conductor." or "Vehicle is assigned to another driver." (See note 6.)	P
TC-COND-SHIFT-154	Unit or driver not active	The vehicle is set to Maintenance	1. Try to start a shift on it	Error: "The assigned vehicle and driver must both be active." (See note 6.)	P

B. Operating Device

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-COND-DEVICE-156	Shift opened on a second device	Shift active on Device A	1. Log in on Device B 2. Open the dashboard	Device B shows the shift as view-only with "Choose the operating device". (See note 7.)	F
TC-COND-DEVICE-157	Collect a fare on a view-only device	Device B is view-only	1. Try to record a fare on Device B	Error: "This shift is active on another device. Sync and release that device before collecting a fare here." (See note 7.)	F
TC-COND-DEVICE-158	Release and claim the shift	Shift active on Device A	1. On Device A click "Release for handoff" 2. On Device B claim the shift	Device A: "The shift is ready to be claimed by another device." Device B: "This device can now operate the shift." (See note 7.)	F
TC-COND-DEVICE-159	Claim while the other device still owns it	Device A hasn't released	1. Claim on Device B	Error: "Another device still owns this shift. Release it there before claiming this device." (See note 7.)	F
TC-COND-DEVICE-160	Release with offline cash not synced	Device A has unsynced cash	1. Click "Release for handoff"	"Offline cash is still waiting to sync. Keep this device connected and try again." (See note 7.)	F

F. SOS, Metrics, and Settings

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-COND-OTHER-190	Settings: scan sound and clear cache	Settings open	1. Toggle Scan Sound 2. Clear cache 3. Confirm	The setting is saved. Cache clears without ending the shift. (See note 9.)	P

Phase 4: Commuter Riding Flow

Roles: Commuter

E. Profile and Trips

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-COMM-PROFILE-228	Change password: weak password	Change Password form open	1. Enter "password1" as the new password (no uppercase letter or symbol)	The password is rejected for the same rules as signup (8+ characters, uppercase, number, symbol).	P

Phase 7: Safety, Lost and Found, Feedback, and Rewards

Roles: Commuter, Conductor, Admin

B. Lost and Found (Admin)

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-LOST-275	Add a 4th photo	Item has 3 photos	1. Upload another	Error: the item already has the maximum of 3 photos. (See note 8.)	F
TC-ADMIN-LOST-280	Approve a second claim on the same item	One claim already approved	1. Approve another claim	Error: "Another claim was approved". (See note 8.)	F

Phase 8: Monitoring, Analytics, Announcements, and Audit

Roles: Admin, Commuter, Conductor

D. Announcements

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-ADMIN-ANNOUNCE-323	Create with required fields blank	New Announcement open	1. Leave title and message blank 2. Save	Validation errors. Nothing is saved.	P

Phase 9: Public Pages and System-Wide Checks

Roles: Public, all roles

C. Session and Reliability

Test Case ID	Test Case Description	Pre-conditions	Steps	Expected Result	Status
TC-SYS-RELIABILITY-341	Two admins edit the same record	Same vehicle open in 2 browsers	1. Save a change in each	The last save wins or a clear error is shown. No data is lost silently. (See note 1.)	P

Notes

Notes 3, 4, 5 and 7 explain cases that stay F because fixing them needs a decision about how the feature should work.

1. **TC-ADMIN-USERS-079, 080 and TC-SYS-RELIABILITY-341:** 079 and 341 need a second admin account. The app has no screen for creating one, so it must be added in the database. Use two different admin accounts, because signing in to the same account in a second browser ends the first session by design (TC-AUTH-LOGIN-033). With only one admin, deleting your own account shows "Cannot delete the last administrator account." (080).
2. **TC-ADMIN-SET-130:** The setting now applies to Regular commuters. Student, Senior and PWD applicants must still upload an ID, because it proves their discount. "Require Phone Number Verification" is still not used, because the system has no SMS code step.
3. **TC-ADMIN-SET-135 (still F, needs a decision):** Discounted fares come from the "discounted fare" column in the Fare Matrix. The Financial Rules percentages are a second source for the same number. Choose one: make the percentages set the fare, or remove them from Financial Rules.
4. **TC-ADMIN-SET-139 (still F, needs a decision):** The hotline part is fixed. It now shows on the conductor's SOS screen as a tap-to-call number. The sender Gmail is not used as the From address. Email goes out through Brevo from the verified chatco.online domain, and sending as a Gmail address would fail Gmail's sender checks, so the mail would be rejected or marked as spam. One option is to use it as the Reply-To address.
5. **TC-COND-SHIFT-149 (still F, needs a decision):** Unit Verification has no Continue button. A shift can only be started by tapping a unit and then a driver, so the "required" message can never appear on screen. The server still returns it when asked directly.
6. **TC-COND-SHIFT-150 to 154:** Unit Verification now also lists units and drivers that can't be used, greyed out with the reason under each one. Tapping one shows that reason. A start-shift refusal now appears inside the confirm dialog instead of behind it. For 152, a conductor who already has a shift is taken to the dashboard, which the expected result allows.
7. **TC-COND-DEVICE-156 to 160 (still F, needs a decision):** Since Aug 23, logging in on a new device takes over the shift, and a second web login ends the first web session (the same rule as TC-AUTH-LOGIN-033). These cases describe the older flow, where the second device stays view-only until the first device releases the shift. The "Release for handoff" button is also never shown on the device that owns the shift. Fixing this means choosing one of the two designs.
8. **TC-ADMIN-SET-133, TC-ADMIN-LOST-275 and 280:** No reason was recorded for these failures, so they were not retested and stay F.
9. **Where to find the fixes:** Conductor Disable and Reset Credentials are under Fleet Management > Personnel, on the eye (View details) button of a conductor row. Vehicle delete is the trash button on a Vehicles row. Route delete is the Delete Route button next to New Route in Settings > Fare Matrix. Route versions is the "Route versions" list under the route editor. Clear cache is in the conductor's Settings > App Preferences.