

# Mint time & transfer count

A shared hook that records when each token was minted, how many times it has changed hands, and makes those values available to your script every time the artwork is shown. Set it up in Creator Dashboard v2 before you mint.

## What your script receives

| NAME                          | WHAT IT IS                                    | NOTES                                                                            |
|-------------------------------|-----------------------------------------------|----------------------------------------------------------------------------------|
| <code>mintTimestamp</code>    | Mint time, in unix seconds                    | Fixed for the life of the token                                                  |
| <code>secondsSinceMint</code> | Seconds that have passed since mint           | Live — a later view returns a larger number                                      |
| <code>transferCount</code>    | Times the token has changed owners after mint | Starts at 0. The mint itself is not counted. Sending to yourself is not counted. |

Transfers can also trigger a re-render, so marketplace stills can update after a sale.

## Before you start

- The project must be on a **v3.3 or later** Engine or Studio (Flex) contract. Older contracts have no Transfer hook field.
- Do this in **Creator Dashboard v2**, on Mainnet or Staging.
- Finish all four steps **before the first mint** you care about. Tokens minted earlier will not have a mint time, and counting only starts from the next transfer.

## The address to paste

Same hook on Ethereum, Arbitrum, Base, Shape, and Staging. It is not yet in the dashboard's hook dropdown — always choose **Custom address...** and paste this.

```
SHARED HOOK · MAINNET & STAGING
0x000000002099d6BB23Ebd24aDCbee931ad461a39
```

## Step by step in Creator Dashboard v2

PostParam hooks only appear after PostParams are enabled, so do the Scripts tab first. Each Save / Submit writes on-chain — you will sign a transaction.

### 1. Enable PostParams

Open the project → **Scripts** tab → section **PostParams**.

- If you see **Enable PostParams**, click it and sign. This adds the PostParams contract to the project.
- If parameters are already listed, skip this.

### 2. Add the `transferCount` parameter

Still on **Scripts** → **PostParams**, click **Add parameter**. In the **Add PostParam** dialog:

| FIELD          | SET TO                                                 |
|----------------|--------------------------------------------------------|
| Parameter name | <code>transferCount</code> — exact spelling, no spaces |
| Parameter type | <b>Number</b>                                          |

| FIELD                          | SET TO                                                                                                                     |
|--------------------------------|----------------------------------------------------------------------------------------------------------------------------|
| Min range                      | 0                                                                                                                          |
| Max range                      | A very large number, e.g. 1000000000 . Do not use a small cap.                                                             |
| Who can change this parameter? | Select <b>only Contract address</b> . Turn off Artist and Token owner if they are selected (Token owner is on by default). |
| Contract address               | Paste the hook address above                                                                                               |
| Lock parameter                 | Leave empty. If you lock this, later transfers will stop updating the count.                                               |

Click **Save parameter**, then **Submit all** and sign. You can keep any other PostParams you already have.

Do not add parameters named `mintTimestamp` or `secondsSinceMint`. Those are injected automatically when the artwork is read.

### 3. Assign the read augmentation hook

On **Scripts** → **PostParam hooks** (this section appears after PostParams are enabled):

- **Read augmentation hook** — choose **Custom address...**, then paste the hook address. Do not pick one of the listed Inject... hooks.
- **Post-config hook** — leave **None — no hook**. Do not put this hook here.

Click **Save** and sign. Both hook fields are written in one transaction.

### 4. Assign the transfer hook

Open **Advanced** → section **Project** → field **Transfer hook**.

- Paste the same hook address. Click **Save** and sign.
- Do not click **Lock transfer hook** unless you want the choice to be permanent.

You can also jump here from the command bar by searching “Transfer hook”.

## Reading the values in your script

Same pattern the dashboard shows under **Accessing PostParams data**. Values are strings. The dependency index is usually 0, but can differ if the project has other on-chain assets.

```
const postParams = tokenData?.externalAssetDependencies?.[0];

const mintTimestamp = Number(postParams?.data?.['mintTimestamp']);
const secondsSinceMint = Number(postParams?.data?.['secondsSinceMint']);
const transferCount = Number(postParams?.data?.['transferCount']);
```

If `mintTimestamp` is 0, the transfer hook was not on at mint.

### Quick check before mint

- PostParams enabled, with a `transferCount` Number param writable only by the hook
- Read augmentation hook = the shared address · Post-config hook = none
- Transfer hook = the shared address, not locked unless you intend that
- No extra params named `mintTimestamp` or `secondsSinceMint`