Floating-point arithmetic and error analysis (AFAE)

Introduction to computer arithmetic

Stef Graillat

LIP6/PEQUAN - Sorbonne University

Lecture Master 2 SFPN - MAIN5





1 / 93

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- Use of Computer Arithmetic: Historical Failures
- 6 Conclusion

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- Use of Computer Arithmetic: Historical Failures
- 6 Conclusion


Computer arithmetic

- Computer Arithmetic is about
 - how to represent Numbers in a Computer
 - Implementation of basic operations like $+, -, \times, /$
 - with nothing but bare transistors
 - with other high-level operations in software
 - Approximation and Error Analysis
 - Floating-Point arithmetic
 - Compute less precisely to go faster
 - Base Algorithms for computation-intensive problems
 - Cryptography
 - Scientific Computing
- Computer Arithmetic is not about but very close to
 - Computing with Formulas ⇒ Computer Algebra
 - Modelization and Problem Solving ⇒ Numerical Analysis

Bibliography







AFAE Master 2 course - organization

Planning for the AFAE Course

| Date | Subject | Organization | MAIN5 | Teacher | | |
|----------|--|-----------------------------------|--------------|---|--|--|
| 06/10/20 | Introduction to computer arithmetic | lect + tuto ✓ tuto ✓ lect + lab ✓ | | S. Graillat V. Ménissier-Morain S. Graillat | | |
| 13/10/20 | Introduction to computer arithmetic (cont'd) | | | | | |
| 20/10/20 | Increasing the accuracy, examples with polynomials | | | | | |
| 27/10/20 | Large scale rounding error analysis, conditioning | lect + tuto | ✓ | S. Graillat | | |
| 03/11/20 | Multiprecision and Interval Arithmetic | lect + lab | \checkmark | S. Graillat | | |
| 17/11/20 | Stochastic Arithmetic | lect + lab | ✓ | F. Jézéquel | | |
| 24/11/20 | Validation of linear systems | lect | \checkmark | S. Graillat | | |
| 08/12/20 | Fixed-Point Arithmetic | lect + tuto | | Th. Hilaire | | |
| 15/12/20 | Elementary Functions | lect | | S. Graillat | | |
| 05/01/21 | Faithfully rounded algorithms | lect | | S. Graillat | | |
| 12/01/21 | Probabilistic rounding error analysis | lect + tuto | | Th. Mary | | |
| 19/01/21 | Arbitrary precision arithmetic | tuto + lab | | M. Mezzarobba | | |
| 26/01/21 | Scientific Articles (Group 1) | talks | | You! | | |
| 02/02/21 | /21 Scientific Articles (Group 2) talks | | | You! | | |

• URL: https://www-pequan.lip6.fr/~graillat/teach/afae/

Login: afae2020 - Password: 2020AFAE

AFAE Master 2 Course - evaluation (SFPN)

Evaluation. SFPN

- 40% of the grade for your abstract and presentation
 - Jan. 26th and Feb. 2nd
 - Approx. 20 min presentation of a scientific article
 - Approx. 15 min of questions on the article and the course
 - Article list will be given Nov. 24th, 2020
 - 2 page abstract to be written by Jan. 19th, 2021.
 - Presentation skills are really important!
- 30% of the grade for the final exam,
 - In Feb. 2021
 - Several exercises covering all parts of the course
- 30% of the grade for pratical work
 - Tutorial on 20/10/20, 03/11/20, 24/11/20 will be graded
 - All functions to be programmed out, tested and tuned

AFAE Master 2 Course - evaluation (MAIN)

Evaluation. MAIN

- 50% of the grade for pratical work
 - Tutorial on 20/10/20, 03/11/20, 24/11/20 will be graded
 - All functions to be programmed out, tested and tuned
- 50% of the grade for the final exam,
 - Same examination sheet as for the SFPN people
 - The MAIN people do not give answers for certain exercises.
 - The grading scheme is different for MAIN and SFPN.

Do you speak english?

- This is a research-oriented Master 2 Course
- The scientific language is English
 - Most of the slide-sets will be in English
 - The scientific articles you will present, too
- The Course will be read in French
 - Ask questions for what you don't understand on the slides
 - Start a small specialized vocabulary list right away
 - the carry la retenue
 - the radix la base
 - ..

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- Use of Computer Arithmetic: Historical Failures
- Conclusion

Early number representations

- Neolithic: invention of the unary representation of integers
- Antiquity; invention of

alphabetic systems (Rome, Egypt, Greece, China)



position systems (Babylonia, India, Mayan)



Position systems

Our decimal system is an example of a position system:

- The position i of a digit gives its weight 10i
- Example: $789 = 7 \cdot 10^2 + 8 \cdot 10^1 + 9 \cdot 10^0$
- With 3 decimal digits we represent from 000 to 999 = 10³ - 1
- In general, using n digits,
 we can represent integers in [0..10ⁿ 1]

First advantage of position systems

With 10 symbols only, we can represent arbitrarily large numbers...

Position system in radix β

- For any β integer \geq 2,
- If we have β symbols (which is called β -ary digits)
- with n such digits, we represent the interval

$$[0..\beta^{\text{n}}-1]$$

- $\bullet \ d_{n-1}d_{n-2}...d_1d_0$ represents $\sum\limits_{i=0}^{n-1}d_i\beta^i$
- Example: $789 = 7 \cdot 10^2 + 8 \cdot 10^1 + 9 \cdot 10^0$
- ullet eta^i is the weight of digit d_i .

Babylonian system is a position system in base 60.

Why 60? And why does our hour have 60 minutes?

More on the Babylonian system

- Radix 60 needs to represent 60 different digits... 60 symbols?
- Babylonians represented digits using an alphabetic system with two symbols only:
 ∫ for 1, and
 ∫ for 10



YBC7289 from http://www.math.ubc.ca/~cass/euclid/ybc/ybc.html

Babylonian digits

| 7 1 | ∢7 11 | ∜7 21 | (((7) 31 | ₹7 41 | 44.7 51 |
|--------------|----------------|-----------------|--------------------|------------------|---|
| 77 2 | 177 12 | 4(77 22 | (((7)7 32 | 42 77 42 | 12 77 52 |
| YYY 3 | 1777 13 | (1777 23 | ((())) 33 | 44 999 43 | 11/17/17 53 |
| 7 4 | √177 14 | (177 24 | ((() 34 | 14 1 44 | 11 54 |
| 777 5 | √∰ 15 | ₩ 25 | (((XXX) 35 | ₹ ₩ 45 | 12 5 5 5 |
| 6 | ∜₩ 16 | 4 🐺 26 | ₩₩ 36 | ₹ ₩ 46 | **** 56 |
| 7 | 17 | () 27 | ## 37 | ₹ 47 | ********************************* 57 |
| 8 | 18 | () 28 | ₩₩ 38 | 48 | 12 58 |
| 77 9 | 19 | 4 29 | **** 39 | 49 | *** 59 |
| (10 | 44 20 | ₩ 30 | 40 | 14 50 | |

Taken from http://en.wikipedia.org/wiki/Babylonian_numerals


Taking into account the limitations of the technology



- Our brain is able to distinguish in a glance 3 pebbles from 4, but not 7 pebbles from 8...
- On the other hand, it is good at recognizing shapes
- For this reason, Babylonians fixed the shape of the digits







Taking into account the limitations of the technol-ogy



Digital electronic technology is based on 2-value (Boolean) logic.

Positive integers in the binary position system

- Radix $\beta = 2$
- Two digits 0 and 1
- Bit for "binary digit"
- With n bits we may represent numbers in $[0..2^n 1]$

Fancy radix β representations

- So far our digit set was $\{0, \beta 1\}$
- But any digit set including zero is OK.

The Setun ternary computer

- Built in 1958 by Moscow State University
- Radix 3, digit set {-1, 0, 1} instead of {0, 1, 2}
- example: 1111 = 27 + 9 + 3 + 1 = 40
- example: $\overline{1111} = -27 9 3 1 = -40$
- n such trits provide $[-(3^n 1)/2...(3^n 1)/2]$
- As many integers (3ⁿ) as with the standard digit set

| 111 | 0001 | 0000 | 0001 | 0011 | 0010 | 0011 | ••• | 1111 |
|-----|----------|------|------|------|------|------|-----|------|
| -40 | -1 | 0 | 1 | 2 | 3 | 4 | ••• | 40 |

Other nice properties (rounding by truncation) but... so far, electronics are binary (+5V vs. OV).

To probe further on fancy radix β representations

- So far our digit set was n digits including zero.
- ullet We may use more than eta digits...
- The system then becomes redundant
 - more than one way to represent some numbers
 - example: radix 10, digits $\overline{7}$, $\overline{6}$...0, 1, ...7, $17 = 2\overline{3}$

Studied by Cauchy (1840) for digits -5...5, then Algirdas A. Avižienis in the 1960s.

If the FP unit in your cellphone includes a division unit, it probably uses Avižienis' ideas.

Stacking several number representations

A very general technique:

- Alphabetic systems is built on top of the unary representation
- Babylonian is a position system with digits represented in an alphabetic system
- Same for Chinese abacus
- Your calculators use a decimal representation where each digit is represented in binary
- GMP multiple-precision library uses a radix-2³² system where each digit is a 32-bit integer represented in radix 2
- ...

use at each level the representation that is adequate to this level

What is a good number representation system?

It is a system that

- is well matched to the technology available
- enables "good" representation of numbers
- even more important, enables "good" algorithms for the arithmetic operations

Try to design the multiplication algorithm for Roman numerals...

Very few basic techniques of number representations


- but many parameters each
- and they can be stacked on top of each other

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- Use of Computer Arithmetic: Historical Failures
- 6 Conclusion

Back to the history

- Neolithic: invention of a non-volatile memory able to store positive integers represented in unary.
- Addition in unary: pour one bag into the other.
- Far antiquity: invention of the pocket calculator in China or in Babylonia
 - still essentially a memory device
 - The real invention is the position system!



Position systems are great for addition

$$\begin{array}{rcl} \textbf{X} + \textbf{Y} & = & \sum\limits_{i=0}^{n-1} \textbf{x}_i \beta^i & + & \sum\limits_{i=0}^{n-1} \textbf{y}_i \beta^i \\ \\ & = & \sum\limits_{i=0}^{n-1} (\textbf{x}_i + \textbf{y}_i) \beta^i \end{array}$$

Problem: $x_i + y_i$ sometimes won't be a digit (e.g. 9+9=18)

carry propagation

- ullet Remove eta from the digit sum
- Add 1 to the digit sum to the left

A bit of mathematical obfuscation

Let TA be the radix β addition table:


TA:
$$\{0,1\} \times \{0..\beta-1\} \times \{0..\beta-1\}$$
 \rightarrow $\{0..1\} \times \{0..\beta-1\}$
$$TA(c,x,y) = (c',s)$$
 such that $\beta c'+s = c+x+y$

- c is an input carry. Assume its value is 0 or 1.
- x and y are two radix-β digits
- Their sum is between 0 and $2\beta-1$. Therefore it can be written in radix β as two digits c's.
- The higher weight digit is called the output carry, and its value is 0 or 1 whatever the radix.

Integer addition algorithm

X and Y two numbers written in radix β on n digits:

- 1: $c_0 = 0$
- 2: **for** i = 0 to n 1 **do**
- 3: $(c_{i+1}, s_i) = TA(c_i, x_i, y_i)$
- 4: end for




GMP addition is exactly this loop, using as TA the adc processor instruction.

The early mechanical computer







- Obviously radix 10
- Digit addition by unary addition of beads
- Carry propagation performed by the hands of the operator

DaVinci / Schickard / Pascal machines

- 1500: Leonardo Da Vinci draws (without building it) a calculating machine
- 1623: Wilhelm Schickard reports building one
- 1645: Blaise Pascal builds 50 Pascaline (sells 15)




1679: Leibniz improves it to perform multiplication and division




DIY version in overhead foils


- rotating wheels perform modulo 10 addition
- carry propagation from one wheel to the next

La machine de Leibniz/Pascal/Schickard/da Vinci/...






The TA function in Pascal's machine






And it even works in binary

TA is now called Full Adder:




(the three inputs now have interchangeable roles)



This cheap binary adder is called ripple carry adder.

Finally getting close to a real computer

A Full Adder cell typically costs 16 transistors.



From Pascal (1645) to Leibniz (1679)


Multiplication is just iterated additions:



Cost of addition and multiplication

Think of what you do by hand: in terms of digit-level operations,

- addition is linear in the number of digits
- multiplication is quadratic in the number of digits.




Multiplication can be reduced to subquadratic asymptotic cost (Karatsuba-Ofman, FFT), but it is practical for very large n only.


So a 100-digit multiplication is very expensive.

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- 5 Use of Computer Arithmetic: Historical Failures
- 6 Conclusion


Bibliography








Bibliography





What every computer scientist should know about floating-point arithmetic. David Goldberg. ACM Computing Surveys, 23(1):5-48, 1991.

A famous failure: Patriot missile

 1/10 is not representable by a finite number of digits in base 2

1/10 = 0.0001100110011001100110011001100...

• On a 24 bit fixed-point register error = $1.1001100... \times 2^{-24} \approx 0.000000095$ in decimal



- First Gulf War in 1991: an american Patriot missile battery failed to intercept an Iraqi Scud missile. The Scud killed 28 soldiers.
- After 100 hours, the error is about 0.34 s: a Scud travels at about 1500 m/s, it makes 500 m

Can we count up to 6 with a computer?

$$\begin{array}{lll} 2-1 & & & & & & \\ & \frac{1}{\cos(100\pi+\pi/4)} \\ 3 & \frac{\tan(\arctan(10000))}{10000} & & & & & \\ & \left(\left(\cdots \left(\sqrt{\sqrt{\cdots \sqrt{4}}} \right)^2 \cdots \right)^2 \right)^2 & & & & \\ & \left(\left(1+e^{-100} \right) - 1 \right) \\ 5 \times \left\{ \frac{(1+e^{-100})-1)}{(1+e^{-100})-1)} \right\} & & & & \\ & & & \\ & \frac{\log(e^{6000})}{1000} & & & & \\ & & & \\ \hline \end{array} \right.$$

Increase the precision?

Rump's polynomial:

$$f(x,y) = 333.75y^6 + x^2(11x^2y^2 - y^6 - 121y^4 - 2) + 5.5y^8 + \frac{x}{2y}$$

On a IBM 370, for x = 77617 and y = 33096, computation of f(x, y) gives:

| precision | computed value |
|-----------|-------------------|
| single | 1.172603 |
| double | 1.1726039400531 |
| extended | 1.172603940053178 |

But exact value is -0.827396059946821368141 · · ·

Reproducibility

Floating-point arithmetic: operations suffer from rounding errors.

Floating-point operations $(+,\times)$ are commutative but not associative:

$$(-1+1)+2^{-53} \neq -1+(1+2^{-53})$$
 in double precision.

Consequence: results of floating-point computations depend on the order of computation.

Reproducibility: ability to obtain bit-wise identical results from run-to-run on the same input data, with different resources.

Motivations for reproducibility

Demands for reproducible floating-point computations:

- Debugging: look inside the code step-by-step, and might need to rerun multiple times on the same input data.
- Understanding the reliability of output.
- Contractual reasons (for security, ...).
- ...

Sources of non-reproducibility

A performance-optimized floating-point library is prone to non-reproducibility for various reasons:

- Changing Data Layouts:
 - Data
 - Data partitioning,
 - Data ordering,
- Changing Hardware Resources:
 - Fused Multiply-Adder support,
 - Intermediate precision (64 bits, 80 bits, 128 bits, etc),
 - Data path (SSE, AVX, GPU warp, etc),
 - Cache line size,
 - Number of processors,
 - Network topology,
 - ...

Compiler options

```
#include <stdio.h>
                           > gcc -03 -o repro repro.c
int main(){
                           > ./repro
                          Correct
volatile double a.b:
double x,y;
a=1.0/3;
b=0.1/2048:
                           > gcc -03 -ffast-math -o repro repro.c
x = a + b;
y = (a \square (a + b)) + b;
                          > ./repro
                           Error
if (y==0.0){
  printf("Error\n");
else {
  printf("Correct\n");
  return 0:
```

Representation

A floating-point number x is represented in base B by:

- its sign s_x (0 for x positive, 1 for x negative)
- its mantissa (significand) m_x of n+1 digits
- \bullet its exponent e_x , an integer of k digits between e_{min} and e_{max}

such that

$$\mathbf{x} = (-1)^{s_x} \times m_x \times B^{e_x}$$

with $m_x = x_0, x_1, x_2, \dots, x_n$ where $x_i \in \{0, 1, \dots, B-1\}$.

To obtain the best possible accuracy with a fixed-length mantissa n, the mantissa is normalized, that is to say, $x_0 \neq 0$, $m_x \in [1, B[$.

A special code is necessary for 0.

Before 1985

The result of an operation may differ depending on the language, the compiler and the computer architecture.

| computer | В | n | e _{min} | e _{max} |
|--------------|----|----|------------------|------------------|
| Cray 1 | 2 | 48 | -8192 | 8191 |
| | 2 | 96 | -8192 | 8191 |
| DEC VAX | 2 | 53 | -1023 | 1023 |
| | 2 | 56 | -127 | 127 |
| HP 28 et 48G | 10 | 12 | -499 | 499 |
| | 16 | 6 | -64 | 63 |
| IBM 3090 | 16 | 14 | -64 | 63 |
| | 16 | 28 | -64 | 63 |

Impossible to write portable numerical code.

Revolution in 1985: IEEE-754 standard

A standard defines the representation of data and the behavior of basic operations in in floating-point arithmetic This standard defines:

- formats for data
- special values
- rounding modes
- accuracy of basic operations
- rules for conversion
- 754 ANSI/IEEE Standard for Binary Floating-Point Arithmetic in 1985
- 854 ANSI/IEEE Standard for Radix-Independent Floating-Point Arithmetic in 1987 (where B=2 or 10)

IEEE 754-2008, ANSI/IEEE Standard for Binary Floating-Point Arithmetic in 2008

Advantages of IEEE-754 standard

- make possible to write portable programs
- make programs deterministic from one computer to another
- keep mathematical properties
- perform correctly rounded operations
- perform reliable conversions
- facilitate the construction of mathematical proof
- facilitate the use of exceptions
- facilitate comparisons between numbers
- support directed roundings useful for interval arithmetic

IEEE-754 standard: formats

B = 2

| format | | number of bits | | | | | |
|------------------|-------|--------------------------|------------------------------|----|--|--|--|
| | total | total sign significand e | | | | | |
| single precision | | | | | | | |
| binary32 | 32 | 1 | (1 implicit +) 23 (fraction) | 8 | | | |
| double precision | | | | , | | | |
| binary64 | 64 | 1 | (1 implicit +) 52 (fraction) | 11 | | | |

The significand (normalized) m_x of x is represented by n+1 bits :

$$\mathsf{m}_{\mathsf{x}}=1.\underbrace{\mathsf{X}_1\;\mathsf{X}_2\;\mathsf{X}_3\;\ldots\;\mathsf{X}_{n-1}\;\mathsf{X}_n}_{\mathsf{f}_{\mathsf{x}}}$$

where x_i are 0 or 1.

The fractionnal part of m_x is called the fraction (of n bits): f_x . We have: $m_x = 1 + f_x$ and $1 \le m_x < 2$.

IEEE-754 standard: exponent

The exponent e_x is a signed integer of k bits such that $e_{min} \le e_x \le e_{max}$

Different representations are possible:

- two's complement,
- sign and magnitude,
- biased.


IEEE-754 standard: choice of a biased representation stored before the significand because it makes it possible comparisons between numbers in lexicographic order (forgetting the sign s_x) and to represent 0 with $e_x = f_x = 0$.

The stored exponent is the biased exponent eb such that $eb_x = e_x + b$ where b is the bias.

IEEE-754 standard: reserved exponents

The unbiased exponent $e_{min}-1$ and $e_{max}+1$ (resp. 0 and 2^k-1 with biased) are reserved for zero, subnormals special values.

| format | size | bias | unbiased | | biased | |
|--------|------|-------------------------------------|------------------|------------------|-------------------|-------------------|
| | k | ь | e _{min} | e _{max} | eb _{min} | eb _{max} |
| SP | 8 | 127 (= 2 ⁸⁻¹ – 1) | -126 | 127 | 1 | 254 |
| DP | 11 | $1023 \ (= 2^{11-1} - 1)$ | -1022 | 1023 | 1 | 2046 |



IEEE-754 standard: representation of zero

$$e_0 = f_0 = 0$$
, $s_0 = ?$

Two different representations: -0 and +0.

Consistent with the fact that we have 2 distinct infinities. We have: $\frac{1}{+0} = +\infty$ and $\frac{1}{-0} = -\infty$.

The standard enforces that the test -0 = +0 returns True.

In single precision, the machine representtion of +0 and -0 are:

| X | s _x | eb_x | m_{x} |
|----|----------------|----------|---|
| -0 | 1 | 00000000 | 000000000000000000000000000000000000000 |
| +0 | 0 | 00000000 | 000000000000000000000000000000000000000 |

IEEE-754 standard: special values

- The infinities, $-\infty$ and $+\infty$: $e_x = e_{max} + 1$ and $f_x = 0$.
- Not a Number: NaN (exception, partial function)


The result of an invalid operation such that 0/0, $\sqrt{-1}$ or $0 \times +\infty$: $e_x = e_{max} + 1$ et $f_x \neq 0$.

NaN propagates during the computations.

In single precision, we have:

| × | s _x | eb _× | m _x |
|-----------|----------------|-----------------|---------------------------------------|
| $-\infty$ | 1 | 11111111 | 00000000000000000000 |
| $+\infty$ | 0 | 11111111 | 00000000000000000000 |
| NaN | 0 | 11111111 | 00001001001111000000100 (for example) |

IEEE-754 standard: around zero, the subnormals



subnormals

The smallest positive normalized number x is such that $e_x = e_{min}$, $f_x = 0$, and so $x = 2^{e_{min}}$.

The "implicit 1" in the significand implies there is no floating-point number between $0\times 2^{e_{min}}$ and $1\times 2^{e_{min}}$ whereas there are 2^n number between $1\times 2^{e_{min}}$ and $2\times 2^{e_{min}}$.

The goal of subnormal numbers is to harmonize the repartition of floating-point numbers around 0.

We allow near 0 numbers with the form $(-1)^{s_x} \times 0.f_x \times 2^{e_{min}}$: $eb_x = 0$, m_x does not follow the rule of "implicit 1".

IEEE-754 standard

Subnormals and exponents

| Exponent unbiased | Significand | Comment |
|---|--------------------|--|
| $e_{\min} \le e_x \le e_{\max}$ | | normalized number, convention "implicit 1" |
| | $m_x = 0$ | zero |
| 1 | $m_x \neq 0$ | subnormal number, close to zero, no "implicit 1" |
| $\mathbf{e}_{x} = \mathbf{e}_{min} - 1$ | | zero, no implich i |
| | $m_x = 0$ | infinity $(-1)^{s_x} \infty$ |
| $\mathbf{e}_{x} = \mathbf{e}_{max} + 1$ | m _x ≠ 0 | NaN, invalid operation, propagates during the computation, NaN≠NaN |

The use of reserved exponent leads to costly computations.

IEEE-754 standard: need for rounding

If x and y are 2 representable numbers, then the result of an operation res = $x \odot y$ is not, in general, a representable number.

For example, in base B=10, the number 1/3 is not representable with a finite number of digits.

It is necessary to round the result, that is to say to return one of the closest representable numbers.

IEEE-754 standard: rounding modes



The norm proposes 4 rounding modes:

- \bullet rounding toward $+\infty$ denoted $\Delta(x)$: return the smallest floating-point number greater or equal the exact result x
- rounding toward $-\infty$ denoted $\nabla(x)$: return the largest floating-point number less or equal the exact result x
- rounding toward 0, denoted $\mathcal{Z}(\mathbf{x})$: return $\Delta(\mathbf{x})$ for negative numbers and $\nabla(\mathbf{x})$ for positive numbers
- rounding to the nearest, denoted ○(x): return the nearest floating-point number of the exact result x (breaks ties by rounding to the nearest even floating-point number)

The 3 first rounding modes are called directed rounding modes.

IEEE-754 standard: correctly rounding

Let x and y be two representable number, \odot be on operations +, -, \times , / and \diamond a rounding mode.

The standard requires that the result of the computation $x \odot y$ be equal to $\diamond(x \odot_{exact} y)$. The result must be similar to the one obtain by computing with infinite precision and then rounding this result.

Similar for square root.

This property is called correctly rounding.

The standard describes an algorithm for addition, subtraction, multiplication, division and square root and requires that the implementation produces the same result as those algorithms.

IEEE-754 standard: comparisons

The standard requires the comparison to be exact and not to overflow.

The specified comparison in the standard are:

- equality
- greater than
- less than

The sign of zero is not taken into account.

In case of a comparison with a NaN, the comparison returns False.

More precisely in case of equality: if x = NaN then x = x returns False and $x \neq x$ returns True (equality is not reflexive but it is a way to detect a Nan)

IEEE-754 standard: exception handling

No calculation should hinder the proper functioning of the machine. A mecanism with 5 flags makes it possible to inform the system about the behavior of operations:

INVALID operation the result by default is a NaN

DIVIDE by ZERO the result is $\pm \infty$

OVERFLOW overflow toward ∞ : the result is either $\pm\infty$ or the greatest floating-point number (in absolute value) depending on the sign of the exact result and the rounding mode

UNDERFLOW overflow toward 0: the result is either ± 0 or a subnormal

INEXACT inexact result: raised when the exact result is not representable exactly. Returns the correctly rounded result by default.

Summary of the IEEE-754 standard

| | exponent | fraction | value |
|---------------|-------------------------------------|----------|------------------------|
| normalized | $e_{min} \le e \le e_{max}$ | f ≥ 0 | ±(1.f)2 ^e |
| denormalized | $\mathbf{e} = \mathbf{e}_{min} - 1$ | f > 0 | $\pm (0.f)2^{e_{min}}$ |
| zero (signed) | $\mathbf{e} = \mathbf{e}_{min} - 1$ | f = 0 | ±ο |
| infinities | $e = e_{max} + 1$ | f = 0 | ±∞ |
| Not a Number | $\mathbf{e} = \mathbf{e}_{max} + 1$ | f > 0 | NaN |

| format | # nb of bits | k | n | e _{min} | e _{max} | b |
|------------------|--------------|----|----|------------------|------------------|------|
| single precision | 32 | 8 | 23 | -126 | 127 | 127 |
| double precision | 64 | 11 | 52 | -1022 | 1023 | 1023 |

| value | single precision | double precision |
|---------------------------|------------------------------|---------------------------------------|
| greatest normalized > 0 | $3.40282347 \times 10^{38}$ | $1.7976931348623157 \times 10^{308}$ |
| smallest normalized > 0 | $1.17549435 \times 10^{-38}$ | $2.2250738585072014 \times 10^{-308}$ |
| greatest denormalized > 0 | $1.17549421 \times 10^{-38}$ | $2.2250738585072009 \times 10^{-308}$ |
| smallest denormalised > 0 | $1.40129846 \times 10^{-45}$ | $4.9406564584124654 \times 10^{-324}$ |

Accuracy of computations


At each rounding, we loose a bit of accuracy, we call this rounding errors.

Even if an operation returns the best possible result (correctly rounded result), a sequence of computation can lead to huge errors due to the accumulation of rounding errors.

The two main sources of rounding errors during a computation are the cancellation and the absorption.

Cancellation


When we subtract two numbers very close.



If operands are results of previous computations with rounding errors, the 0's add on the right (red part) are wrong. The cancellation is said to be catastrophic when there is nearly no significant digits

Absorption

When we add 2 numbers of different order of magnitude we can "loose" all the information about the smallest one.



Combine with a cancellation it can be catastrophic. for example in single precision, if a=1 and $b=2^{-30}$ then: $a\oplus b=1$ and so $(a\oplus b)\ominus a=0$.

Example of absorption

We compute, for large values of N, the sum:

$$\sum_{i=1}^{N} \frac{1}{i}$$

Result of a C program (in single precision) on a Pentium 4:

| order | N | | | | | | |
|--------|----------------------------|-----------------------------|-----------------------------|-----------------------------|--|--|--|
| | 10 ⁵ | 10 ⁶ | 10 ⁷ | 108 | | | |
| exact | 1.209015e+01 | 1.439273e+01 | 1.669531e+01 | 1.899790e+01 | | | |
| 1 	o N | 1.2090 <mark>85e+01</mark> | 1.43 <mark>5736</mark> e+01 | 1.540368e+01 | 1.540368e+01 | | | |
| N 	o 1 | 1.209015e+01 | 1.4392 <mark>65</mark> e+01 | 1.66 <mark>8603</mark> e+01 | 1.8 <mark>80792</mark> e+01 | | | |

Floating-point numbers

Normalized floating-point numbers $\mathbb{F} \subseteq \mathbb{R}$:

$$\mathbf{x} = \pm \underbrace{\mathbf{x}_0.\mathbf{x}_1 \dots \mathbf{x}_{\mathsf{M}-1}}_{\mathsf{mantissa}} \times \mathbf{b}^e, \quad 0 \le \mathbf{x}_i \le \mathsf{b} - 1, \quad \mathbf{x}_0 \ne \mathbf{0}$$

b : basis, M : precision, e : exponent such that $e_{min} \leq e \leq e_{max}$ epsilon machine $\epsilon = b^{1-M}$

Approximation of $\mathbb R$ by $\mathbb F$ with rounding $\mathsf{fl}:\mathbb R\to\mathbb F.$ Let $\mathsf x\in\mathbb R$ then

$$fl(x) = x(1 + \delta), \quad |\delta| \le u$$

Unit rounding $\mathbf{u} = \varepsilon/2$ for rounding to the nearest

Standard model of floating-point arithmetic

Let $x, y \in \mathbb{F}$ and $o \in \{+, -, \cdot, /\}$.

The result $x \circ y$ is not in general a floating-point number

$$fl(x \circ y) = (x \circ y)(1 + \delta), \quad |\delta| \le u$$

IEEE 754 standard (1985 and 2008)

Correctly rounded : arithmetic ops $(+,-,\times,/,\sqrt{\ })$ performed as if first calculated to infinite precision, then rounded.

| | | | | , J | Inter |
|----------|---------|-----------|---------|---|----------------------|
| | | 23+1 bits | | $\mathbf{u} = 2^{1-24} \approx 1,92 \times 10^{-7}$ | |
| binary64 | 64 bits | 52+1 bits | 11 bits | $\mathbf{u} = 2^{1-53} \approx 2, 22 \times 10^{-16}$ | $\approx 10^{\pm 3}$ |

Useful notation : $\gamma_n := n\mathbf{u}/(1 - n\mathbf{u}) \approx n\mathbf{u}$

Advantages of the standard

IEEE arithmetic is closed: every operation produces a result. Default results:

| Exception type | Default result |
|-------------------|--------------------------|
| Invalid operation | NaN (Not a Number) |
| Overflow | $\pm\infty$ |
| Divide by zero | $\pm \infty$ |
| Underflow | subnormal numbers |
| Inexact | correctly rounded result |

NaN is generated by operations such as 0/0, $0 \times \infty$, ∞/∞ , $(+\infty) + (-\infty)$ and $\sqrt{-1}$.

Infinity symbol satisfies $\infty + \infty = \infty$, $(-1) \times \infty = -\infty$ and (finite)/ $\infty = 0$.

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- Use of Computer Arithmetic: Historical Failures
- 6 Conclusion

Therac 25: Description

- Therac 25: a radiation therapy machine
- Production: 1980ies
- Controlled by a DEC PDP-11



- Two possible modes:
 - Electron beam: 5MeV beam on patient
 - Short time therapy
 - X-Ray beam: 25MeV beam on collider, X-Ray on patient
 - Long time therapy
- One single electron gun, collider used for X-Ray mode.
- Switching from one mode to another under software control

Therac 25: A deadly failure

- Six high-overdoses between 1985 and 1987.
- ⇒ Therac 25 called back in 1987
 - Particular cases:
 - Marietta, Georgia, June 1985: 15000rad instead of 200rad
 - Breast ablation necessary
 - Patient alive
 - Hamilton, Ontario, July 1985: 15000rad instead of 200rad
 - Patient dies
 - 4 other similar cases, even after hardware update
 - What had happened?

Therac 25: Failure Analysis

- The failure could happen only in very rare circumstances
- Testing had not caught these cases
- When hardware detected wrong configuration of the system, software increased an error variable e by 1.
- The operator could start the radiation only of e was 0.
- The error variable e was stored on a 1 byte memory location
- After the 255th error, the next error made e become 0!
- Patients died due to a classical integer overflow problem

Mars Climate Orbiter: Description

- Mars Climate Orbiter:
 a space mission sent to Mars in 1999
- Two modules:
 - Mars Climate Orbiter stays in orbit
 - Mars Polar Lander descends to mars




- Mars Climate Orbiter was built by two companies
- Lockheed delivered a gravitational-force measuring equipment
- Data was analyzed by a computer built by Jet Propulsion Lab

Mars Climate Orbiter: Failure Analysis

- On 09/23/1999, Mars Climate Orbiter crashed on mars
- What had happened?
- The Lockheed system delivered data in fixed-point format
 - with imperial pound-force as a basic unit
 - $\bullet \ \ f = \beta_1^q \cdot \sum f_i \, \beta^i$
- The Jet Propulsion Lab computer expected fixed-point data
 - with metric Newton as a basic unit
 - $\bullet \ \ f = \beta_2^q \cdot \sum f_i \, \beta^i$
- Half a billion US \$s lost due to wrong fixed-point arithmetic

Ariane 5: Description

- ESA builds Ariane space launchers
- Ariane 5 followed Ariane 4
- First Ariane 5 flight: June 4th 1996 🖳



- Development time for Ariane 5: 10 years
- Cost of Ariane 5 development: 7 billion US \$
- Ariane 5 is not a complete redevelopment Ariane 5 somehow just extends Ariane 4

Ariane 5: half a billion US\$s lost

- At its first flight, Ariane 5 explodes
- The explosion happens 37 seconds after the launch



- The cost for this Ariane 5 and the satellites is roughly
 500 million US \$
- Any problem at an inaugural launch yields to reputation problems for ESA

Ariane 5: Failure Analysis

- Ariane 5 had a software module that check horizontal speed
- The software module was needed for the first seconds of flight
- Somewhere in that code (in ADA), there is this line:

```
horiz_veloc_bias := integer(horiz_veloc_sensor);
```

- This means a floating-point value is converted to integer
- The conversion is not protected and may overflow
- Testing had been done on Ariane 4
- Ariane 4 is much slower than Ariane 5
- ⇒ An overflow happened on Ariane 5 and cost 500 million US \$.

The Pentium Bug: Description

- Intel launches Pentium CPUs in 1993
- The old 486 floating-point unit gets reworked



- The 486 floating-point division used a restoring division
- That division produced 1 bit per division cycle
- The Pentium uses SRT-4, producing 2 bits per division cycle
- There are less operations between each division cycle
- ⇒ The Pentium fdiv is about 5 times faster

The Pentium Bug: a billion US\$s lost


- Pentium is launched in 1993
- In June 1994, a researcher discovers a bug in fdiv
 - He was doing research on primality
 - Some basic facts about integer division were not satisfied
- Intel starts by denying the problem
- Eventually, Intel admits that fdiv is bugged
 - About 4 leading digits are correct
 - Then, the divider might produce nonsense
- With market pressure, Intel exchanges all buggy CPUs for free
- ⇒ about a billion US \$s of loss for Intel

The Pentium Bug: Analysis

- What was wrong with the Pentium fdiv?
- The SRT-4 algorithm uses a table
 - One digit of the residual and one digit of the divisor
 - give a guess on one digit of the quotient
- Generation of the right table is pretty hard
 - but well understood in theory
- What happened:
 - The design team computed a table with 1066 entries
 - Only 1061 entries were transferred to the HW architects
 - A for loop was 5 iterations short
- Morality: prove your implementation not just the algorithm

Patriot Missiles: US soldiers killed

- MIM-104 Patriot missiles used by NATO
- Patriot supposed to intercept enemy missiles
- Used e.g. in the 1st Gulf war in 1991



- Missile able to find/follow target if target is close enough
- i.e. launch unit must fire the missile with enough precision
- On 02/25/1991, a Patriot missile fails to intercept an Iraqi SCUD missile
- The SCUD missile hits a US garrison in Saudi-Arabia, killing 28

Patriot Missiles: Analysis

- What had happened?
- The Patriot HW clock delivers time in 1/10ths of seconds
- The guidance software handles time in seconds, using single precision floating-point
- Conversion from HW time is not done dividing by 10 but by multiplying by 0.1
- 0.1 is not representable in binary floating-point
- A relative error of about 5.96 · 10⁻⁸ occurs
- The Patriot system had been running for more than 100 hours
- ⇒ Time was off by: $10 \cdot 100 \cdot 3600 \cdot 5.96 \cdot 10^{-8}$ s = 0.21 s
 - In these 0.21 s, a SCUD missile flies about 360 meters
 - The Patriot missile cannot follow missiles that far.

Vancouver Stock exchange: Description

- Vancouver, BC, Canada, has a stock exchange since 1906
- In 1982, the Vancouver Stock Exchange adopts an index



 A stock exchange index is a weighted sum of traded stocks:

$$I = \sum_i w_i \cdot c_i$$

 To avoid recomputation of the whole index each time a stock changes, perform an update of the index:

$$\mathbf{I}' = \sum_i \mathbf{w}_i \cdot (\mathbf{c}_i + \Delta_i) = \mathbf{I} + \sum_i \mathbf{w}_i \cdot \Delta_i$$

Vancouver Stock exchange: Where's the money?

- The Vancouver Stock Exchange Index starts in January 1982
- The weights are set such that the index starts at 1000 points
- Economy throughout 1982 and 1983 was good, trading was at high level
- In November 1983, the Vancouver Stock Exchange Index was at 524 points
- External advisors from Toronto and California reevaluated the index to 1099 points.

Vancouver Stock exchange: Failure Analysis

- What had happened?
- At each update, the product $w_i \cdot \Delta_i$ and the new index sum $I + w_i \cdot \Delta_i$ was computed on 4 valid digits
- Instead of unbiased rounding, truncation was used
- ⇒ each update yielded a systematic negative error

$$\tilde{\mathbf{I}}' = \nabla (\mathbf{I} + \mathbf{w_i} \cdot \Delta_i) = \mathbf{I}' + \delta$$

where $10^{-4} < \delta \le 0$.


 At 2900 transaction a day in 1982, and 440 days of wrong computations, we get an overall mean error of:

$$5 \cdot 10^{-4} \cdot 2900 \cdot 440 = 638$$

 Morality: the error of long running numerical systems must be shown to tend to zero.

Finite Elements: A method

- The Finite Element Method is a numerical technique for solving ODEs.
- Example: flow of air in atmosphere
- Idea behind the Finite Element Method:
 - Decompose the domain into small, but finite elements (boxes)
 - Suppose the solution (function) to be constant in each element
 - The ODE problem, with its boundary and starting values, becomes a linear system
 - Solve the linear system and hence obtain an approximate solution to the ODE.
- Using finite elements instead of infinitely small ones yields error.
- The analysis and bounding of such method error is important.



Finite Elements failure 1: Tacoma Bridge


Washington, US West Coast:
 The Tacoma Narrows Bridge connects
 Tacoma with the Kitsap Peninsula



- First Tacoma Bridge built in July 1940
- The bridge collapses in November 1940.
- What had happened?
- Finite Element Method at the time had modelled all static forces
- The Finite Element Method was proven correct if all dynamic forces vanished.
- The slightest wind creates a dynamic force onto the bridge structure.
- Morality: always check your hypotheses with reality.

Finite Elements failure 2: Lothar storm

- Meteorological services use FEM a lot
- On 12/24/1999
 1:00PM, German
 Meteorological
 Service predicts a
 storm



- Then, to be sure, adds data and recomputes
- On 12/24/1999 4:30PM, the service cancels the alert
- The storm hits Germany badly on 12/25/1999.
- Some data for the Atlantic was just interpolated.
- Morality: when it comes to safety-critical problems, classical numerical methods and Computer Arithmetic are not enough.

Is testing a solution?

- Smart Software testing may enhance safety of the system
- However, we need to be sure that we test with real-life values
- Testing for numerical systems is not (always) worthwhile
 - A double precision floating-point variable can represent about 10¹⁹ different values
 - Current computers manipulate about 10¹⁵ such variables per second
 - A failure might occur for 1 out of the 10⁵⁰ possibilities
- Multiple sources of approximation error:
 - A measurement approximates a physical value
 - The mathematical model approximates reality
 - The code approximates functions with polynomials
 - ullet Floating-point arithmetic approximates the reals ...
 - Humans can only think of about 8 things at a time

We need proofs & code generation

- Numerical code can be made safe
 - if modelization and software development care about errors in an a priori way
 - i.e. if every values comes with its error analysis and its bounds.
- Proofs of correctness are needed
 - They are easier to establish when made while developing the software
 - Humans may forget to check corner-cases in proofs
 - Computer checked proofs are becoming accessible
- Humans can think of 8 things at a time
 - Do no longer write numerical code by hand
 - Have the computer generate numerical code for you
 - A research project for the next decade

Outline

- Introduction
- Number representations
- Representing numbers to compute with them
- Floating-point arithmetic
- 5 Use of Computer Arithmetic: Historical Failures
- 6 Conclusion

Conclusion

- Number representation systems
 - ullet Different radices eta possible and used
 - Use a number representation that fits your technology!
 - Redundant number systems enable dirty but fast algorithms
- Operations
 - Addition is typically $\mathcal{O}(\mathbf{n})$
 - Multiplication is naively $\mathcal{O}(n^2)$
- Fixed & Floating-Point numbers are not the same as the reals
 - In Fortran, we write

```
real*8 :: a, b, c
```

- But: $a \oplus (b \oplus c) \neq (a \oplus b) \oplus c$
- Correct modeling, tidy error & round-off analysis are required
 - You don't want to be the engineer responsible of a failure

92 / 93

• Computer checked proofs are helpful and accessible

S. Graillat (SU) AFAE - Master 2 SFPN - MAIN5

Read the good books

Handbook of Floating-Point Arithmetic, by Muller et al.



Also

- Digital Arithmetic by Ercegovac and Lang
- Arithmétique des ordinateurs by J.-M. Muller, (on his page)
- What Every Computer Scientist Should Know About Floating-Point Arithmetic by Goldberg (Google will find you several copies)
- The web page of William Kahan at Berkeley.