Section 1.2 Basic Language Features

- 1. Overview
- 2. Terminology
- 3. Operators
- 4. Control and data structures
- 5. Variables and data types
- 6. Standard I/O streams
- 7. Functions
- 8. References

1.2.1 Overview

- History of C++
 - C++ is a general purpose object-oriented programming language
 - it was developed by Bjarne Stroustrup, starting in 1979
 - initially known as "C with classes", i.e. object-oriented C

Overview (cont.)

- Characteristics of C++
 - it provides all the standard high-level OO functionality
 - polymorphism
 - generic programming using templates
 - operator overloading
 - multiple inheritance
 - exception handling
 - it also allows calls to low-level C functions
 - memory management operations, basic I/O
 - bit-wise operations
 - C libraries for TCP/IP sockets, for threads, etc.

1.2.2 Terminology

Expression

- a sequence of operations that resolve to a single value
- > examples:

```
a + b - 3 * cd * pow(q, a)
```

Statement

- an expression terminated by a semi-colon
- > examples:

```
■ tmpValue = a + b - 3 * c;
```

- what happens here: d * pow(g, a);
- statements also resolve to a single value
 - value may be void, or it may be ignored

Terminology (cont.)

Block

- a sequence of statements between a pair of matching braces
- > examples:
 - functions
 - loops, if-statements
 - free-floating blocks!
- spot the difference:

```
int x = 8, size = 5, i = 0;
while (i <= size) {
    x = i;
    ++i;
}
cout << x << endl;
int x = 8, size = 5, i = 0;
while (i <= size) {
    int x = i;
    ++i;
}
cout << x << endl;</pre>
```

Terminology (cont.)

- Scope
 - the part of the program where a variable can be used
- Block scope:
 - variables are declared inside a block
 - these are called *local variables*
 - any kind of block can have local variables
- Global scope (also called file scope)
 - variables are declared outside of any block
 - these are called *global variables*
 - industrial quality software never uses global variables

1.2.3 Operators

• Types of operators:

Operators (cont.)

- Characteristics of operators:
 - arity
 - number of operands
 - operators can be unary, binary, or ternary
 - precedence
 - order in which operators execute
 - remember BEDMAS?
 - associativity
 - order in which operators of the same precedence execute
 - associativity can be left-to-right, or right-to-left

1.2.4 Control and Data Structures

- Control structures
 - conditional
 - example: if-else
 - selective
 - example: switch
 - iterative
 - example: for, while, do-while
 - > jump
 - example: break, continue

Control and Data Structures (cont.)

- Data structures
 - > C-style structs
 - in C++, they contain variables and functions, just like classes
 - by default, their members are public
 - this is bad software engineering



- classes
 - like Java, they contain variables and functions
 - by default, their members are private
 - using classes follows the principle of least privilege
 - this is good software engineering
- do not use structs in assignments or tutorials

1.2.5 Variables and Data Types

- Program memory is like a bookshelf full of boxes
 - the boxes have different sizes
 - each box has a label or name
 - each box contains something
 - each box is in a specific location on the shelf
- Variables are like those boxes
 - they come in different sizes, based on data type
 - examples: int, double, char
 - they have a name
 - they contain something, called a value
 - they have a location in memory
 - represented as a memory address where the value is stored

Variables and Data Types (cont.)

- Characteristics of variables:
 - name
 - this is the identifier that the program uses to access the content
 - value
 - this is the content of the variable
 - data type
 - this determines the number of bytes required in memory
 - location in memory
 - this is the address in memory where the value is stored

Variables and Data Types (cont.)

- Data types
 - > primitive (built-in)
 - examples: int, float, double, char, bool
 - user defined
 - defined by programmer (you!)
 - these are your *classes*
 - memory address
 - example: pointers

1.2.6 Standard I/O Streams

- C++ library stream objects
 - declared in the iostream library
 - encapsulated in the std namespace

• cout

object of class ostream, used for standard output

• cin

object of class istream, used for standard input

• cerr

object of class ostream, used for standard error

1.2.7 Functions

- In C++, there are two types of functions:
 - global functions
 - they are defined outside of any block
 - they can be called from any function and any class in the program
 - example: main()
 - member functions
 - they are defined within a class
 - they may be called on an object of that class
 - static member functions can also be called on the class itself
 - some OO languages call these functions methods

© 2018 Christine Laurendeau

Functions (cont.)

- Important terminology:
 - function declaration
 - this is the function prototype
 - function implementation
 - this is the code between the braces
 - it's the "body" of the function
- Member functions:
 - declaration and implementation are stored in different files

Function Design

- Characteristics of *correctly designed* functions:
 - they take data into the function, do something, return a result
 - two ways to return results: return value or using parameters
 - they are single-purpose
 - they have a single goal, they do one thing only
 - they encapsulate (hide) their functionality
 - other programmers know what function does, not how it does it
 - they should be reusable
 - in the same program, and in other programs

Function Design (cont.)

- Return values:
 - they are often used to indicate success or failure
 - they are used to return results from very simple functions
 - mostly "getter" functions
 - > normally, results are returned using an *output parameter*
 - this allows multiple values to be returned to calling function
 - ... more on this coming up...

©2018 Christine Laurendeau

Function Design (cont.)

- Parameters
 - they are treated as local variables inside a function
- Parameter modifiability:
 - pass-by-value
 - the parameter value is *copied* from the calling function
 - the function works on the local copy
 - pass-by-reference
 - parameter is memory address of variable declared in calling function
 - this allow variables in calling function to be modified
 - in C++, this can be done using pointers or references

Function Design (cont.)

- Every parameter has a role to play in the function:
 - input parameter
 - this is a value required by function to do its work
 - it is data sent by calling function
 - output parameter
 - this stores a result of the function doing its work
 - this is how results are correctly "returned" to the calling function
 - in assignments, use this technique instead of return values!
 - input-output parameter
 - this is both an input parameter, and an output parameter
 - it contains a value that is needed by the function
 - it gets modified by the function

1.2.8 References

- To pass parameters by reference:
 - we need to use a memory address as a variable
 - the best way to do this is with pointers
 - pointers are very powerful, but can be difficult to learn
 - ... more on pointers later ...
 - > an alternative to pointers: references
 - they are used for pass-by-reference
 - they are not very versatile
 - they are not a language feature in C, only in C++

© 2018 Christine Laurendeau

References (cont.)

- What is a reference not?
 - > a reference is **not** a real variable! it does not occupy memory
 - it must be assigned a value on declaration
 - its value can never change
- So what is it?
 - a binding, or an alias, for an existing variable
 - declaring and initializing a reference creates a bond between:
 - the reference name
 - an existing variable
 - the bond is unbreakable
 - most common usage is for passing parameters by reference

© 2018 Christine Laurendeau