

1. Introduction

1.1 What is the RIVA Control Center?

The **RIVA Control Center** is a centralized administrative interface designed to manage and update content for the RIVA website. It serves as the backend system for maintaining datasets and system configurations related to regional economic integration and value chain analysis.

The system is composed of three key modules:

- **RI (Regional Integration Analysis):** Manages data relating to the integration of domestic economies within a regional context.
- **VA (Value Chain Analyzer):** Handles data describing the structure and distribution of value added in international production chains.
- **User Management:** Allows administrators to manage user accounts and access credentials.

Each module is integrated into a single interface to ensure efficient data maintenance and consistency across the RIVA platform.

1.2 Purpose and Scope of this Manual

This manual is designed to guide users through the features and functionalities of the RIVA Control Center. It provides step-by-step instructions for data entry, user management, and the use of supplementary tools such as Navicat.

Intended users of this manual include:

- System administrators responsible for backend data maintenance.
- Content managers and analysts involved in data entry and updates.
- Technical staff responsible for supporting the RIVA system infrastructure.

The manual covers:

- Functional overviews of each module
- Instructions for managing data via web interface and external tools
- Guidelines for secure access and best practices for data integrity

2. System Overview

2.1 Architecture of RIVA Control Center

The RIVA Control Center is built using a **client-server architecture**. The **frontend** utilizes the **Quasar Framework (Vue 3)** to deliver a responsive and user-friendly interface. The **backend** is developed in **PHP**, and all data is stored in a **MySQL** database.

Data operations are performed via **RESTful APIs**, separating frontend and backend processes for better scalability and maintainability. Both the public-facing RIVA website and the RIVA Control Center share the same database, ensuring data consistency and centralized management.

2.2 Core Modules Overview

The RIVA Control Center comprises three core modules:

2.2.1 RI Module (Regional Integration Analysis)

This module enables administrators to manage datasets related to regional integration, including annual economic indicators and country-specific information.

2.2.2 VA Module (Value Chain Analyzer)

This module handles data associated with global value chains, such as individual economic inputs, groupings of economies, and exporting sectors. It also includes a **Data Upload Guide** to assist users with uploading structured datasets.

2.2.3 User Management Module

This module provides tools to manage staff login credentials. At present, all logged-in users have full access to all modules; no role-based restrictions are currently in place.

3. Accessing the RIVA Control Center

3.1 Login Procedure

To access the RIVA Control Center, follow the steps below:

Step 1: Open the Login Page

Open your preferred web browser and navigate to the following URL:

👉 <https://riva.negotiatetrade.org/cc>

You will be presented with the RIVA Control Center login screen, as shown in **Figure 1** below.




Figure 1: RIVA Control Center Login Page

Step 2: Enter Login Credentials

On the login screen, enter the required credentials:

- **Username:** admin
- **Password:** rivacc2024

⚠️ *Please ensure that the credentials are typed accurately. Passwords are case-sensitive.*

Once the credentials have been entered, click the **Login** button to proceed.

Step 3: Access the Main Dashboard

After a successful login, you will be redirected to the **Main Dashboard**, where you can begin managing data within the RIVA system. The dashboard provides access to all three primary modules—**RI**, **VA**, and **User Management**—via the left-side menu.

You can now select a module to begin updating categories and datasets in the central database.




Figure 2: Welcome Page After Logging into the RIVA Control Center

4. RI Module

4.1 Overview

The **RI Module** (Regional Integration Analysis) in the RIVA Control Center allows administrators to configure key interface elements used in the Regional Integration Analyzer, including the range of years available for analysis and the list of economic groups and individual economies.

This module consists of two main components:

- **Year Management:** Used to define the time period (start year and end year) available for users to explore.
- **Economics Management:** Used to upload structured JSON files that define the economy groups and country lists used in analysis.

 **Note:** Core calculation data is not handled in this module. Data for index scores, indicators, and time-series calculations must be imported directly into the MySQL database using **Navicat** from pre-structured CSV files provided by the data team. This is covered in Section 7.

4.2 Year Management

The **Year** menu is used to define the **Start Year** and **End Year** for which the RI Analyzer will display available data. For example, if the system is configured from 2010 to 2023, users will only be able to select and view data within this range.

To access and update the year range:


1. Navigate to **RI > Year** in the left-hand menu.
2. The current year settings will be displayed (Figure 3).



Start year	End year	Edit
2010	2023	Edit

Figure 3: Year Page in RI section

3. Click the **Edit** button to open the configuration dialog.
4. Enter the new **Start Year** and **End Year** in the fields provided (Figure 4).
5. Click **Save** to apply the changes.



The dialog box is titled "Year Setting for RI". It contains two input fields: "Start year" with the value "2010" and "End year" with the value "2023". At the bottom, there are two buttons: "Cancel" and "Save".

Figure 4: Year Setting for RI dialog

⚠ We recommend updating the year range **after all necessary datasets have been uploaded** to avoid inconsistencies in user interface and calculations.

4.3 Economics Management

This section allows administrators to upload structured JSON files that define the groupings of economies and individual economies available for regional integration analysis. Each entry must be updated separately.

To upload a dataset:

1. Go to **RI > Economics**.
2. You will see a list of 24 data entries available for update (Figure 5).

JSON sample file			
No.	Economics	Date	Upload
1	Integration overview	30/09/2024 16:50	Upload
2	Intra-group (sustainable)	30/09/2024 16:50	Upload
3	Intra-group (conventional)	22/08/2024 03:38	Upload
4	Economy-partner-reporter (sustainable)	22/08/2024 08:12	Upload
5	Economy-partner-partner (sustainable)	22/08/2024 08:12	Upload
6	Economy-partner-reporter (conventional)	22/08/2024 08:13	Upload
7	Economy-partner-partner (conventional)	22/08/2024 08:13	Upload
8	Build your own-reporter (sustainable)	22/08/2024 08:14	Upload
9	Build your own-partner (sustainable)	22/08/2024 08:14	Upload
10	Build your own-reporter (conventional)	22/08/2024 08:14	Upload
11	Build your own-partner (conventional)	22/08/2024 08:15	Upload
12	Data availability all data (sustainable)	22/08/2024 08:15	Upload
13	Data availability all data (conventional)	22/08/2024 08:15	Upload
14	Data availability DigiSRII (sustainable)	22/08/2024 08:17	Upload
15	Data availability DigiSRII (conventional)	22/08/2024 08:17	Upload
16	Data availability spec all data reporter (sustainable)	22/08/2024 08:17	Upload
17	Data availability spec all data partner (sustainable)	22/08/2024 08:17	Upload
18	Data availability spec DigiSRII reporter (sustainable)	22/08/2024 08:18	Upload
19	Data availability spec DigiSRII partner (sustainable)	22/08/2024 08:19	Upload
20	Data availability spec all data reporter (conventional)	22/08/2024 08:19	Upload
21	Data availability spec all data partner (conventional)	22/08/2024 08:19	Upload
22	Data availability spec DigiSRII reporter (conventional)	01/09/2024 03:17	Upload
23	Data availability spec DigiSRII partner (conventional)	01/09/2024 03:18	Upload
24	Country brief	22/08/2024 08:20	Upload

Figure 5: Economics Page in the RI Section

3. Click the **Upload** link for the specific entry you wish to update.
4. A dialog box will appear where you can upload your file (Figure 10).




Figure 6: Upload Dialog for Economics

5. Click **Choose File**, select your JSON file, and click **Upload** to complete the process.

⚠ Important: When a file is uploaded, the system **removes all previous data** in that entry and replaces it with the content of the new file. Partial updates are not supported. Ensure each file is complete and encoded in **UTF-8** format.

4.3.1 JSON Structure Requirements

Each JSON file must contain two sections:

- **Economic Group**
- **Individual Economies**

Example header for Economic Group:

```
{  
  "country": "Economy groups",  
  "disable": true  
}
```

Example data entry for Economic Group:

```
{  
  "iso": "escap",  
  "country": "Asia-Pacific"  
}
```

Example header for Individual Economies:

```
{  
  "country": "Individual economies",  
  "disable": true  
}
```

Example data entry for Individual Economies:

```
{  
  "iso": "AFG",  
  "country": "Afghanistan"  
}
```

✓ All content must be enclosed in square brackets [] to form a valid JSON array.

↺ This process must be repeated for each of the 24 entries individually.

4.4 Data for Calculation (Imported via Navicat)

All datasets required for actual index calculations—such as integration scores, dimension weights, and other indicators—must be imported into the database using **Navicat**.

These datasets are usually prepared in **multiple CSV files** by the data team and imported directly into MySQL. The RIVA Control Center does not provide a web interface for uploading large datasets due to system performance and validation limitations.

i For more details, refer to **Section 7: Data Management with Navicat**

5. VA Module

5.1 Overview

The VA Module (Value Chain Analyzer) in the RIVA Control Center is used to manage structural economic data shown in the VA section of the RIVA website. Most datasets can be managed through the web interface, including year ranges, individual economies, economy groups, and export sectors. However, some datasets still require manual imports using the Navicat tool.

The VA Module includes the following submenus:

1. Year – Manage years available for data analysis
2. Individual Economics – Manage country-level economic data
3. Economy Groups – Manage economic groupings for comparison
4. Exporting Sector – Manage sectors used in export-based analysis
5. Data Upload Guide – A reference table for Navicat-based data import

5.2 Year

The Year menu allows users to manage the list of years available for analysis in the VA module. Each year can be marked as "Active" or deleted.

- Active years will appear in the frontend year selection menu.
- Delete will remove the year from the interface (data in the database is not affected).

To add a new year, click the "Add new year" button.




Figure 7: Year Management Page in the VA Module

5.3 Individual Economics

This section lists individual economies (e.g., countries) and their attributes.

Displayed columns include:

- Economic name
- ISO code
- Region (e.g., East Asia, Europe)
- Area (e.g., Asia-Pacific, Europe)

Users can add new economies or edit/delete existing ones using the "Add new eco" button or Edit/Delete actions on each row.



No.	Economic	ISO	Region	Area	Edit	Delete
1	Argentina	ARG	Latin America and the Caribbean	Latin America	Edit	
2	Armenia	ARM	North and Central Asia	Asia-Pacific	Edit	
3	Australia	AUS	Pacific	Asia-Pacific	Edit	
4	Austria	AUT	Western Europe	Europe	Edit	
5	Bangladesh	BGD	South and South-West Asia	Asia-Pacific	Edit	
6	Belgium	BEL	Western Europe	Europe	Edit	
7	Bhutan	BTN	South and South-West Asia	Asia-Pacific	Edit	
8	Brazil	BRA	Latin America and the Caribbean	Latin America	Edit	
9	Brunei Darussalam	BRN	South-East Asia	Asia-Pacific	Edit	
10	Bulgaria	BGR	Eastern Europe	Europe	Edit	
11	Cambodia	KHM	South-East Asia	Asia-Pacific	Edit	
12	Canada	CAN	North America	North America	Edit	
13	Chile	CHL	Latin America and the Caribbean	Latin America	Edit	
14	China	CHN	East and North-East Asia	Asia-Pacific	Edit	
15	Colombia	COL	Latin America and the Caribbean	Latin America	Edit	
16	Croatia	HRV	Eastern Europe	Europe	Edit	
17	Cyprus	CYP	Southern Europe	Europe	Edit	
18	Czech Republic	CZE	Eastern Europe	Europe	Edit	
19	Denmark	DNK	Northern Europe	Europe	Edit	
20	Ecuador	ECU	Latin America and the Caribbean	Latin America	Edit	
21	Egypt	EGY	Africa and Middle East Asia	Asia-Pacific	Edit	
22	Estonia	EST	Northern Europe	Europe	Edit	
23	Fiji	FJI	Pacific	Asia-Pacific	Edit	
24	Finland	FIN	Northern Europe	Europe	Edit	
25	France	FRA	Western Europe	Europe	Edit	
26	Georgia	GEO	North and Central Asia	Asia-Pacific	Edit	
27	Germany	DEU	Western Europe	Europe	Edit	
28	Greece	GRC	Southern Europe	Europe	Edit	

Figure 8: Individual Economics Page in the VA Module

5.4 Economy Groups

Economy groups are sets of countries used for grouped visualization and comparison in the VA module.

Displayed columns include:


- Group name
- Number of economies in the group (used for plotting)
- ISO code
- Edit / Delete actions

To add a new group, click "Add new eco group" and provide:

1. Group name
2. ISO code

3. List of ISO codes for member economies

⚠ After creating a group, please notify the development team at pakkawat.kh@gmail.com to ensure backend mapping is updated.



No.	Economy group	economics	ISO	Edit	Delete
1	APEC	10	APEC	Edit	Delete
2	APTA	6	APTA	Edit	Delete
3	Asia-Pacific	10	AP	Edit	Delete
4	BIMSTEC	5	BIMSTEC	Edit	Delete
5	CPTPP	10	CPTPP	Edit	Delete
6	East and North-East Asia	6	ENEA	Edit	Delete
7	Europe	10	EUR	Edit	Delete
8	European Union	10	EUZ	Edit	Delete
9	FEALAC	10	FEALAC	Edit	Delete
10	Latin America and the Caribbean	7	LAC	Edit	Delete
11	MERCOSUR	6	MERCOSUR	Edit	Delete
12	North and Central Asia	3	NCA	Edit	Delete
13	Pacific	2	PAC	Edit	Delete
14	Pacific Alliance	4	PAC_ALLIANCE	Edit	Delete
15	RCEP	12	RCEP	Edit	Delete
16	SAARC	5	SAARC	Edit	Delete
17	South and South-West Asia	7	SSWA	Edit	Delete
18	South-East Asia	9	SEA	Edit	Delete
19	USMCA	3	USMCA	Edit	Delete
20	World	10	WLD	Edit	Delete

Figure 9: Economy Groups Page in the VA Module

5.5 Exporting Sector

This section lists the economic sectors used for export-related analysis. Sectors can be grouped and reordered using the Order ID.

Displayed columns include:

- Order ID
- Sector name (full)
- Short name
- Sector group (e.g., Manufacturing, Services)

Use the "Add sector" button to insert new sectors. Edit/Delete functions are available for each row.

Order ID	Sector name	Short name	Sector group	Edit	Delete
10	Agriculture, hunting, forestry, and fishing	Agriculture	Agriculture	Edit	
20	Mining and quarrying	Mining	Mining	Edit	
30	Food, beverages, and tobacco	Food & Beverages	Manufacturing Low tech	Edit	
40	Textiles and textile products	Textiles	Manufacturing Low tech	Edit	
50	Leather, leather products, and footwear	Leather & Footwear	Manufacturing Low tech	Edit	
60	Wood and products of wood and cork	Wood & Cork	Manufacturing Low tech	Edit	
70	Pulp, paper, paper products, printing, and publishing	Paper & Publishing	Manufacturing Low tech	Edit	
80	Coke, refined petroleum, and nuclear fuel	Petroleum & Nuclear	Manufacturing High and medium tech	Edit	
90	Chemicals and chemical products	Chemicals	Manufacturing High and medium tech	Edit	
100	Rubber and plastics	Rubber & Plastics	Manufacturing Low tech	Edit	
110	Other nonmetallic minerals	Nonmetallic Minerals	Manufacturing High and medium tech	Edit	
120	Basic metals and fabricated metal	Basic Metals	Manufacturing High and medium tech	Edit	
130	Machinery, nec	Machinery	Manufacturing High and medium tech	Edit	
140	Electrical and optical equipment	Electrical Equipment	Manufacturing High and medium tech	Edit	
150	Transport equipment	Transport Equipment	Manufacturing High and medium tech	Edit	
160	Manufacturing, nec; recycling	Manufacturing & Recycling	Manufacturing Low tech	Edit	
170	Electricity, gas, and water supply	Utilities	Utilities	Edit	
180	Construction	Construction	Construction	Edit	
190	Sale, maintenance, and repair of motor vehicles and motorcycles; retail sale of fuel	Motor Vehicles & Fuel	Services Trade and repair	Edit	
200	Wholesale trade and commission trade, except of motor vehicles and motorcycles	Wholesale Trade	Services Trade and repair	Edit	
210	Retail trade, except of motor vehicles and motorcycles; repair of household goods	Retail Trade	Services Trade and repair	Edit	
220	Hotels and restaurants	Hotels & Restaurants	Services Tourism	Edit	
230	Inland transport	Inland Transport	Services Transport	Edit	
240	Water transport	Water Transport	Services Transport	Edit	
250	Air transport	Air Transport	Services Transport	Edit	
260	Other supporting and auxiliary transport activities; activities of travel agencies	Transport Support	Services Transport	Edit	
270	Post and telecommunications	Post & Telecom	Services ICT	Edit	
280	Financial intermediation	Finance	Services Financial	Edit	

Figure 10: Exporting Sector Page in the VA Module

5.6 Data Upload Guide

This page provides a mapping between the database tables and the source folders used for data import via Navicat. It is intended for internal use by the data team.

Each entry shows:

- Table name
- Folder path for the source CSV files

⚠ This page is read-only. Data import must be done using Navicat.

📁 For detailed import procedures, refer to Chapter 7: Data Management with Navicat

Table	Data Folder
va_gvc_overview	GVC_relationships/overview
va_st_value_added1	Structure_of_value_added/REP_PART_X
va_st_value_added2	Structure_of_value_added/REP_PART_TB
va_backward1	Backward_linkages/IND
va_backward2	Backward_linkages/SOURCE
va_forward1	Forward_linkages/IND

All files must be imported using Navicat by the data team.
Please make sure each file is complete and correctly structured before import.

Figure 11: Data Upload Guide Page

6. User Management Module

6.1 Overview

The User Management module allows administrators to manage staff accounts that have access to the RIVA Control Center. This includes creating new user accounts, resetting passwords, and removing users.

There is no role-based permission system; all users who are logged in have full access to all modules in the system.


6.2 Staff Management

The Staff page shows a list of usernames that have access to the system. Each account can be edited using the following options:

Displayed columns include:

- **Username** – The login name of the user
- **Reset password** – Click to set a new password for the user
- **Delete** – Remove the user from the system

To create a new user, click the **"Add new staff"** button, then enter the desired username and password, and click **Save**.



Username	Reset password	Delete
art	Reset password	Delete
pam	Reset password	Delete
admin	Reset password	Delete

Figure 12: Staff List Page

7. Connecting to the Database Using Navicat

This chapter provides a step-by-step guide for installing Navicat Premium (Windows only) and connecting to the RIVA database using MySQL.

7.1 Installing Navicat Premium (Windows Only)

To begin importing data into the RIVA database, the data team must first install Navicat Premium on their computer. The installation process is as follows:

1. Download the Program

- Visit the following link: <https://riva.negotiatetrade.org/#/download/uploadapp>
- Download the Navicat Premium installation file.

2. Extract and Run the Installer

- After downloading, you will get a file named Navicat Premium 17.0.13 x64.zip.
- Double-click to open the .zip file and run the installer inside.




Figure 13: Files Inside the ZIP Archive

- If a Windows security prompt appears, click on **More info**, then click **Run anyway**.




Figure 14: Windows protected your PC Window

3. Finish Installation

- After the installer completes, the software is ready to use. *Do not update the software after installation.*

7.2 Connecting to the Database in RIVA Using Navicat Premium

Once Navicat Premium is installed, you can proceed to connect to the RIVA database by following the steps below:

1. Open Navicat Premium 17

- Search for **Navicat Premium 17** on your computer and open the application.

2. Create a New Connection

- Click on **Connection** from the top menu.




Figure 15: Selecting Connection to Create a Database Connection

3. Select MySQL

- From the list of database types, select **MySQL**, then click **Next**.




Figure 16: Selecting a connection type

4. Enter Connection Information

- A new screen will appear. Fill in the fields as follows:
 - **Connection Name:** riva
 - **Host:** 150.95.83.14
 - **Port:** 3306
 - **User Name:** admin_unescap
 - **Password:** @Chomart12
 - Select **Save password**




Figure 17: Entering Connection Information

5. Test the Connection

- Click **Test Connection** to verify that the information is correct.
- Once successful, the message "Connection Successful" will appear at the bottom.




Figure 18: Successful Database Connection

6. Save the Connection

- Click **OK** to save the connection settings.

7.3 Importing Data into the Database

This section demonstrates how to import CSV data into the va_str_value_added1 table using Navicat.

1. Locate the data folder:

- **Folder:** Structure_of_value_added/REP_PART_X
- **Target Table:** va_str_value_added1

AP.csv	12/9/2567 8:32	Microsoft Excel C...	8,923 KB
APEC.csv	12/9/2567 8:32	Microsoft Excel C...	9,050 KB
APTA.csv	12/9/2567 8:32	Microsoft Excel C...	7,407 KB
ARE.csv	12/9/2567 8:32	Microsoft Excel C...	2,876 KB
ARG.csv	12/9/2567 8:32	Microsoft Excel C...	2,300 KB
ARM.csv	12/9/2567 8:32	Microsoft Excel C...	1,222 KB
AUS.csv	12/9/2567 8:32	Microsoft Excel C...	5,757 KB
AUT.csv	12/9/2567 8:32	Microsoft Excel C...	6,614 KB
BEL.csv	12/9/2567 8:32	Microsoft Excel C...	7,053 KB
BGD.csv	12/9/2567 8:32	Microsoft Excel C...	2,081 KB
BGR.csv	12/9/2567 8:32	Microsoft Excel C...	4,106 KB
BIMSTEC.csv	12/9/2567 8:32	Microsoft Excel C...	7,477 KB
BRA.csv	12/9/2567 8:32	Microsoft Excel C...	5,695 KB
BRN.csv	12/9/2567 8:32	Microsoft Excel C...	1,116 KB
BTN.csv	12/9/2567 8:32	Microsoft Excel C...	758 KB
CAN.csv	12/9/2567 8:32	Microsoft Excel C...	6,722 KB

Figure 19: shows individual CSV files in the folder

- Open Navicat and select the riva > riva schema from the left-hand panel.




Figure 20: Navigating to the database

3. Identify and right-click the table va_str_value_added1

- Choose **Truncate Table** to clear existing data.
- Then choose **Empty Table** to reset index.




Figure 21: Context menu

4. Select **Import Wizard** from the same menu.

- In the wizard, choose **CSV file** as import type and click **Next**





Figure 22: Import Wizard Window


- Click **Add File(s)** and select all CSV files in REP_PART_X.



The 'Import Wizard' window displays a message: "You must select a file which will be a source of data." Below this, the 'Import from:' section contains a text input field with the placeholder "Please provide a file path or an URL to import". To the right of this field are two buttons: "Add File(s)" and "Add URL". Below the input field is an 'Encoding:' dropdown menu currently set to "65001 (UTF-8)". At the bottom of the window, there are navigation buttons: "<<", "< Back", "Next >", ">>", and "Cancel".

Figure 23: Window for Adding CSV Files

5. In the **Target Table** column, right-click the first entry (va_str_value_added1) and choose **Map All to This Target Table**



The 'Import Wizard' window displays the instruction: "Select the target tables. You can select from existing tables or input other names for new tables." It features a table with three columns: 'Source', 'Target Table', and 'New Table'. The 'Source' column lists various country codes (AP, APEC, APTA, ARE, ARG, ARM, AUS, AUT, BEL, BGD, BGR, BIMSTEC, BRA, BRN, BTN). The 'Target Table' column shows the mapping for each source, with 'va_str_value_added1' selected for 'AP'. The 'New Table' column indicates 'Yes' for all entries. A right-click context menu is open over the 'va_str_value_added1' entry, showing the option "Map All to This Target Table". At the bottom, navigation buttons include "<<", "< Back", "Next >", ">>", and "Cancel".

Source	Target Table	New Table
AP	va_str_value_added1	
APEC	APEC	Yes
APTA	APTA	Yes
ARE	ARE	Yes
ARG	ARG	Yes
ARM	ARM	Yes
AUS	AUS	Yes
AUT	AUT	Yes
BEL	BEL	Yes
BGD	BGD	Yes
BGR	BGR	Yes
BIMSTEC	BIMSTEC	Yes
BRA	BRA	Yes
BRN	BRN	Yes
BTN	BTN	Yes

Figure 24: Mapping tables

6. Click >> to proceed and review the summary.
 - Then click **Start** to begin the import.




Figure 25: Upload confirmation

7. When the import is finished, **do not press Start again** to avoid duplicate data.




Figure 26: Import finished screen