

All Microsoft~

Products~

Get helpwwith Windows upgrade and installation errors

► *Applies To* Resources∨

Buy Microsoft 365

Windows 11 Windows 10

There are many reasons why you might receive an error message when upgrading or installing Windows 11, but common errors can be fixed with a few steps that you can do on your own. Note: An upgrade takes your device from an older version of Windows, such as Windows 7, Windows 8.1, or Windows 10 to Windows 11.

Before searching for a specific error code, try the tips listed in **General fixes**. If those don't fix your upgrade or installation problem, check the table of error codes at the bottom of this article.

General fixes

Here are some things you can try to fix upgrade and installation errors:

Remove external hardware	~
Update Windows	~
Uninstall non-Microsoft antivirus software	~
Uninstall nonessential software	~
Free up disk space	~

0xC1900101 Errors

An error that begins with 0xC1900101 is usually a driver error. If you see any of these error codes, try the following steps first to fix the problem. If these steps don't work, see Resolve Windows upgrade errors for more detailed technical info.

- 0xC1900101 0x2000c
- 0xC1900101 0x20017
- 0xC1900101 0x30018
- 0xC1900101 0x3000D
- 0xC1900101 0x4000D
- 0xC1900101 0x40017
- 1. Make sure that your device has enough space. Your device requires at least 16 GB of free space to upgrade a 32-bit OS, or 20 GB for a 64-bit OS. For more info, see Free up drive space in Windows.
- 2. **Run Windows Update a few times.** Download and install any available updates in Windows Update, including software updates, hardware updates, and some third-party drivers. Use the Windows Update Troubleshooter to fix Windows 11 Update errors.
- 3. Check third-party drivers and download any updates. You can find third-party drivers and installation instructions for any hardware you've added to your device on the manufacturer's website.
- 4. **Unplug extra hardware.** Remove all external storage devices and drives, docks, and other hardware you might have plugged into your device that isn't needed for basic functionality.
- 5. Check Device Manager for errors. In the search box on the taskbar, type device manager. Choose Device Manager from the results. In the window that pops up, look for any device with a yellow exclamation mark beside it (you may have to select each category to switch to the list of devices). Press and hold (or right-click) the device name and select either Update Driver Software or Uninstall to correct the errors.

- 6. **Remove third-party security software.** Make sure you know how to reinstall your programs and that any necessary product keys are on hand. Windows Defender will help protect your device in the meantime.
- 7. **Repair hard-drive errors.** In the search box on the taskbar, type **command prompt**. Choose **Command Prompt** from the list of results. In the window that pops up, type **chkdsk/f C:** and press the Enter key. Repairs automatically start on your hard drive, and you'll be asked to restart your device.

Note: You must have administrator permissions on your device to do this.

- 8. Do a clean restart into Windows. See How to perform a clean boot in Windows.
- Restore and repair system files. In the search box on the taskbar, type command prompt. Choose Command Prompt from the list of results. In the window that pops up, type DISM.exe /Online /Cleanup-image /Restorehealth and press the Enter key. (Learn to repair a Windows image)

Note: You must have administrator permissions on your device to do this.

Other Common Errors

The following table lists the most common upgrade and installation errors and some things you can try to fix them. If you continue having problems upgrading or installing Windows, contact Microsoft support.

Error	What it means and how to fix it
0xc1900223	This indicates that there was a problem downloading and installing the selected update. Windows Update will try again later and there is nothing you need to do at this time.
0xC1900208 – 0x4000C	This could indicate that an incompatible app installed on your PC is blocking the upgrade process from completing. Check to make

Error	What it means and how to fix it
	sure that any incompatible apps are uninstalled and then try upgrading again.
0xC1900107	A cleanup operation from a previous installation attempt is still pending, and a system restart is required to continue the upgrade. Restart the device and run setup again. If restarting device does not resolve the issue, then use the Disk Cleanup utility and clean up the temporary files and the System files. For more information, see Disk cleanup in Windows.
0x80073712	A file needed by Windows Update is likely damaged or missing. Try repairing your system files: In the search box on the taskbar, type command prompt. Choose Command Prompt from the list of results. In the window that appears, type DISM.exe /Online /Cleanup-image /Restorehealth and press the Enter key.
0xC1900200 - 0x20008 0xC1900202 - 0x20008	This may signify that your PC doesn't meet the minimum requirements to download or install the upgrade to Windows 11. Learn more about the minimum requirements for Windows 11.
0x800F0923	This might indicate that a driver or other software on your PC isn't compatible with the upgrade to Windows 11. For info about how to fix this problem, contact Microsoft support.
0x80200056	This could mean that the upgrade process was interrupted because you accidentally restarted your PC or signed out of your PC. Try upgrading again and make sure your PC is plugged in and stays turned on.
0x800F0922	This error might mean that your PC couldn't connect to the Windows Update servers. If you're using a VPN connection to

Error	What it means and how to fix it
	connect to a work network, disconnect from the network and turn off the VPN software (if applicable) and try upgrading again.
	The error could also mean there isn't enough free space in the System Reserved partition. You might be able to fix this problem by using third-party software to increase the size of the System Reserved partition.
Error: We couldn't complete the updates. Undoing	These are generic errors that might appear any time a Windows update fails. You'll need to determine the specific error code to investigate how to best resolve this problem.
changes. Don't turn off your computer.	You can find the error code for the failed update by viewing your update history. Look for the update that wasn't installed, note the
Error: Failure	error code, and then contact Microsoft support.
configuring Windows Updates. Reverting changes.	To view your update history in Windows 11:
Reverting changes.	Select Start > Settings > Windows Update >
	Update history.
Error: The update isn't applicable to	This error might mean that your PC doesn't have the required updates installed.
your computer.	Check to make sure that all important updates are installed on you
	PC before you try upgrading.
0x80070070 – 0x50011	This likely indicates that your PC doesn't have enough space available to install the upgrade.
	available to install the upgrade.
0x50011	

Error	What it means and how to fix it
0x80300024	The specified disk operation is not supported by the target disk, partition, or volume.
	Make sure your machine meets the minimum requirements to install Windows.
0x80070002 0x20009	The system cannot find the file specified.
	If you have a disk or disks where you are not installing Windows 11 on, remove those disks.
0xC1900101 0x20017	A driver has caused a problem.
0xC1900101 0x30017	Disable or remove all 3rd party antivirus or antispyware from your system. Disconnect all peripheral devices that are connected to the system, except for the mouse, keyboard and display.
	Contact your hardware vendor to obtain updated device drivers.
0x8007042B 0x4000D	Windows Setup terminated unexpectedly due to another process running in the background.
	When you start Windows by using a normal startup, several applications and services start automatically, and then run in the background. These programs include basic system processes, antivirus software, system utility applications, and other software that has been previously installed. These applications and services can cause interference when you attempt to upgrade to the latest version of Windows 11.
	To help you determine whether a background program is interfering with the upgrade, a "clean boot" may be needed. See How to perform a clean boot in Windows.
0x800700B7 0x2000a	Windows Setup terminated unexpectedly due to another process

https://support.microsoft.com/en-us/windows/get-help-with-windows-upgrade-and-installation-errors-ea144c24-513d-a60e-40df-31ff78b3158a

running in the background.