Matrix-Matrix Multiplication – A More Complex Kernel


• We can map every valid data element in a 2D array to a unique thread using threadIdx, blockIdx, blockDim, and gridDim variables:

```
// Calculate the row #
int Row = blockIdx.y*blockDim.y + threadIdx.y;
// Calculate the column #
int Col = blockIdx.x*blockDim.x + threadIdx.x;
```

Matrix-Matrix multiplication between an I x J matrix d_M and a J x K matrix d_N produces an I x K matrix d_P.

Matrix-Matrix Multiplication – A More Complex Kernel

When performing a matrix-matrix multiplication, each element of the product matrix d_P is an inner product of a row of d_M and a column of d_N . The inner product between two vectors is the sum of products of corresponding elements. That is, $d_P_{Row,Col} = \Sigma d_M_{Row,k} * d_N_{k,Col}$, for k = 0, 1, ... Width-1.



- We design a kernel where each thread is responsible for calculating one d_P element.
- The d_P element calculated by a thread is in row blockIdx.y * blockDim.y + threadIdx.y and in column blockIdx.x * blockDim.x + threadIdx.x.

2


Matrix-Matrix Multiplication – three variants

We will write program in CUDA to multiply matrix-A (ha \times wa) and matrix-B (hb \times wb) in 3 variations as follows:


- 1. Each row of resultant matrix to be computed by one thread.
- 2. Each column of resultant matrix to be computed by one thread.
- 3. Each element of resultant matrix to be computed by one thread.

Accessing Row & Col of a matrix

Accessing Row



- Recall that a matrix M is linearized into an equivalent 1D array where the rows of M are placed one after another in the memory space, starting with the 0 row.
- For example, the beginning element of the 1 row is M[1 * Width] because we need to account for all elements of the 0 row.
- In general, the beginning element of the Row row is M[Row * Width].
- Since all elements of a row are placed in consecutive locations, the k element of the Row row is at M[Row * Width + k].



Accessing Col

- The beginning element of the Col column is the Col element of the 0 row, which is M[Col].
- Accessing each additional element in the Col column requires skipping over entire rows. This is because the next element of the same column is actually the same element in the next row.
- Therefore, the k element of the Colcolumn is M[k * Width + Col].

Matrix M

M ₀	M ₁	M ₂	M_3
M ₄	M ₅	M ₆	M ₇
M ₈	M ₉	M ₁₀	M ₁₁

1. Each row of resultant matrix to be computed by one thread

```
multiplyKernel_a<<<1,ha>>>(d_a, d_b, d_c, wa, wb);
 __global___ void multiplyKernel_rowwise(int * a, int * b, int * c, int wa, int wb)
        int ridA = threadIdx.x;
       int sum;
        for(int cidB = 0; cidB < wb; cidB++)
                  sum = 0;
                  for(k = 0; k < wa; k++)
                           sum += (a[ridA * wa + k] * b[k * wb + cidB]);
       c[ridA * wb+ cidB] = sum;
```

2. Each column of resultant matrix to be computed by one thread

```
multiplyKernel_b<<<1, wb>>>(d_a, d_b, d_c, ha,wa);
  _global___ void multiplyKernel_colwise(int * a, int * b, int * c, int ha, int wa)
       int cidB = threadIdx.x;
       int wb = blockDim.x;
       int sum, k;
         for(ridA = 0; ridA < ha; ridA++)
                  sum = 0;
                  for( k=0; k< wa; k++)
                           sum += (a[ridA * wa + k] * b[k * wb + cidB]);
       c[ridA * wb + cidB] =sum;
```

3. Each element of resultant matrix to be computed by one thread

```
multiplyKernel_b<<<(1, 1), (wb,ha)>>>(d_a, d_b, d_c, wa);
  _global___ void multiplyKernel_elementwise(int * a, int * b, int * c, int wa)
       int ridA = threadIdx.y;
       int cidB= threadIdx.x;
       int wb = blockDim.x;
       int sum=0, k;
       for(k = 0; k < wa; k++)
           sum += (a[ridA * wa + k] * b[k * wb + cidB]);
       c[ridA * wb + cidB] =sum;
```

Matrix-Matrix Multiplication—Kernel for thread-to-data mapping

- In the following kernel, we assume **square matrices** having dimension **Width*Width**.
- Throughout the source code, instead of using a numerical value 16 for the block-width, the programmer can use the name BLOCK_WIDTH by defining it. It helps in *autotuning*.

```
global__ void MatrixMulKernel(float* d_M, float* d_N, float* d_P, int Width)
// Calculate the row index of the d P element and d M
                                                                  #define BLOCK WIDTH 16
int Row = blockIdx.y*blockDim.y+threadIdx.y;
// Calculate the column index of d P and d N
                                                                  // Setup the execution configuration
int Col = blockIdx.x*blockDim.x+threadIdx.x;
                                                                  int NumBlocks = Width/BLOCK_WIDTH;
if ((Row < Width) && (Col < Width))
                                                                  if (Width % BLOCK WIDTH)
                                                                             NumBlocks++:
 float Pvalue = 0;
 // each thread computes one element of the block sub-matrix
                                                                  dim3 dimGrid(NumBlocks, NumbBlocks);
        for (int k = 0; k < Width; ++k)
                                                                  dim3 dimBlock(BLOCK WIDTH, BLOCK WIDTH);
           Pvalue += d_M[Row*Width+k]*d_N[k*Width+Col];
                                                                  // Launch the device computation threads
       d_P[Row*Width+Col] = Pvalue;
                                                                   matrixMulKernel<<dimGrid, dimBlock>>(M, N, P, Width);
                                                                                                   Host code
```

Kernel code