Introduction to Frequency Response Methods: Bode Plots

```
In [ ]: #/ default exp frequency response
In [ ]: #/ include: false
        %load ext autoreload
        %autoreload 2
In [ ]: #/ include: false
        from IPython.display import Image
        from IPython.display import HTML
        # For animations
        from matplotlib import animation, rc
In []: |#/ hide
        # equivalent to rcParams['animation.html'] = 'html5'
        rc('animation', html='html5')
In []: #/ export
        import numpy as np
        import matplotlib
        import matplotlib.pyplot as plt
        import pandas as pd
        # import control
In [ ]: #/ include: false
        matplotlib.rc('xtick', labelsize=20)
        matplotlib.rc('ytick', labelsize=20)
        matplotlib.rcParams.update({'font.size': 22})
```

Frequency response


```
Given an LTI system with transfer function: G(s)=C(sI-A)^{-1}B and an input signal: u(t)=Asin(\omega t)
```

Assuming that the system is **asymptotically stable**, it is possible to verify that:

$$y(t) = A|G(j\omega)|sin(\omega t + \angle G(j\omega))$$

This means that the output y(t) converges to a sinusoidal signal that has the **same frequency** of the input, and that has magnitude $A|G(j\omega)|$ and is shifted in phase by $\angle G(j\omega)$.

Note also that this is true independently of the initial state x_0 . In fact, since the system is asymptotically stable, the effect of the initial state on the output will go to zero.




Let's see what this means with our LinearCar:

```
In [ ]: from feedback_control.intro_to_control_theory import *
        # Let's define its initial conditions
In []:
        x_0 = (0,0)
        # no slope terrain
        theta = np.radians(0)
        # Define the car parameters
        m = 1
        alpha = 1
        beta = 1
        qamma = 1
        params = (m, alpha, beta, gamma)
        # Create the car
        car = LinearCar(x_0, params)
        # run it!
        t0, tf, dt = 0, 30, 0.1
        time = np.arange(t0, tf, dt)
        w = 1 \# rad/s
        u = 1*np.sin(w*time) # SINUSOIDAL INPUT
        position = []
        velocity = []
        time = []
        for i, t in enumerate(np.arange(t0, tf, dt)):
            car.step(dt, u[i], theta)
            x_i, y_i, v = car.sensor_i()
            position.append((x_i,y_i)), velocity.append(v)
            time.append(t)
```

And now we plot it:

```
In [ ]: # First set up the figure, the axis, and the plot element we want to animate
        fig, ax = plt.subplots();
        ax.set_xlim((min(position)[0], max(position)[0]));
        ax.set ylim((-50, 10));
        line, = ax.plot([], [], lw=4);
        x range = np.linspace(int(position[0][0]), int(position[-1][0]), num=20)
        # animation function. This is called sequentially
        def animate(i):
            x_{min}, x_{max} = position[max(0,i-2)][0], position[i][0]
            y_{min}, y_{max} = position[max(0,i-2)][1], position[i][1]
            line.set_data([x_min, x_max], [y_min, y_max])
            return (line,)
        # call the animator. blit=True means only re-draw the parts that have changed.
        anim = animation.FuncAnimation(fig, animate,
                                        frames=len(time), interval=40, blit=True,
                                        repeat delay=10000, repeat=True);
        plt.close()
        HTML(anim.to_html5_video())
```

Out[]:




And if we plot the speed with respect to the input signal:

```
In []: fig = plt.figure(figsize=(10,5))

plt.plot(u, linewidth=4)
   plt.plot(velocity, linewidth=4)
   fig.legend(['input: u', 'output: v'], loc='upper left')

plt.title('Frequency response')
   plt.xlabel('time (s)')
   plt.grid()
```



Comments

Given an LTI system with transfer function: $G(s) = C(sI-A)^{-1}B$

and an input signal: $u(t) = Asin(\omega t)$

Assuming that the system is asymptotically stable, it is possible to verify that:

$$y(t) = A|G(j\omega)|sin(\omega t + \angle G(j\omega))$$

• The complex function $G(j\omega)$ is called frequency response (or harmonic response) of the system

If we know magnitude and phase of $G(j\omega)$, as ω varies, then effectively we know how the system behaves for all sinusoidal inputs with different driving frequencies.

- It is possible to experimentally determine $G(j\omega)$ which means that we can also reconstruct the transfer function
- $G(j\omega)$ can be represented graphically through Magnitude and Phase diagrams (each one is a Real Function of the real variable ω):

$$G(j\omega) = |G(j\omega)|e^{j\angle G(j\omega)}$$

- This makes it possible to analyse the gain and the phase shift across the full frequency spectrum
- Finally, as a side observation, note that if we have a sinusoidal input $sin(\omega_0 t)$, the output can be zero only if $G(j\omega_0)=0$. This happens if the T.F. G(s) has a pair of imaginary zeros in $j\omega_0$.


Note:

• The time of the transient before the output of the system converges towards $y(t) = A|G(j\omega)|sin(\omega t + \angle G(j\omega))$ depends on dynamics of the system and can be evaluated using the settling time t_s .

Complex numbers and their representation through magnitude and phase

Complex Numbers are a very popular and frequently used aspect of Mathematics. Composed of a real part and an imaginary part, they are written in the form $\mathbf{x} + \mathbf{i}\mathbf{y}$.


- **x** denotes the real part and **iy** denotes the imaginary part.
- Complex numbers can be represented on an **Argand Diagram**.
- ullet An **Argand Diagram** is similar to the **Cartesian Coordinate System** except that the Real axis and Imaginary axis replace the X and Y axis respectively which you would usually expect see on the Cartesian system. For example:



The complex number $\mathbf{z} = \mathbf{x} + \mathbf{i}\mathbf{y}$ can hence be also represented as:

$$|\mathbf{z}|\mathbf{e}^{\mathbf{j}\angle\mathbf{z}}$$

- The Modulus of the Complex Number gives the straight line distance from the origin to the point: $|\mathbf{z}| = \sqrt{\mathbf{x}^2 + \mathbf{y}^2}$
- The Argument gives the angle between the line representing the complex number and the positive real axis: $\angle z = \arctan \frac{y}{x}$



- Sinusoids can be represented as complex numbers called *phasors*.
- The magnitude of the complex number is the amplitude of the sinusoid,
- The angle of the complex number is the phase angle of the sinusoid.

Thus:

$$M_1 cos(\omega t + \phi_1)$$

Can be represented as:


$$M_1 \angle \phi_1$$

where the frequency ω is implicit.

Frequency Response and Bode Plots

The objective is that of analysing the gain and the phase shift across the full frequency spectrum.

Let's now suppose that we have one simple system:



When we have $u(t) = \sin(0.5t)$, the output of this system is:

$$y(t) = 2\sin(0.5t) + \int \sin(0.5t)dt = 2\sin(0.5t) - \frac{1}{0.5}\cos(0.5t)$$

Since (Trigonometry Identity):

$$a\sin x + b\cos x = \sqrt{a^2 + b^2}\sin(x + \phi)$$
 , where $\phi = an^{-1}rac{b}{a}$

We can then write:

$$y(t) = 2\sin(0.5t) + \int \sin(0.5t)dt = 2\sin(0.5t) - 2\cos(0.5t) = \sqrt{8}\sin(0.5t + \tan^{-1}(-1)) pprox 2.83\sin(0.5t)$$

This gives the output for one frequency ω .

More often though we are going to be interested in a range of frenquecies, and to represent the gain and phase shift across the frequency spectrum we can use **Bode Plots**

• They plot frequency response information to be displayed graphically on two diagrams: gain and phase (plotted against frequency on a logarithmic horizontal axis)

Note

- To plot the gain on a Bode diagram we do not plot the gain directly
- We first convert the gain into Power, and then we represent the gain in dB (a logarithmic unit)
- ullet To convert the amplitude to decibel: $20\log_{10}rac{A}{A_0}$
 - This comes from quantifying loss in audio levels through telephone circuits units of measurement that could cover a large range of audio power differences. Since the ear responds to sound pressure logarithmically using a log scale corresponds to the way humans perceive sound.
 - $1TU = 10 \log_{10} \Delta Power Loss$
 - ullet $1 \mathrm{TU}$ was the smallest power attenuation detectable by the average listener
 - $1 \mathrm{TU}$ was later renamed after Alexander Bell as decibel (1/10 bel): $1 \mathrm{TU} = \frac{1}{10} \mathrm{bel} = 1 \mathrm{dB}$
 - Since $Power \propto Amplitude^2$ we can write the equation with respect to amplitude:
 - $\circ 1 dB = 10 \log_{10} Amplitude^2 = 20 \log_{10} Amplitude$ (properties of logarithms)


In our case:

- $y(t) = 2.83\sin(0.5t 0.785)$
- Gain: $20\log_{10}(2.83) \approx 9 dB$
- Phase: -0.785 rad = -45 deg

```
In []: fig, axs = plt.subplots(1, 2, figsize=(10,5));

axs[0].plot(0.5, 20*np.log10(2.83), marker='.', markersize=15)
axs[0].set_xlabel('Frequency (rad/s)')
axs[0].set_ylabel('Gain (dB)');
axs[0].grid()

axs[1].plot(0.5, np.degrees(-0.785), marker='.', markersize=15)
axs[1].set_xlabel('Frequency (rad/s)')
axs[1].set_ylabel('Phase (deg)');
axs[1].grid()
```



- This is the frequency response for a single sine wave.
- We are interested in plotting the gain and phase across the entire frequency spectrum

We can manually calculate the frequency response for all possible values of ω :

$$y_t = \sqrt{2^2 + rac{1}{w}^2} sin(wt + an^{-1}ig(rac{-1/w}{2}ig))$$

And we can plot for a finite number of values of ω

```
In []: fig, axs = plt.subplots(1, 2, figsize=(20,5));
        ws = np \cdot logspace(-3, 3, 100) # logspace sets the exponents
        gain, phase = [], []
        for w in ws:
             \# y t = np.sqrt(2**2+1/w**2) * sin(w*t + np.atan2(-1/w, 2))
             gain.append(np.sqrt(2**2 + (1/w)**2))
             phase.append(np.arctan2(-1/w, 2))
        # Gain diagram
        axs[0].plot(ws, 20*np.log10(gain), linewidth=3)
        axs[0].plot(0.5, 20*np.log10(2.83), marker='.', markersize=15, color='red')
        axs[0].set_xscale('log')
        axs[0].grid('log')
        axs[0].set xlabel('Frequency (rad/s)')
        axs[0].set ylabel('Gain (dB)');
        axs[0].text(10**3, 20*np.log10(2), '6dB')
        # Phase diagram
        axs[1].plot(ws, np.degrees(phase), linewidth=3)
        axs[1].plot(0.5, np.degrees(-0.785), marker='.', markersize=15, color='red')
        axs[1].set xscale('log')
        axs[1].grid('log')
        axs[1].set xlabel('Frequency (rad/s)')
        axs[1].set ylabel('Phase (deg)');
          60
                                                             0
          50
                                                           -20
                                                        Phase (deg)
        Gain (dB)
                                                           -40
                                                           -60
          20
                                                          -80
          10
                                                    6dB
```

• For this simple example, solving the response to the sine wave input is quite straightforward. But what about a more general case?

 10^{3}

 10^{2}

 10^{-3}

 10^{-2}

 10^{-1}

10°

Frequency (rad/s)

 10^{3}

• We can obtain the result using directly the transfer function.

10°


Frequency (rad/s)

 10^{-1}

 10^{-3}

 10^{-2}

The system we had was:



This can be written as:

$$G(s)=\left(2+rac{1}{s}
ight)=rac{2s+1}{s}$$

which means:

$$y(t) = \frac{2s+1}{s}u(t)$$

Recall that: $s=\sigma+j\omega$ (complex variable)

- When we calculate the frequency response we are interested in the state state response, once all the transients have died out (or in other words, when $\sigma = 0$).
- ullet So for steady state: $s=j\omega$

When can then calculate **steady state gains and phases** directly substituting in the transfer functions $s=j\omega$:

$$\left.rac{2s+1}{s}
ight|_{s=j\omega}
ightarrowrac{2j\omega+1}{j\omega}=2-rac{1}{\omega}j$$

We can then plot these real and imaginary components on the Real-Imaginary axis, and we can calculate gain and phase geometrically from these plots.


And for $\omega=0.5$

```
In []: fig = plt.figure()

w = 0.5

def plot_imre(w, display_text=1):
    plt.plot([-3, 6], [0, 0], color='black', linestyle='---') # real axis
    plt.plot([0, 2], [0, -1/w], color='red') # vector
    plt.plot(0, 0, marker='.', markersize=12, color='black');
    plt.plot(2, -1/w, marker='.', markersize=12, color='red');
    if display_text: plt.text(2+0.1, -1/w+0.1, '2-{:.1f}j'.format(1/w), size=16) # add a te

plot_imre(w)
    plt.ylabel('Real')
    plt.ylabel('Imaginary')
    plt.axis([-3, 3, -3, 1])
    plt.grid()
```



- ullet The length of the line is the **Gain** of the system: $l=\sqrt{real^2+imag^2}$
- The angle between the line and the positive real line is the **Phase**: $\angle = atan2(imag, real)$

And if we speed across the frequencies, from 0 to \inf , we can obtain a visual understanding of what the gain and phase are doing for this system:

- $w \to 0$, \Rightarrow , $imag \to inf$
- $ullet \ w
 ightarrow \inf$, \Rightarrow , imag
 ightarrow 0


And we can plot a few examples:

```
In []: fig = plt.figure()
    ws = np.logspace(0.001, 10, 100)

ws = [0.01, 0.1, 1]
    for w in ws:
        plot_imre(w)

plt.xlabel('Real')
    plt.ylabel('Imaginary')
    plt.axis([-3, 6, -120, 10])
    plt.grid()

# add a note on the plot to show the direction of w
    plt.arrow(5, -40, 0, 30, head_width=0.4, head_length=10, length_includes_head=True, color='
    plt.arrow(5, -70, 0, -30, head_width=0.4, head_length=10, length_includes_head=True, color='
    plt.text(4.5, -8, '$0$ for $\omega=\infty$', fontsize=14)
    plt.text(4.5, -110, '$\infty$ for $\omega=0$', fontsize=14);
```



The real part never changes.

Gain

- As ω decreases, the Gain increases (inf for $\omega = 0$)
- As ω increases, the Gain decreases (2 for $\omega = \inf$)

Phase

- As ω decreases, the Phase increases (-90^o for $\omega=0$)
- As ω increases, the Phase decreases (0 for $\omega=\inf$)

Let's be more formal

- ullet The transfer function of linear systems are polynomial fractions in s
- It is always possible to factor polynomials in terms of their roots (zeros and poles)
- Each polynomial is the product of first-order or second-order (potentially with multiplicity > 1)
- To build the frequency response of the system is useful to have simple rules to represent each term
- We can leverage the properties of the logarithms: the logarithm of a product is equal to a sum of logarithms:
 - $\log(AB) = \log(A) + \log(B)$
 - $\log(A/B) = \log(A) \log(B)$
 - $\bullet \ \log(y^x) = x \log(y)$

Magnitude and Phase

and:

$$|G(jw)| = rac{|j\omega-z_1||j\omega-z_2|\dots}{|j\omega-p_1||j\omega-p_2|\dots} \ egin{aligned} igl G(jw)| = + igl (j\omega-z_1) + igl (j\omega-z_2) + \dots - igl (j\omega-p_1) - igl (j\omega-p_2) - \dots \end{aligned}$$

Bode Amplitude Plot

- In the amplitude plot, it is convenient to report the value of the magnitude in decibel or dB.
- By convention, the dB value of a positive quantity x is: $20 \log_{10}(x)$.
- ullet This means: $|G(j\omega)|_{dB}=20log|G(j\omega)|$
- Note that when:

$$\qquad \left| \left. \left| G(j\omega) \right|_{dB} > 0 \rightarrow \left| G(j\omega) \right| > 1 \right.$$

•
$$|G(j\omega)|_{dB} < 0 \rightarrow |G(j\omega)| < 1$$

$$ullet \left| G(j\omega)
ight|_{dB} = 0
ightarrow \left| G(j\omega)
ight| = 1$$

When we use dB things become simpler:

$$egin{align*} |G(jw)| &= rac{|j\omega - z_1||j\omega - z_2|...}{|j\omega - p_1||j\omega - p_2|...} \Rightarrow \ &|G(j\omega)|_{dB} = 20 \log |G(j\omega)| = 20 \log (|j\omega - z_1|) + 20 \log (|j\omega - z_2|) + \ldots \ &-20 \log (|j\omega - p_1|) - 20 \log (|j\omega - p_2|) \ldots \end{aligned}$$


- It is convenient to use a logarithmic scale for the *w*-axis.
- Logarithmic scales are useful when plotting functions that vary over many orders of magnitude.
- One term we will use in our discussion of frequency response plots is "decade". A decade change in frequency is a factor of ten. So, for example, 1 kHz is a decade above 100 Hz and a decade below 10 kHz.

Sketching Bode Plots

- Being able to quickly draw Bode plots is important
 - They provide an intuitive understanding how poles and zeros affect the frequency response
 - Make it possible to estimate the transfer function looking at the frequency response (e.g. estimate
 of the transfer function from the output of a frequency sweep that we are providing to the system)


Recall

- ullet Given a transfer function G(s) we can obtain the (steady state) frequency response setting $s=j\omega o G(j\omega)$
- Remember also that $G(j\omega) = \mathrm{real} + \mathrm{imag} j$
- If we plot it on the Real-Imag diagram:



- ullet Gain: $\sqrt{\mathrm{real}^2 + \mathrm{img}^2} = |G(j\omega)|$
- ullet Phase: $atan2(\mathrm{img,real}) = arg(G(j\omega)) = \angle G(j\omega)$

• The sign of the phase is determined based on which side of the real line it appears




Representing the simplest transfer function on a Bode Plot

- G(s) = K
- ullet where $K\in R$ can be positive of negative

We apply the definition

- ullet Gain = $|G(j\omega)|=|K|={
 m positive}\ {
 m K}$
- Phase = atan2(img, real) = atan2(0, K)
 - The img part is zero in our case

If we plot this on the real-img axis, all values would lie on the real axis (imaginary component is zero)



- The gain is always K (distance from the origin)
- ullet K can be positive or negative,
 - For K > 0, Phase = 0,
 - lacktriangledown For K<0, Phase = $180^o=-180^o$, but traditionally use -180^o
 - \circ if we use atan2 we already keep track of the sign.


Represent on a Bode Plot


Gain

- ullet We need to remember to convert the gain to dB: $|H(j\omega)|=20\log_{10}|K|$
- Then it is just a constant for all frequencies, so it is a straight line

Phase

- Constant for all frequencies
- K>0, Phase = 0^o
- K < 0, Phase = -180°






What is happening in time?

The system that we are considering is:

$$\sin(\omega t)$$
 \longrightarrow $K \sin(\omega t)$

- Input is $\sin(\omega t)$
- Output is $K\sin(\omega t)$, which is a sinusoid with the same frequency, but scaled by K (and shifted in phase if K<0 by -180 deg).



Bode Plot of the Integrator

- Consider a system that has a single pole at the origin.
- ullet The steady-state frequency-response is determined by letting $s o j\omega$:

$$G(s) = rac{1}{s} \Rightarrow G(j\omega) = rac{1}{j\omega} = -rac{1}{w}j$$

Side note

$$j = \sqrt{-1}$$

Therefore:


$$\frac{1}{j} = \frac{1}{\sqrt{-1}} \frac{\sqrt{-1}}{\sqrt{-1}} = \frac{\sqrt{-1}}{-1} = -\sqrt{-1} = -j$$

Given
$$G(j\omega) = -\frac{1}{w}j$$

- Real component is 0
- Imaginary component is $-\frac{1}{w}$
- Gain = $|G(j\omega)| = \left| -\frac{1}{w}j \right| = \frac{1}{\omega}$:

ullet Phase = $rg G(j\omega) = rg ig(-rac{1}{w}, 0 ig) = -90^o$

We can see this graphically on the real-img axis:



Another way to look at this is through a block diagram

$$\sin(\omega t)$$
 \longrightarrow $\int \sin(\omega t) = -\frac{1}{\omega}\cos(\omega t)$


• And if we plot it, we see that the resulting signal has a -90 deg phase shift:

```
In []: fig = plt.figure(figsize=(10,5))

t = np.linspace(0, 30, 50)
w = 0.5

plt.plot(t, np.sin(w*t), color = 'green', label='sin(wt)', linewidth=4)
plt.plot(t, -1/w*np.cos(w*t), color = 'blue', label='-1/w cos(wt)', linewidth=4)


rc('font', **{'size':22})
plt.grid()
plt.legend(loc="lower right", bbox_to_anchor=(1.4,0.7));
```



Let's se what the Bode plot looks like:

• Gain =
$$|G(j\omega)|= \left|-\frac{1}{w}j\right|=\frac{1}{\omega}$$
 :

- lacksquare when $\omega=1~{
 m rad/s}$, then gain = 1, $ightarrow20\log_{10}1=0{
 m dB}$
- lacktriangledown when $\omega=10~\mathrm{rad/s}$, then gain = 1/10, $ightarrow20\log_{10}1=-20\mathrm{dB}$
- $\quad \left| \left. G(j\omega) \right|_{dB} = 20 \log \left| \frac{1}{j\omega} \right| = -20 \log(\omega)$
- Given that we are using a logarithmic scale on both axis, this corresponds to a straight line with a -20dB slope every "decade".
- ullet Phase = $rg\left(-rac{1}{w},0
 ight)=-90^o$ at all frequencies




We can also use the Python Control Systems Library for this.

The Python Control Systems Library is a Python module that implements basic operations for analysis and design of feedback control systems.


```
In []: import control

In []: fig = plt.figure(figsize=(15,10))
    # integrator: 1/s = 1/(s+0)
    num = [1]
    den = [1, 0]
    control.bode_plot(control.tf(num, den), dB=True, omega_limits=(0.1, 100));
```



What about a zero?

- G(s) = s
- It is easy to calculate this from what we know already.
- ullet For example we can use the property of logarithms to say: $G(s)=s=rac{1}{1/s}\Rightarrow 1-rac{1}{s}$
- So the gain of a zero is simply the negative of the gain of a pole (reflection about the real axis)
- And the phase of a zero is +90 deg



Frequency Response of Simple Poles and Zeros

Transfer function with a single real pole

• Given a transfer function G(S), re-write the transfer function in the Bode form:

$$\frac{1}{1+\frac{s}{w_0}}$$


■ ex

$$\circ~G(s)=rac{1}{s+1} \Rightarrow rac{1}{1+rac{s}{w_0}}$$

- \circ we call w_0 "break frequency" or "corner frequency"
- Sometime you also see it written as:

$$\circ~G(s)=rac{w_0}{s+w_0}=rac{1}{1+ au s}$$

- $\circ \;\;$ where $au = rac{1}{w_0}$ is called *Time constant*
- All these representations are equivalent
- To be clear:
 - A real pole has an effect on the frequency response



Now, given a transfer function with a single real pole:

$$G(s) = rac{1}{1 + rac{s}{w_0}} \stackrel{Set \ s = j\omega}{\longrightarrow} rac{1}{1 + rac{j\omega}{w_0}}$$

We are trying to separate the real part and the imaginary part:

$$rac{1}{1+rac{j\omega}{w_0}} = rac{1}{1+jrac{\omega}{w_0}}rac{1-jrac{\omega}{w_0}}{1-jrac{\omega}{w_0}} = rac{1-jrac{\omega}{w_0}}{1+rac{\omega^2}{w_0^2}}$$

_Note: $1-jrac{\omega}{w_0}$ is the complex conjugate of $1+jrac{\omega}{w_0}$ _

- Real part = $\frac{1}{1 + \frac{\omega^2}{\omega_0^2}}$
- Imaginary part = $\frac{-\frac{\omega}{\omega_0}}{1 + \frac{\omega^2}{\omega_0^2}}$

And now we can solve for the gain and phase as we did before:

• Gain:


$$20\log_{10}\left|H(j\omega)
ight| = \sqrt{real^2 + img^2} = \sqrt{rac{1}{1 + rac{\omega^2}{\omega_0^2}}} \stackrel{in ext{ dB}}{\longrightarrow} -20\log_{10}\left(\sqrt{1 + rac{\omega^2}{\omega_0^2}}
ight)$$

• Phase:


$$\arctan \frac{\mathrm{img}}{\mathrm{real}} = \arctan \frac{-w}{w_0}$$

And now we can plot them:


- ullet case 1: $w \ll w_0
 ightarrow rac{\omega^2}{\omega_0^2}
 ightarrow 0$,
 - $\quad \blacksquare \quad \mathsf{Gain:} -20\log_{10}1 = 0 \; \mathrm{dB}$
 - Phase: $\arctan(0) = 0$ degrees



ullet case 2: $w=w_0 o rac{\omega^2}{\omega_0^2}=1$, ullet Gain: $-20\log_{10}\sqrt{2}=-3~\mathrm{dB}$ ullet Phase: $\arctan(-1)=-45~\mathrm{degrees}$




- case 3: $w\gg w_0$,
 - The term $\frac{\omega^2}{\omega_o^2}$ dominates the gain equation
 - \bullet Gain: $-20\log_{10}\frac{\omega}{\omega_o}$
 - \circ Every time ω gets 10 times bigger, there is a drop in gain of -20 dB
 - $\circ~-20~\mathrm{dB/decade}$ slope and intercepts 0 at ω_0
 - Phase: $\arctan(-\frac{\omega}{\omega_o}) = \arctan(-\inf) = -90$ degrees




• This is called the asymptotic Bode plot, which is an approximation of the actual plot.

What does the actual Bode plot look like?



And for this reason, sometimes we use a different approximation of the phase:



Transfer function with a single real zero

- G(s) = s + z
- It is easy from what we know already
- One way to do it is to reshape it as:

$$G(s) = s + z = rac{1}{rac{1}{s+z}} = rac{1}{rac{1}{1+rac{s}{w_0}}} = 1 + rac{s}{w_0}$$

- And now we can simply use the property of the logarithm:
 - real zero is real pole when plotted on a log-log Bode plot.
- Gain slops up at 20 dB/decade (at w_0)
- Phase goes from 0 to 90 degrees.

Summary

- Write the transfer function as: $\frac{1}{1+\frac{s}{w_0}}$ (pole) or as $1+\frac{s}{w_0}$ (zero)
- Find the break frequency w_0 on the log-log Bode plot
- Gain: find and draw the two asymptotes (0 dB until w_0 , then -20dB/decade (pole) or 20dB/decade (zero))
- ullet Phase: draw the two asymptotes (0 until w_0 , then -90 deg (pole), 90 deg (zero)
 - Optional: use the better approximation

One more comment:

ullet If you have a $G(s)=rac{1}{s+4}$ you can always refactor it to the form we would like:

$$G(s) = rac{1}{s+4} = rac{1}{4} rac{1}{1 + rac{s}{4}}$$

ullet $rac{1}{4}$ is the gain, and the break frequency $w_0=4$ rad/s

Transfer function with a pair of complex poles / zeros

Let's now consider a transfer function of the form:

$$H(s)=rac{\omega_o^2}{s^2+2\xi\omega_o s+\omega_o^2}$$

The roots of the denominator (the poles) are:

$$s=-\xi\omega_o\pm\omega_o\sqrt{\xi^2-1}$$

- ullet w_o is the break frequency
- ξ dumping ratio
- ullet if $\xi>1$, the second-order response has two simple real poles and we know how to deal with that alreadv.
- if $0<\xi<1$, we have stable complex-conjugatee pole pairs.

First, like we did before, we want to manipulate the form to bring it to the Bode form:

$$H(s) = rac{1}{rac{s^2}{2} + 2 \xi rac{\omega_o}{arphi_o^2} s + rac{\omega_o^2}{arphi_o^2}} = rac{1}{rac{s^2}{\omega_o^2} + 2 rac{\xi}{\omega_o} s + 1}$$

Second, we substitute $s=j\omega$ and solve for the real and img parts:

$$H(j\omega) = rac{1}{-rac{\omega^2}{\omega_o^2} + 2j \xi rac{\omega}{\omega_o} + 1}$$


• Real =
$$\frac{1 - \left(\frac{w}{w_0}\right)^2}{\left[1 - \left(\frac{w}{w_0}\right)^2\right]^2 + \left[2\xi \frac{w}{w_0}\right]^2}$$

• Imaginary =
$$\frac{-2\xi \frac{w}{w_0}}{\left[1 - \left(\frac{w}{w_0}\right)^2\right]^2 + \left[2\xi \frac{w}{w_0}\right]^2}j$$


We can use these to estimate the Gain and Phase.

- Case 1: $w \ll w_0$,

 - $\frac{w}{w_0}$ is very small \Rightarrow Real = 1, Img = 0 $|H(j\omega)|_{dB} = 20\log(1) = 0$ dB $\arg H(j\omega) = \arctan \frac{0}{1} = 0$ deg



- Case 2: $w\gg w_0$,
 - $1 \left(\frac{w}{w_0}\right)^2 \approx -\left(\frac{w}{w_0}\right)^2 \Rightarrow \text{Real} = -\left(\frac{w}{w_0}\right)^{-2}, \text{ Img} = -2\xi\left(\frac{w}{w_0}\right)^{-3}$
 - ullet $\left|H(j\omega)
 ight|_{dB}=20\log\left(rac{w}{w_0}
 ight)^{-2}=-40\log(rac{w}{w_0})$ dB
 - Note that the real component dominates (there is a square) over the imaginary component
 - o -40 dB/decade drop in gain
 - $= \arg H(j\omega) = \arctan 2\big(-2\xi\big(\tfrac{w}{w_0}\big)^{-3}, -\big(\tfrac{w}{w_0}\big)^{-2}\big) = -180\deg$
 - This is because both real and imaginary components are negative and the imaginary component goes to zero faster than the real component.



-Case 3: $w = w_0$,

• $\frac{w}{w_0}=1$, Real = 0, Img = $-\frac{1}{2\xi}$

ullet $|H(j\omega)|_{dB}=20\log_{10}(rac{1}{2\xi})$ dB = $-20\log_{10}(2\xi)$ dB

• Strongly depends on the parameter ξ , the _damping ratio.

lacksquare When $\xi=0.5
ightarrow -20 \log_{10}(1)=0$ dB (no peak)

ullet When $\xi>0.5$ then the peak goes slightly down at w_0

 \bullet When $\xi < 0.5$ peak of magnitude $-20\log_{10}(2\xi)$


• When $\xi=0$ (no dumping) peak goes to \inf

■ -40 dB/decade drop in gain


• $\arg H(j\omega) = \arctan(\inf) = -90$ deg (remember the quadrant)

 $\,\blacksquare\,$ The slope of the line however changes as a function of ξ

In case $\xi = 0.3$:




How does the actual plot look like?



• Remember: - This is still an approximation!

To do a better approximation of the phase, sometime we identify $w_0^-=\frac{w_0}{5^\xi}, w_0^+=w_0 5^\xi$ and we connect them with a straight line.

Here is a more accurate representation of the Bode plots for a pair of complex poles and how their response changes with ξ .



Transfer function with a pair of complex zeros

- The frequency response of complex zeros can be obtained from what we know already
- Reflection of the response of a pole about the horizontal axis.

Final comments

- Drawing Body plots is easy once we understand the key rules
- Makes it possible to understand how adding poles/zeros changes the frequency response of the system
- Really useful when desigining controllers or filters

OK, really the final comment - Bode plot of a delay

The transfer function of a delay is $G(s) = e^{-s\tau}$.

The frequency response $G(j\omega)=1e^{-j\omega au}$ is already a phasor!

$$|e^{-j\omega au}|=1$$

$$\angle e^{-j\omega\tau} = -\omega\tau$$

• A delay τ introduces a phase shift proportional to the delay and to the frequency.

Exercises

Exercise 1

Draw the Bode plot of the system:


$$G(s) = rac{10^3(s+0.1)}{s(s+1)^2}$$

- zeros: $(s+0.1)=0 \Rightarrow s=-0.1$
- ullet poles: $s(s+1)^2=0\Rightarrow s=0, s=-1$ (with multiplicity 2)


Write the frequency response, setting $s=j\omega$ as:

$$G(j\omega) = rac{10^3 0.1 ig(1 + rac{j\omega}{0.1}ig)}{j\omega(1 + j\omega)^2}$$


- ullet Given that we have a pole at the origin we know that the plot starts with a slope of $-20 {
 m dB/decade}$, and passing through $w=1 {
 m rad/s}$
- ullet Constant Gain: $K=0.1\cdot 10^3\Rightarrow 20\log_{10}(10^2)=40$




\bullet Zero in s=0.1



ullet Poles in s=1 with multiplicity 2




• Summing all contribution together:



• And we can refine our plot a bit:

100



And finally we can ask the Python Control library to plot it for us:

```
In []: fig, axs = plt.subplots(2, 1, figsize=(15,10))
   num = [10**3, 10**3*0.1]
   den = [1, 2, 1, 0]
   control.bode_plot(control.tf(num, den), dB=True, omega_limits=(0.001, 1000));
```

Exercise 2

Draw the Bode plot of the system:


$$G(s) = rac{10(s+1)}{(s+0.1)(s-1)}$$

- zeros: $(s + 0.1) = 0 \Rightarrow s = -1$
- poles: $(s+0.1)(s-1)=0 \Rightarrow s=0.1, s=1$

Write the frequency response, setting $s=j\omega$ as:


$$G(j\omega) = rac{10ig(1+rac{j\omega}{1}ig)\cdot 10\cdot -1}{ig(1+rac{j\omega}{0.1}ig)ig(1+rac{j\omega}{-1}ig)}$$

- ullet Constant Gain: $K=-1\cdot 10\cdot 10\Rightarrow 20\log_{10}(10^2)=40$
- We do not have any poles/zeros at the origin, the diagram starts constant.
- ullet A pole in s=-0.1, a pole in s=1 and a zero in s=-1



• Summing all contribution together:

100



Let's verify that it is correct:

```
In []: fig, axs = plt.subplots(2, 1, figsize=(15,10))
   num = [10, 10]
   den = [1, -0.9, -0.1]
   control.bode_plot(control.tf(num, den), dB=True, omega_limits=(0.001, 1000));
```

Final notes on Bode Plots

- The **frequency response** interpretation of a Bode Plot only holds for stable (or marginally stable) systems
- If we apply a sinusoidal input to an unstable system, then the output is not sinuisoidal
- Under additional technical hypotesis we can still recover some of the results discussed before, but we will not tackle this here
- Note that we can still draw Bode plots for unstable systems

Other important properties of the frequency response are:

- ullet the resonant peak M_r , the largest value of the frequency response,
- ullet and the peak frequency ω_{mr} , the frequency where the maximum occurs,
- Bandwidth

Bandwidth

- Definitions may very with application
- For us: Bandwidth (B) is the range of frequencies for which gain is significant
- We need to define what significant means:
 - typically, gain greater than 1/sqrt(2) or a -3 dB on the Bode Plot, relative to low frequency gain i.e. 3dB drop off w.r.t. low frequency (or could be absolute)
 - sometimes also gain greater than 0 dB line is used.
- Often the bandwidth of interest is for the closed-loop system, but there might be little difference
- Bandwidth is an indication of the speed of response of the system: higher bandwidth implies faster transient response (i.e. can track higher frequencies)

Finding the –3 dB bandwidth of an arbitrary system can be a difficult problem in general. Consider, for example, the standard recipe for computing bandwidth:

- Derive the input-output transfer function
- Set $s = j\omega$;
- Find the magnitude of the resulting expression;
- Set the magnitude = $1/\sqrt{2}$ of the "midband" value (or half of the power); and
- Solve for ω_b

Given a transfer function:

$$G(s) = rac{N(s)}{D(s)}$$

we obtain the frequence response as:

$$G(j\omega) = rac{N(j\omega)}{D(j\omega)}$$

If we take magnitude-squared of the frequency response (power):

$$\left|G(j\omega)
ight|^2 = \left|rac{N(j\omega)}{D(j\omega)}
ight|^2$$

we can calculate the -3dB frequency as the frequency which results in half of the power:

$$\left|G(j\omega_b)\right|^2 = \frac{1}{2} \left|G(j0)\right|^2$$

or


$$\left|rac{N(j\omega_b)}{D(j\omega_b)}
ight|^2 = rac{1}{2} \left|rac{N(j0)}{D(j0)}
ight|^2$$

and we can now solve for ω_b to find the bandwidth.

- If the dominant pole approximation holds, the Bandwidth is approximated by the can be frequency of the dominant pole
- We can read the bandwidth visually inspecting the Bode plot.

Definition 1: Gain greater than -3dB

```
In []: fig, axs = plt.subplots(2, 1, figsize=(15,10))
          num = [10, 10]
          den = [1, -0.9, -0.1]
          control.bode_plot(control.tf(num, den), dB=True, omega_limits=(0.001, 1000));
          ax1,ax2 = plt.gcf().axes
                                            # get subplot axes
          plt.sca(ax1)
                                            # magnitude plot
          plt.plot(plt.xlim(),[-3, -3],'r--')
          plt.plot([13.5, 13.5],plt.ylim(),'r--')
          plt.text(15, 2, "0 dB line");
                40
           Magnitude (dB)
                20
                                                                                   0 dB line
                 0
               -20
              -40
                         10<sup>-3</sup>
                                      10-2
                                                    10^{-1}
                                                                  10°
                                                                               10<sup>1</sup>
                                                                                             10<sup>2</sup>
                                                                                                          10<sup>3</sup>
              -90
         Phase (deg)
              -135
```



10-2

 10^{-1}

10°

Frequency (rad/sec)

10²

 10^{1}


10³


Definition 2: Gain greater than 0 dB

10⁻³

-180

-225





0 dB Bandwidth (range of freq. for which gain > 0): 10 rad/s


• Not too much difference

Definition 3: -3dB relative to steady state

```
In []: fig, axs = plt.subplots(2, 1, figsize=(15,10))
    num = [10, 10]
    den = [1, -0.9, -0.1]
    control.bode_plot(control.tf(num, den), dB=True, omega_limits=(0.001, 1000));

ax1,ax2 = plt.gcf().axes  # get subplot axes

plt.sca(ax1)  # magnitude plot
    plt.plot(plt.xlim(),[40-3, 40-3],'r--')
    plt.plot([0.1, 0.1],plt.ylim(),'r--');
```




-3dB Bandwidth relative to low frequency, is B = [0, 0.1] rad/s

A different example

```
In []: fig, axs = plt.subplots(2, 1, figsize=(15,10))
    num = [2.5, 0]
    den = [4e-5, 0.6, 2554, 250000]
    control.bode_plot(control.tf(num, den), dB=True, omega_limits=(1, 100000));

ax1,ax2 = plt.gcf().axes  # get subplot axes

plt.sca(ax1)  # magnitude plot
    plt.plot(plt.xlim(),[-60, -60],'r--')
    plt.plot([100, 100],plt.ylim(),'r--')
    plt.plot([3000, 3000],plt.ylim(),'r--')
    plt.text(150, -57, "Significant gain");
```



- $\bullet \ \ {\rm The \ bandwidth} \ B=[100,3000] \ {\rm rad/s}$
- Range of frequency where the gain is significant
- Usually easy to visually identify it

- ullet Given a bandwidth $B=[0,\omega_b]$
- If the slope of the Gain diagram is -20 dB/decade beyond frequency ω_b , then the system is behaving like a first-order system, with a pole in ω_b .
- ullet This means that the system transient response is characterised by a time constant $au=rac{1}{\omega h}$
- The system is hence the faster, the larger its bandwidth is
- The bandwidth is hence a good indicator of the velocity of the system

Bandwidth and system response


• For first order systems the relationship between badnwidth and settling time is

$$T_s = rac{1}{w_b}$$

- Settling time is inversely proportional to the bandiwdth:
 - lacktriangle For first order systems the settling time T_s is proportional to the time constant au_s
 - lacksquare The bandwidth $w_b=rac{1}{ au}$
- Broadly speaking we can say (even for systems of order greater than 1) that the larger the bandwidth, the faster is the response (the shorter is the system settling time)

Bandwidth in feedback systems

Given the system:



$$Y(s) = rac{GR}{1+GR} = G_c U(s)$$

- For a closed-loop system it is normal to expect no offset for step targets, in steady-state
- This means $G_c(0) = 1$ or 0 dB
- In this case, B is when the gain drops $-3\mathrm{dB}$

For example:

• Given a system

$$G(s) = rac{2}{s+4}$$


• and a compensator

$$R(s) = 2\frac{s+2}{s}$$

The closed loop system is:

$$G_c = \frac{GR}{1 + GR}$$


and is Bode plot is:



$\bullet \;$ Bandwidth is about 2rad/s

In feedbak system, with high loop gain, the bandwidth of the closed loop system G_c can be approximated by the knowledge of the loop gain function GR:


$$G_c = rac{RG}{1+RG} pprox \left\{ egin{array}{ll} 1 & ext{if} & |RG| \gg 1 \ RG & ext{if} & |RG| \ll 1 \end{array}
ight.$$



Example

$$G(s) = rac{1000}{(s+1)^3(s+10)}$$
 $G_c(s) = rac{G(s)}{1+G(s)}$

```
In [ ]: fig, axs = plt.subplots(2, 1, figsize=(15,10))
        mag_ol, phase_ol, omega_ol = control.bode(control.tf([1000],[1, 13, 33, 31, 10]), dB=True,
        mag_cc, phase_cc, omega_cc = control.bode(control.tf([1000],[1, 13, 33, 31, 10+1000]), dB=T
        # bandwidth
        ax1,ax2 = plt.gcf().axes
                                    # get subplot axes
        plt.sca(ax1)
                                      # magnitude plot
        plt.text(1, 40, '$G(s)$', color='blue')
        plt.plot(plt.xlim(),[40-3, 40-3], 'b--')
        plt.plot([0.5, 0.5],plt.ylim(),'b--');
        plt.text(0.5, -100, '$\omega_b$', color='blue')
        plt.plot(plt.xlim(),[-3, -3],[-3, -3])
        plt.plot([5, 5],plt.ylim(),'r--')
        plt.text(0.01, 3, '$G_c(s)$', color='orange')
        plt.text(5, -100, '$\omega_{bc}$', color='blue');
```



In []: