Troubleshooting

```
The following command enables debug information to stdout - to be displayed
with docker logs container\_id\_of\_sematext-agent-docker:
docker run -d --name sematext-agent -e SPM_TOKEN=YOUR-SPM_TOKEN \
-e SPM_LOG_TO_CONSOLE=true \
-e SPM_LOG_LEVEL=debug \
-v /var/run/docker.sock:/var/run/docker.sock \
sematext/sematext-agent-docker
docker logs -f sematext-agent
Parameters for debug output:
-e SPM_LOG_TO_CONSOLE=true - enables internal log messages to the console. Normally only metrics
-e SPM_LOG_LEVEL=debug - "info|warn|error|debug" - set this to "debug" to see all messages on co
-e DEBUG_SPM_LOGGING=enabled - very detailed logging before parsing, after parsing, inserts to
If running Sematext Docker Agent in debug mode doesn't help you spot and
solve the problem please send us the diagnostics package as described below.
Run the following to collect basic information for our support, such as environ-
ment variables, and configuration:
docker exec -it sematext-agent spm-client-diagnostics
SPM diagnostics info is in /tmp/spm-diagnose.zip
Please e-mail the file to [support@sematext.com] (mailto:support@sematext.com)
Please contact us via chat or email us the output of that command and the
generated ZIP file (to support@sematext.com). You can copy the ZIP file to
your host using "docker cp":
docker cp sematext-agent:/tmp/spm-diagnose.zip .
```