# CAMD User Guide

Patrick R. Amestoy\* Yanqing (Morris) Chen Timothy A. Davis<sup>†</sup> Iain S. Duff<sup>‡</sup> VERSION 3.3.2, Feb XX, 2024

#### Abstract

CAMD is a set of ANSI C routines that implements the approximate minimum degree ordering algorithm to permute sparse matrices prior to numerical factorization. Ordering constraints can be optionally provided. A MATLAB interface is included.

CAMD, Copyright©2007-2023, Timothy A. Davis, Yanqing Chen, Patrick R. Amestoy, and Iain S. Duff. All Rights Reserved.

SPDX-License-Identifier: BSD-3-clause **Availability:** http://www.suitesparse.com.

#### Acknowledgments:

This work was supported by the National Science Foundation, under grants ASC-9111263 and DMS-9223088 and CCR-0203270, and by Sandia National Labs (a grant from DOE). The conversion to C, the addition of the elimination tree post-ordering, and the handling of dense rows and columns were done while Davis was on sabbatical at Stanford University and Lawrence Berkeley National Laboratory. The ordering constraints were added by Chen and Davis.

<sup>\*</sup>ENSEEIHT-IRIT, 2 rue Camichel 31017 Toulouse, France. email: amestoy@enseeiht.fr. http://www.enseeiht.fr/~amestoy.

<sup>&</sup>lt;sup>†</sup>email: DrTimothyAldenDavis@gmail.com, http://www.suitesparse.com. This work was supported by the National Science Foundation, under grants ASC-9111263, DMS-9223088, and CCR-0203270. Portions of the work were done while on sabbatical at Stanford University and Lawrence Berkeley National Laboratory (with funding from Stanford University and the SciDAC program). Ordering constraints added with support from Sandia National Laboratory (Dept. of Energy).

<sup>&</sup>lt;sup>‡</sup>Rutherford Appleton Laboratory, Chilton, Didcot, Oxon OX11 0QX, England. email: i.s.duff@rl.ac.uk. http://www.numerical.rl.ac.uk/people/isd/isd.html. This work was supported by the EPSRC under grant GR/R46441.

#### 1 Overview

CAMD is a set of routines for preordering a sparse matrix prior to numerical factorization. It uses an approximate minimum degree ordering algorithm [1, 2] to find a permutation matrix  $\mathbf{P}$  so that the Cholesky factorization  $\mathbf{PAP}^{\mathsf{T}} = \mathbf{LL}^{\mathsf{T}}$  has fewer (often much fewer) nonzero entries than the Cholesky factorization of  $\mathbf{A}$ . The algorithm is typically much faster than other ordering methods and minimum degree ordering algorithms that compute an exact degree [4]. Some methods, such as approximate deficiency [9] and graph-partitioning based methods [5, 7, 8, 10] can produce better orderings, depending on the matrix.

The algorithm starts with an undirected graph representation of a symmetric sparse matrix **A**. Node i in the graph corresponds to row and column i of the matrix, and there is an edge (i, j) in the graph if  $a_{ij}$  is nonzero. The degree of a node is initialized to the number of off-diagonal nonzeros in row i, which is the size of the set of nodes adjacent to i in the graph.

The selection of a pivot  $a_{ii}$  from the diagonal of  $\mathbf{A}$  and the first step of Gaussian elimination corresponds to one step of graph elimination. Numerical fill-in causes new nonzero entries in the matrix (fill-in refers to nonzeros in  $\mathbf{L}$  that are not in  $\mathbf{A}$ ). Node i is eliminated and edges are added to its neighbors so that they form a clique (or *element*). To reduce fill-in, node i is selected as the node of least degree in the graph. This process repeats until the graph is eliminated.

The clique is represented implicitly. Rather than listing all the new edges in the graph, a single list of nodes is kept which represents the clique. This list corresponds to the nonzero pattern of the first column of  $\mathbf{L}$ . As the elimination proceeds, some of these cliques become subsets of subsequent cliques, and are removed. This graph can be stored in place, that is using the same amount of memory as the original graph.

The most costly part of the minimum degree algorithm is the recomputation of the degrees of nodes adjacent to the current pivot element. Rather than keep track of the exact degree, the approximate minimum degree algorithm finds an upper bound on the degree that is easier to compute. For nodes of least degree, this bound tends to be tight. Using the approximate degree instead of the exact degree leads to a substantial savings in run time, particularly for very irregularly structured matrices. It has no effect on the quality of the ordering.

The elimination phase is followed by an elimination tree post-ordering. This has no effect on fill-in, but reorganizes the ordering so that the subsequent numerical factorization is more efficient. It also includes a pre-processing phase in which nodes of very high degree are removed (without causing fill-in), and placed last in the permutation  $\mathbf{P}$  (subject to the constraints). This reduces the run time substantially if the matrix has a few rows with many nonzero entries, and has little effect on the quality of the ordering. CAMD operates on the symmetric nonzero pattern of  $\mathbf{A} + \mathbf{A}^{\mathsf{T}}$ , so it can be given an unsymmetric matrix, or either the lower or upper triangular part of a symmetric matrix.

CAMD has the ability to order the matrix with constraints. Each node i in the graph (row/column i in the matrix) has a constraint, C[i], which is in the range 0 to n-1. All nodes with C[i] = 0 are ordered first, followed by all nodes with constraint 1, and so on. That is, C[P[k]] is monotonically non-decreasing as k varies from 0 to n-1. If C is NULL, no constraints are used (the ordering will be similar to AMD's ordering, except that the postordering is different). The optional C parameter is also provided in the MATLAB interface, (p = camd(A,Control,C)).

For a discussion of the long history of the minimum degree algorithm, see [4].

# 2 Availability

CAMD is available at http://www.suitesparse.com. The Fortran version is available as the routine MC47 in HSL (formerly the Harwell Subroutine Library) [6]. MC47 does not include ordering constraints.

# 3 Using CAMD in MATLAB

To use CAMD in MATLAB, you must first compile the CAMD mexFunction. Just type make in the Unix system shell, while in the CAMD directory. You can also type camd\_make in MATLAB, while in the CAMD/MATLAB directory. Place the CAMD/MATLAB directory in your MATLAB path. This can be done on any system with MATLAB, including Windows. See Section 6 for more details on how to install CAMD.

The MATLAB statement p=camd(A) finds a permutation vector p such that the Cholesky factorization chol(A(p,p)) is typically sparser than chol(A). If A is unsymmetric, camd(A) is identical to camd(A+A') (ignoring numerical cancellation). If A is not symmetric positive definite, but has substantial diagonal entries and a mostly symmetric nonzero pattern, then this ordering is also suitable for LU factorization. A partial pivoting threshold may be required to prevent pivots from being selected off the diagonal, such as the statement [L,U,P] = lu (A (p,p), 0.1). Type help lu for more details. The statement [L,U,P,Q] = lu (A (p,p)) in MATLAB 6.5 is not suitable, however, because it uses UMFPACK Version 4.0 and thus does not attempt to select pivots from the diagonal. UMFPACK Version 4.1 in MATLAB 7.0 and later uses several strategies, including a symmetric pivoting strategy, and will give you better results if you want to factorize an unsymmetric matrix of this type. Refer to the UMFPACK User Guide for more details, at http://www.suitesparse.com.

The CAMD mexFunction is much faster than the built-in MATLAB symmetric minimum degree ordering methods, SYMAMD and SYMMMD. Its ordering quality is essentially identical to AMD, comparable to SYMAMD, and better than SYMMMD [3].

An optional input argument can be used to modify the control parameters for CAMD (aggressive absorption, dense row/column handling, and printing of statistics). An optional output argument provides statistics on the ordering, including an analysis of the fill-in and the floating-point operation count for a subsequent factorization. For more details (once CAMD is installed), type help camd in the MATLAB command window.

# 4 Using CAMD in a C program

The C-callable CAMD library consists of eight user-callable routines and one include file. There are two versions of seven of the routines, with int32\_t and int64\_t integers. The routines with prefix camd\_l\_use int64\_t integer arguments; the others use int32\_t integer arguments.

The following routines are fully described in Section 7:

• camd\_order (int64\_t version: camd\_l\_order)

```
#include "camd.h"
int32_t n, Ap [n+1], Ai [nz], P [n], C [n];
double Control [CAMD_CONTROL], Info [CAMD_INFO];
int result = camd_order (n, Ap, Ai, P, Control, Info, C);
```

Computes the approximate minimum degree ordering of an n-by-n matrix  $\mathbf{A}$ . Returns a permutation vector  $\mathbf{P}$  of size  $\mathbf{n}$ , where  $\mathbf{P}[\mathtt{k}] = \mathbf{i}$  if row and column  $\mathbf{i}$  are the  $\mathbf{k}$ th row and column in the permuted matrix. This routine allocates its own memory of size 1.2e + 9n integers, where e is the number of nonzeros in  $\mathbf{A} + \mathbf{A}^\mathsf{T}$ . It computes statistics about the matrix  $\mathbf{A}$ , such as the symmetry of its nonzero pattern, the number of nonzeros in  $\mathbf{L}$ , and the number of floating-point operations required for Cholesky and LU factorizations (which are returned in the Info array). The user's input matrix is not modified. It returns CAMD\_OK if successful, CAMD\_OK\_BUT\_JUMBLED if successful (but the matrix had unsorted and/or duplicate row indices), CAMD\_INVALID if the matrix is invalid, CAMD\_OUT\_OF\_MEMORY if out of memory.

The array C provides the ordering constraints. On input, C may be null (to denote no constraints); otherwise, it must be an array size n, with entries in the range 0 to n-1. On output, C[P[0..n-1]] is monotonically non-descreasing.

• camd\_defaults (int64\_t version: camd\_l\_defaults)

```
#include "camd.h"
double Control [CAMD_CONTROL] ;
camd_defaults (Control) ;
```

Sets the default control parameters in the Control array. These can then be modified as desired before passing the array to the other CAMD routines.

• camd\_control (int64\_t version: camd\_l\_control)

```
#include "camd.h"
double Control [CAMD_CONTROL] ;
camd_control (Control) ;
```

Prints a description of the control parameters, and their values.

• camd\_info (int64\_t version: camd\_l\_info)

```
#include "camd.h"
double Info [CAMD_INFO] ;
camd_info (Info) ;
```

Prints a description of the statistics computed by CAMD, and their values.

• camd\_valid (int64\_t version: camd\_valid)

```
#include "camd.h"
int32_t n, Ap [n+1], Ai [nz] ;
int result = camd_valid (n, n, Ap, Ai) ;
```

Returns CAMD\_OK or CAMD\_OK\_BUT\_JUMBLED if the matrix is valid as input to camd\_order; the latter is returned if the matrix has unsorted and/or duplicate row indices in one or more columns. Returns CAMD\_INVALID if the matrix cannot be passed to camd\_order. For camd\_order, the matrix must also be square. The first two arguments are the number of rows and the number of columns of the matrix. For its use in CAMD, these must both equal n.

- camd\_2 (int64\_t version: camd\_12) CAMD ordering kernel. It is faster than camd\_order, and can be called by the user, but it is difficult to use. It does not check its inputs for errors. It does not require the columns of its input matrix to be sorted, but it destroys the matrix on output. Additional workspace must be passed. Refer to the source file CAMD/Source/camd\_2.c for a description.
- camd\_version: returns the CAMD version

The nonzero pattern of the matrix **A** is represented in compressed column form. For an *n*-by-*n* matrix **A** with nz nonzero entries, the representation consists of two arrays: Ap of size n+1 and Ai of size nz. The row indices of entries in column j are stored in Ai[Ap[j] ... Ap[j+1]-1]. For camd\_order, if duplicate row indices are present, or if the row indices in any given column are not sorted in ascending order, then camd\_order creates an internal copy of the matrix with sorted rows and no duplicate entries, and orders the copy. This adds slightly to the time and memory usage of camd\_order, but is not an error condition.

The matrix is 0-based, and thus row indices must be in the range 0 to n-1. The first entry Ap[0] must be zero. The total number of entries in the matrix is thus nz = Ap[n].

The matrix must be square, but it does not need to be symmetric. The camd\_order routine constructs the nonzero pattern of  $\mathbf{B} = \mathbf{A} + \mathbf{A}^\mathsf{T}$  (without forming  $\mathbf{A}^\mathsf{T}$  explicitly if  $\mathbf{A}$  has sorted columns and no duplicate entries), and then orders the matrix  $\mathbf{B}$ . Thus, either the lower triangular part of  $\mathbf{A}$ , the upper triangular part, or any combination may be passed. The transpose  $\mathbf{A}^\mathsf{T}$  may also be passed to camd\_order. The diagonal entries may be present, but are ignored.

#### 4.1 Control parameters

Control parameters are set in an optional Control array. It is optional in the sense that if a NULL pointer is passed for the Control input argument, then default control parameters are used.

- Control [CAMD\_DENSE] (or Control(1) in MATLAB): controls the threshold for "dense" rows/columns. A dense row/column in  $\mathbf{A} + \mathbf{A}^\mathsf{T}$  can cause CAMD to spend significant time in ordering the matrix. If Control [CAMD\_DENSE]  $\geq 0$ , rows/columns with more than Control [CAMD\_DENSE]  $\sqrt{n}$  entries are ignored during the ordering, and placed last in the output order. The default value of Control [CAMD\_DENSE] is 10. If negative, no rows/columns are treated as "dense." Rows/columns with 16 or fewer off-diagonal entries are never considered "dense."
- Control [CAMD\_AGGRESSIVE] (or Control(2) in MATLAB): controls whether or not to use aggressive absorption, in which a prior element is absorbed into the current element if it is a subset of the current element, even if it is not adjacent to the current pivot element (refer to [1, 2] for more details). The default value is nonzero, which means that aggressive absorption will be performed. This nearly always leads to a better ordering (because the approximate degrees are more accurate) and a lower execution time. There are cases where it can lead to a slightly worse ordering, however. To turn it off, set Control [CAMD\_AGGRESSIVE] to 0.

Statistics are returned in the Info array (if Info is NULL, then no statistics are returned). Refer to camd.h file, for more details (14 different statistics are returned, so the list is not included here).

### 4.2 Sample C program

The following program, camd\_demo.c, illustrates the basic use of CAMD. See Section 5 for a short description of each calling sequence.

The Ap and Ai arrays represent the binary matrix

$$\mathbf{A} = \left[ \begin{array}{ccccc} 1 & 1 & 0 & 0 & 0 \\ 1 & 1 & 1 & 0 & 1 \\ 0 & 1 & 1 & 1 & 0 \\ 0 & 0 & 1 & 1 & 0 \\ 0 & 1 & 1 & 0 & 1 \end{array} \right].$$

The diagonal entries are ignored. CAMD constructs the pattern of  $\mathbf{A} + \mathbf{A}^{\mathsf{T}}$ , and returns a permutation vector of (3, 2, 1, 4, 0). Note that nodes 1, 2, and 3 appear first (they are in the constraint set 0), node 4 appears next (since C[4] = 1), and node 0 appears last. Since the matrix is unsymmetric but with a mostly symmetric nonzero pattern, this would be a suitable permutation for an LU factorization of a matrix with this nonzero pattern and whose diagonal entries are not too small. The program uses default control settings and does not return any statistics about the ordering, factorization, or solution (Control and Info are both (double \*) NULL). It also ignores the status value returned by camd\_order.

More example programs are included with the CAMD package. The camd\_demo.c program provides a more detailed demo of CAMD. Another example is the CAMD mexFunction, camd\_mex.c.

#### 4.3 A note about zero-sized arrays

CAMD uses several user-provided arrays of size n or nz. Either n or nz can be zero. If you attempt to malloc an array of size zero, however, malloc will return a null pointer which CAMD will report as invalid. If you malloc an array of size n or nz to pass to CAMD, make sure that you handle the n = 0 and nz = 0 cases correctly.

# 5 Synopsis of C-callable routines

The matrix **A** is n-by-n with nz entries.

```
#include "camd.h"
int32_t n, status, Ap [n+1], Ai [nz], P [n], C [n];
double Control [CAMD_CONTROL], Info [CAMD_INFO];
camd_defaults (Control);
status = camd_order (n, Ap, Ai, P, Control, Info, C);
camd_control (Control);
```

```
camd_info (Info);
status = camd_valid (n, n, Ap, Ai);

The camd_l_* routines are identical, except that all int32_t arguments become int64_t:

#include "camd.h"
int64_t n, status, Ap [n+1], Ai [nz], P [n], C [n];
double Control [CAMD_CONTROL], Info [CAMD_INFO];
camd_l_defaults (Control);
status = camd_l_order (n, Ap, Ai, P, Control, Info, C);
camd_l_control (Control);
camd_l_info (Info);
status = camd_l_valid (n, n, Ap, Ai);

The camd_version function uses plain int:

#include "camd.h"
int version [3];
camd_version (version);
```

#### 6 Installation

CAMD now relies primarily on CMake to build the library. It also includes a simple CAMD/Makefile which uses cmake to do the actual build. The use of this CAMD/Makefile is optional; for Windows, just import the CMakeLists.txt into MS Visual Studio.

To compile and install the library for both system-wide usage and local usage:

```
make
sudo make install
```

To compile/install for just local usage (SuiteSparse/lib and SuiteSparse/include):

```
make local
make install
```

To run the demos

make demos

To remove all files in CAMD/ not in the original distribution (leaves SuiteSparse/lib and SuiteSparse/include unchanged):

```
make clean
```

To use the CAMD mexFunction in MATLAB, simply type camd\_make in MATLAB while in the CAMD/MATLAB directory. This works on any system with MATLAB, including Windows.

## 7 The CAMD routines

The file CAMD/Include/camd.h listed below describes each user-callable routine in the C version of CAMD, and gives details on their use.

```
// CAMD/Include/camd.h: constrained approximate minimum degree ordering
// CAMD, Copyright (c) 1996-2024, Timothy A. Davis, Yanqing Chen,
// Patrick R. Amestoy, and Iain S. Duff. All Rights Reserved.
// SPDX-License-Identifier: BSD-3-clause
//-----
/* CAMD finds a symmetric ordering P of a matrix A so that the Cholesky
* factorization of P*A*P' has fewer nonzeros and takes less work than the
* Cholesky factorization of A. If A is not symmetric, then it performs its
* ordering on the matrix A+A'. Two sets of user-callable routines are
 * provided, one for int32_t integers and the other for int64_t integers.
* The method is based on the approximate minimum degree algorithm, discussed
* in Amestoy, Davis, and Duff, "An approximate degree ordering algorithm",
* SIAM Journal of Matrix Analysis and Applications, vol. 17, no. 4, pp.
* 886-905, 1996.
#ifndef CAMD_H
#define CAMD_H
#include "SuiteSparse_config.h"
/* make it easy for C++ programs to include CAMD */
#ifdef __cplusplus
extern "C" {
#endif
int camd_order /* returns CAMD_OK, CAMD_OK_BUT_JUMBLED,
                           * CAMD_INVALID, or CAMD_OUT_OF_MEMORY */
(
                              /* A is n-by-n. n must be >= 0. */
   int32_t n,
   const int32_t Ap [ ],
                              /* column pointers for A, of size n+1 */
   const int32_t Ai [ ],
                              /* row indices of A, of size nz = Ap [n] */
   int32_t P [ ],
                              /* output permutation, of size n */
   double Control [ ],
                          /* input Control settings, of size CAMD_CONTROL */
   double Info [],
                          /* output Info statistics, of size CAMD_INFO */
   const int32_t C [ ]
                              /* Constraint set of A, of size n; can be NULL */
);
int camd_l_order /* see above for description */
   int64_t n,
   const int64_t Ap [ ],
   const int64_t Ai [ ],
   int64_t P [],
   double Control [],
   double Info [],
   const int64_t C [ ]
);
```

```
/* Input arguments (not modified):
       n: the matrix A is n-by-n.
       Ap: an int32_t/int64_t array of size n+1, containing column
           pointers of A.
       Ai: an int32_t/int64_t array of size nz, containing the row
           indices of A, where nz = Ap [n].
       Control: a double array of size CAMD_CONTROL, containing control
           parameters. Defaults are used if Control is NULL.
* Output arguments (not defined on input):
       P: an int32_t/int64_t array of size n, containing the output
           permutation. If row i is the kth pivot row, then P[k] = i. In
           MATLAB notation, the reordered matrix is A (P,P).
       Info: a double array of size CAMD_INFO, containing statistical
           information. Ignored if Info is NULL.
* On input, the matrix A is stored in column-oriented form. The row indices
* of nonzero entries in column j are stored in Ai [Ap [j] ... Ap [j+1]-1].
* If the row indices appear in ascending order in each column, and there
* are no duplicate entries, then camd_order is slightly more efficient in
* terms of time and memory usage. If this condition does not hold, a copy
st of the matrix is created (where these conditions do hold), and the copy is
* ordered.
* Row indices must be in the range 0 to
* n-1. Ap [0] must be zero, and thus nz = Ap [n] is the number of nonzeros
* in A. The array Ap is of size n+1, and the array Ai is of size nz = Ap [n].
* The matrix does not need to be symmetric, and the diagonal does not need to
* be present (if diagonal entries are present, they are ignored except for
* the output statistic Info [CAMD_NZDIAG]). The arrays Ai and Ap are not
* modified. This form of the Ap and Ai arrays to represent the nonzero
* pattern of the matrix A is the same as that used internally by MATLAB.
* If you wish to use a more flexible input structure, please see the
* umfpack_*_triplet_to_col routines in the UMFPACK package, at
* http://www.suitesparse.com.
* Restrictions: n \ge 0. Ap [0] = 0. Ap [j] \le Ap [j+1] for all j in the
       range 0 to n-1. nz = Ap [n] >= 0. Ai [0..nz-1] must be in the range 0
       to n-1. Finally, Ai, Ap, and P must not be NULL. If any of these
       restrictions are not met, CAMD returns CAMD_INVALID.
  CAMD returns:
       CAMD_OK if the matrix is valid and sufficient memory can be allocated to
           perform the ordering.
       CAMD_OUT_OF_MEMORY if not enough memory can be allocated.
       CAMD_INVALID if the input arguments n, Ap, Ai are invalid, or if P is
           NULL.
       CAMD_OK_BUT_JUMBLED if the matrix had unsorted columns, and/or duplicate
           entries, but was otherwise valid.
```

\* The CAMD routine first forms the pattern of the matrix A+A', and then

```
* computes a fill-reducing ordering, P. If P [k] = i, then row/column i of
* the original is the kth pivotal row. In MATLAB notation, the permuted
* matrix is A (P,P), except that O-based indexing is used instead of the
* 1-based indexing in MATLAB.
* The Control array is used to set various parameters for CAMD. If a NULL
* pointer is passed, default values are used. The Control array is not
       Control [CAMD_DENSE]: controls the threshold for "dense" rows/columns.
          A dense row/column in A+A' can cause CAMD to spend a lot of time in
          ordering the matrix. If Control [CAMD_DENSE] >= 0, rows/columns
          with more than Control [CAMD_DENSE] * sqrt (n) entries are ignored
          during the ordering, and placed last in the output order. The
          default value of Control [CAMD_DENSE] is 10. If negative, no
          rows/columns are treated as "dense". Rows/columns with 16 or
          fewer off-diagonal entries are never considered "dense".
       Control [CAMD_AGGRESSIVE]: controls whether or not to use aggressive
           absorption, in which a prior element is absorbed into the current
           element if is a subset of the current element, even if it is not
          adjacent to the current pivot element (refer to Amestoy, Davis,
          & Duff, 1996, for more details). The default value is nonzero,
          which means to perform aggressive absorption. This nearly always
          leads to a better ordering (because the approximate degrees are
          more accurate) and a lower execution time. There are cases where
          it can lead to a slightly worse ordering, however. To turn it off,
           set Control [CAMD_AGGRESSIVE] to 0.
       Control [2..4] are not used in the current version, but may be used in
          future versions.
* The Info array provides statistics about the ordering on output. If it is
* not present, the statistics are not returned. This is not an error
* condition.
       Info [CAMD_STATUS]: the return value of CAMD, either CAMD_OK,
           CAMD_OK_BUT_JUMBLED, CAMD_OUT_OF_MEMORY, or CAMD_INVALID.
       Info [CAMD_N]: n, the size of the input matrix
       Info [CAMD_NZ]: the number of nonzeros in A, nz = Ap [n]
       Info [CAMD_SYMMETRY]: the symmetry of the matrix A. It is the number
          of "matched" off-diagonal entries divided by the total number of
          off-diagonal entries. An entry A(i,j) is matched if A(j,i) is also
           an entry, for any pair (i,j) for which i != j. In MATLAB notation,
              S = spones (A);
              B = tril (S, -1) + triu (S, 1) ;
               symmetry = nnz (B & B') / nnz (B) ;
       Info [CAMD_NZDIAG]: the number of entries on the diagonal of A.
       Info [CAMD_NZ_A_PLUS_AT]: the number of nonzeros in A+A', excluding the
          diagonal. If A is perfectly symmetric (Info [CAMD_SYMMETRY] = 1)
          with a fully nonzero diagonal, then Info [CAMD_NZ_A_PLUS_AT] = nz-n
           (the smallest possible value). If A is perfectly unsymmetric
```

(Info [CAMD\_SYMMETRY] = 0, for an upper triangular matrix, for example) with no diagonal, then Info [CAMD\_NZ\_A\_PLUS\_AT] = 2\*nz

```
(the largest possible value).
       Info [CAMD_NDENSE]: the number of "dense" rows/columns of A+A' that were
           removed from A prior to ordering. These are placed last in the
           output order P.
       Info [CAMD_MEMORY]: the amount of memory used by CAMD, in bytes. In the
           current version, this is 1.2 * Info [CAMD_NZ_A_PLUS_AT] + 9*n
           times the size of an integer. This is at most 2.4nz + 9n. This
           excludes the size of the input arguments Ai, Ap, and P, which have
           a total size of nz + 2*n + 1 integers.
       Info [CAMD_NCMPA]: the number of garbage collections performed.
       Info [CAMD_LNZ]: the number of nonzeros in L (excluding the diagonal).
           This is a slight upper bound because mass elimination is combined
           with the approximate degree update. It is a rough upper bound if
           there are many "dense" rows/columns. The rest of the statistics,
           below, are also slight or rough upper bounds, for the same reasons.
           The post-ordering of the assembly tree might also not exactly
           correspond to a true elimination tree postordering.
       Info [CAMD_NDIV]: the number of divide operations for a subsequent LDL'
           or LU factorization of the permuted matrix A (P,P).
       Info [CAMD_NMULTSUBS_LDL]: the number of multiply-subtract pairs for a
           subsequent LDL' factorization of A (P,P).
       Info [CAMD_NMULTSUBS_LU]: the number of multiply-subtract pairs for a
           subsequent LU factorization of A (P,P), assuming that no numerical
           pivoting is required.
       Info [CAMD_DMAX]: the maximum number of nonzeros in any column of L,
           including the diagonal.
       Info [14..19] are not used in the current version, but may be used in
           future versions.
/* direct interface to CAMD */
/* ------ */
/* camd_2 is the primary CAMD ordering routine. It is not meant to be
* user-callable because of its restrictive inputs and because it destroys
* the user's input matrix. It does not check its inputs for errors, either.
* However, if you can work with these restrictions it can be faster than
\ast camd_order and use less memory (assuming that you can create your own copy
* of the matrix for CAMD to destroy). Refer to CAMD/Source/camd_2.c for a
* description of each parameter. */
void camd_2
   int32_t n,
   int32_t Pe [],
   int32_t Iw [],
   int32_t Len [ ],
   int32_t iwlen,
   int32_t pfree,
```

```
int32_t Nv [],
   int32_t Next [ ],
   int32_t Last [],
   int32_t Head [ ],
   int32_t Elen [ ],
   int32_t Degree [ ],
   int32_t W [],
   double Control [],
   double Info [],
   const int32_t C [ ],
   int32_t BucketSet [ ]
);
void camd_12
   int64_t n,
   int64_t Pe [],
   int64_t Iw [],
   int64_t Len [],
   int64_t iwlen,
   int64_t pfree,
   int64_t Nv [],
   int64_t Next [ ],
   int64_t Last [],
   int64_t Head [ ],
   int64_t Elen [ ],
   int64_t Degree [ ],
   int64_t W [ ],
   double Control [],
   double Info [],
   const int64_t C [ ],
   int64_t BucketSet [ ]
);
                ----- */
/* camd valid */
/* ------ */
/* Returns CAMD_OK or CAMD_OK_BUT_JUMBLED if the matrix is valid as input to
 * camd_order; the latter is returned if the matrix has unsorted and/or
* duplicate row indices in one or more columns. Returns CAMD_INVALID if the
 * matrix cannot be passed to camd_order. For camd_order, the matrix must also
 * be square. The first two arguments are the number of rows and the number
 st of columns of the matrix. For its use in CAMD, these must both equal n.
 */
int camd_valid
   int32_t n_row,
                            /* # of rows */
   int32_t n_col,
                            /* # of columns */
   const int32_t Ap [ ],
                           /* column pointers, of size n_col+1 */
   const int32_t Ai [ ]
                           /* row indices, of size Ap [n_col] */
);
int camd_l_valid
   int64_t n_row,
   int64_t n_col,
```

```
const int64_t Ap [ ],
   const int64_t Ai [ ]
);
/* ----- */
/* camd_cvalid */
/* ----- */
/* Returns TRUE if the constraint set is valid as input to camd_order,
* FALSE otherwise. */
int camd_cvalid
  int32_t n,
  const int32_t C [ ]
);
int camd_l_cvalid
  int64_t n,
  const int64_t C [ ]
/* ----- */
/* CAMD Control and Info arrays */
/* ------ */
/* camd_defaults: sets the default control settings */
void camd_defaults (double Control [ ]);
void camd_l_defaults (double Control [ ]) ;
/* camd_control: prints the control settings */
void camd_control (double Control [ ]);
void camd_l_control (double Control [ ]) ;
/* camd_info: prints the statistics */
void camd_info
              (double Info [ ]) ;
void camd_l_info
                 (double Info [ ]) ;
// camd_version: return CAMD version. The version array is returned with
// version [0..2] = {CAMD_MAIN_VERSION, CAMD_SUB_VERSION, CAMD_SUBSUB_VERSION}
void camd_version (int version [3]);
#ifdef __cplusplus
#endif
#define CAMD_CONTROL 5
                       /* size of Control array */
#define CAMD_INFO 20
                       /* size of Info array */
/* contents of Control */
#define CAMD_DENSE 0
                       /* "dense" if degree > Control [0] * sqrt (n) */
#define CAMD_AGGRESSIVE 1
                        /* do aggressive absorption if Control [1] != 0 */
/* default Control settings */
#define CAMD_DEFAULT_DENSE 10.0
                              /* default "dense" degree 10*sqrt(n) */
#define CAMD_DEFAULT_AGGRESSIVE 1
                             /* do aggressive absorption by default */
/* contents of Info */
```

```
#define CAMD_STATUS 0 /* return value of camd_order and camd_l_order */
#define CAMD_N 1
                                /* A is n-by-n */
#define CAMD_NZ 2
                        /* number of nonzeros in A */
#define CAMD_NZDIAG 4 /* symmetry of pattern (1 is sym., 0 is unsym.) */
#define CAMD_NZDIAG 4 /* # of entries on diagonal */
#define CAMD_NZ_A_PLUS_AT 5 /* nz in A+A' */
                     /* number of "dense" rows/columns in A */
#define CAMD_NDENSE 6
                        /* amount of memory used by CAMD */
#define CAMD_MEMORY 7
#define CAMD_NCMPA 8
                        /* number of garbage collections in CAMD */
#define CAMD_LNZ 9
                        /* approx. nz in L, excluding the diagonal */
#define CAMD_NDIV 10
                        /* number of fl. point divides for LU and LDL' */
\#define\ CAMD\_NMULTSUBS\_LDL\ 11\ /*\ number\ of\ fl.\ point\ (*,-)\ pairs\ for\ LDL'\ */
#define CAMD_NMULTSUBS_LU 12 \ /* number of fl. point (*,-) pairs for LU */
#define CAMD_DMAX 13
                         /* max nz. in any column of L, incl. diagonal */
/* ----- */
/* return values of CAMD */
/* ----- */
#define CAMD_OK 0
                             /* success */
#define CAMD_OUT_OF_MEMORY -1 /* malloc failed, or problem too large */
#define CAMD_INVALID -2  /* input arguments are not valid */
#define CAMD_OK_BUT_JUMBLED 1  /* input matrix is OK for camd_order, but
   * columns were not sorted, and/or duplicate entries were present. CAMD had
    * to do extra work before ordering the matrix. This is a warning, not an
    * error. */
/* =========== */
/* === CAMD version ========== */
 * As an example, to test if the version you are using is 1.2 or later:
       if (CAMD_VERSION >= CAMD_VERSION_CODE (1,2)) ...
 * This also works during compile-time:
       #if (CAMD_VERSION >= CAMD_VERSION_CODE (1,2))
           printf ("This is version 1.2 or later\n") ;
           printf ("This is an early version\n");
       #endif
#define CAMD_DATE "Feb XX, 2024"
#define CAMD_MAIN_VERSION 3
#define CAMD_SUB_VERSION
#define CAMD_SUBSUB_VERSION 2
#define CAMD_VERSION_CODE(main, sub) SUITESPARSE_VER_CODE(main, sub)
#define CAMD_VERSION CAMD_VERSION_CODE(3,3)
#define CAMD__VERSION SUITESPARSE__VERCODE(3,3,2)
#if !defined (SUITESPARSE__VERSION) || \
   (SUITESPARSE__VERSION < SUITESPARSE__VERCODE(7,7,0))
#error "CAMD 3.3.2 requires SuiteSparse_config 7.7.0 or later"
#endif
```

#endif

## References

- [1] P. R. Amestoy, T. A. Davis, and I. S. Duff. An approximate minimum degree ordering algorithm. SIAM J. Matrix Anal. Applic., 17(4):886–905, 1996.
- [2] P. R. Amestoy, T. A. Davis, and I. S. Duff. Algorithm 837: An approximate minimum degree ordering algorithm. *ACM Trans. Math. Softw.*, 30(3):381–388, 2004.
- [3] T. A. Davis, J. R. Gilbert, S. I. Larimore, and E. G. Ng. A column approximate minimum degree ordering algorithm. *ACM Trans. Math. Softw.*, 30:353–376, 2004.
- [4] A. George and J. W. H. Liu. The evolution of the minimum degree ordering algorithm. *SIAM Review*, 31(1):1–19, 1989.
- [5] B. Hendrickson and E. Rothberg. Improving the runtime and quality of nested dissection ordering. SIAM J. Sci. Comput., 20:468–489, 1999.
- [6] HSL. HSL 2002: A collection of Fortran codes for large scale scientific computation, 2002. www.cse.clrc.ac.uk/nag/hsl.
- [7] G. Karypis and V. Kumar. A fast and high quality multilevel scheme for partitioning irregular graphs. SIAM J. Sci. Comput., 20:359–392, 1998.
- [8] F. Pellegrini, J. Roman, and P. Amestoy. Hybridizing nested dissection and halo approximate minimum degree for efficient sparse matrix ordering. *Concurrency: Practice and Experience*, 12:68–84, 2000.
- [9] E. Rothberg and S. C. Eisenstat. Node selection strategies for bottom-up sparse matrix orderings. SIAM J. Matrix Anal. Applic., 19(3):682–695, 1998.
- [10] J. Schulze. Towards a tighter coupling of bottom-up and top-down sparse matrix ordering methods. *BIT*, 41(4):800–841, 2001.