SERVICENOW MATERIAL LIFECYCLE

Interchange step-by-step: jumatano__70 (30) → Jumatano_71 (20)

You receive **30** on the first work order. The second work order needs **20**. You do **not** receive 20 again from the warehouse for Jumatano_71. You take 20 from what jumatano__70 already received and issue it across. That movement is an **Interchange**.

Work order	Role	Qty	What happens
jumatano__70	Source (original request)	30	Raise SWO → Receive 30 → keep 10 → send 20 out
Jumatano_71	Target (needs material)	20	Raise SWO → receive 20 **from 70** by interchange → then consume

Rule to remember
The original request on jumatano__70 is never deleted. Interchange is a new SNWO Material Transaction. Jumatano_71 does not get a warehouse Receive of 20. Its 20 arrives as Interchanged In. A reason is mandatory. HTT is not used.

Picture of the quantities

After this step	70 Received	70 Warehouse remaining	70 Interchanged out	71 Interchanged in	71 Issued
Both SWOs created	0	0	0	0	0
70 receives 30	30	30	0	0	0
Interchange 20 to 71	30	10	20	20	20
71 consumes 20	30	10	20	20	20
70 issues remaining 10 to itself, then consumes 10	30	0	20	20	20

Before you start (once)

- WMS Site for Jumatano exists (site code must match the SWO site).
- Item master exists (the part both orders need).
- You are logged in as Stock User / Warehouse Manager / System Manager.
- Desk search finds **ServiceNow Site Work Order** and **SNWO Material Transaction**.

Step 1 — Create jumatano__70 (need 30)

- New **ServiceNow Site Work Order** (or import). SWO Number = **jumatano__70**.
- Site = Jumatano site. Order Type = **Material**. Quantity = **30**. Part Code = the item.
- Save. Process Status should be **Material Required**. Materials row Qty Requested = 30.
- Write the document name (same as SWO Number): jumatano__70.

Expected: MP Material Used = 0. Qty Received = 0. Do not type Maintenance Partner; it fetches from the site.

Step 2 — Create Jumatano_71 (need 20)

- New ServiceNow Site Work Order. SWO Number = **Jumatano_71**.
- Same site (or the site that needs the part). Order Type = Material. Quantity = **20**. Same Part Code.
- Save. Process Status = Material Required. Qty Requested = 20. Qty Received = 0.

Expected: Two separate work orders. 71 is still waiting. You have not received warehouse stock for 71.

Step 3 — Receive 30 on jumatano__70 only

- Open **jumatano__70** → **Material** → **Receive Material**.
- Transaction Type = Receive. Original Work Order = jumatano__70. Received For = jumatano__70.
- Add item, Qty = **30**. Posting Date = today. Save → **Submit**.
- Reload jumatano__70: Qty Received = 30, Warehouse Remaining = 30, Process Status = **Material Received**.
- Reload Jumatano_71: still Qty Received = 0. Correct.

Expected: Stock Balance of Main Warehouse does **not** change (this is not an MP issue).

Wrong: Receiving 20 on Jumatano_71 from the warehouse. That is a second supply, not interchange.

Step 4 — Interchange 20 from 70 to 71

Start from the **source** work order (the one that already has the stock).

- Open **jumatano__70** → **Material** → **Issue Material**.
- Keep Original Work Order = **jumatano__70**. Keep Received For = **jumatano__70** (stock came in on 70).
- Change **Issued To Work Order** = **Jumatano_71**.
- Enter **Reason for Interchange** (required), example: *Jumatano_71 needs 20 pcs; take from jumatano__70 remaining received stock.*
- Add the same item, Qty = **20** (not 30). Is MP Stock must stay **0**.
- Save. The form should switch Type to **Interchange** and tick Is Interchange.
- Submit.

If Save throws an error
Qty 20 must be ≤ warehouse remaining on 70 (here 30). If remaining is less than 20, receive more on 70 first, or interchange a smaller qty. If Issued To is still 70, this is a normal Issue, not interchange. If reason is empty, it will not submit.

Step 5 — Check both work orders (this is 71 “receiving”)

Jumatano_71 has now received the 20 — not by Receive Material, but by interchange-in.

On this document	Field	Must show
jumatano__70	Qty Received	30
jumatano__70	Qty Interchanged Out	20
jumatano__70	Warehouse Remaining	10 (30 received – 20 sent to 71)
jumatano__70	Interchange Count	at least 1
Jumatano_71	Qty Interchanged In	20
Jumatano_71	Qty Issued	20
Jumatano_71	Qty Remaining (on site)	20 (issued, not yet consumed)
Jumatano_71	Qty Received (warehouse receive)	0 — do not expect 20 here
The transaction	Original / Issued To	jumatano__70 / Jumatano_71

Expected: jumatano__70 still exists with the original request of 30. Nothing was overwritten.

Step 6 — Use the 20 on Jumatano_71 (consume)

- Open **Jumatano_71** → **Material** → **Consume Material**.
- Original / Issued To = Jumatano_71. Item qty = **20** (or consume in parts).
- Submit. Qty Consumed = 20, Qty Remaining = 0. Process Status = Material Consumed.
- Try Consume 1 more. It must fail (nothing remaining on 71).

Do not Issue MP Stock unless you truly have no received/interchanged qty and must take company warehouse stock.

Step 7 — Finish the leftover 10 on jumatano__70

- Open jumatano__70. Warehouse Remaining should be 10.
- Material → Issue Material. Issued To = **jumatano__70** (same order). Qty = 10. No interchange reason needed.
- Submit. Warehouse Remaining = 0. Qty Issued on 70 includes those 10. Qty Remaining on 70 = 10.
- Material → Consume Material, qty 10. Remaining on 70 = 0.
- Optional: Material → Reconcile (sign-off only, does not move stock).
- Material → Complete Work Order on 70, then on 71.

Step 8 — Reports and dashboard

- Report **SNWO Interchange Report**: one row original jumatano__70, issued to Jumatano_71, qty 20, reason filled.
- Report **SNWO Material Traceability** for 70: received 30, interchanged out 20, warehouse remaining 0 after step 7.
- Traceability for 71: interchanged in 20, issued 20, consumed 20.
- Dashboard tab Interchange / chart Site Interchange: qty 20 in this date range.
- Dashboard Total Work Orders Receive Material counts **sites that received** (70’s Receive). 71’s interchange-in is not a warehouse receive.

Click path (short)

1. New SWO **jumatano__70** qty 30 → Save.
2. New SWO **Jumatano_71** qty 20 → Save.
3. 70 → Material → Receive Material → item 30 → Submit.
4. 70 → Material → Issue Material → Issued To = **Jumatano_71** → qty 20 → Reason → Submit (becomes Interchange).
5. Check 70 remaining 10, 71 interchanged in 20.
6. 71 → Consume 20.
7. 70 → Issue 10 to itself → Consume 10 → Complete both.

Common mistakes

Mistake	What you will see	Do this instead
Receive 20 on Jumatano_71 from warehouse	71 Qty Received = 20, no interchange row	Only Receive on 70. 71 gets stock via Issue to Jumatano_71
Leave Issued To = jumatano__70	Normal Issue on 70, 71 still empty	Set Issued To = Jumatano_71
Interchange qty 30	70 has nothing left; or error if remaining < 30	Send only 20. Keep 10 on 70 unless you intend to send all
Skip interchange reason	Cannot save / submit	Type why 71 is taking from 70
Tick Is MP Stock / Issue MP Stock	Main Warehouse Stock Balance falls	Interchange uses 70's received qty, not MP warehouse
Delete or overwrite jumatano__70	History lost	Never delete the original request

Sign-off

Check	Result	Initial / date
70 received 30 and still exists	■ Pass	
Interchange 20 to 71 submitted with reason	■ Pass	
70 warehouse remaining 10 then 0 after own issue	■ Pass	
71 interchanged in 20, consumed 20, Qty Received still 0	■ Pass	
Interchange report shows 70 → 71 qty 20	■ Pass	
No HTT documents were used	■ Pass	

End of interchange flow. Reconcile is only a sign-off; it does not move the 20. Complete closes each SWO.