Gregorio and gregoriotex: A project which provides tools for gregorian score engraving.

Homepage Source code available on GitHub.

This is a draft document which does not reflect the whole of the package. We are working on making a more complete version.

C	contents		3	Gregorio Controls	15
1	Gregoriotex Macros	1	4	Gregoriotex Controls 4.1 Distances	16 24
2	User Controls 2.1 Using the Package 2.2 Commands	1 1 2	5	Special arguments 5.1 Note Alignment Type .	29 29
	2.3 Distances	8	In	dex	29

1 Gregoriotex Macros

The following sections document the macros available in the gregoriotex package. The format is as follows:

Macroname source file

Arg	Value	Description
Arg #	Data type	Descriptor

The source file where the macro is defined is included for developers who wish to consult it.

Some of the macros intended for inclusion in the main.tex file by the user include usage examples.

2 User Controls

These functions are available to the user to customize elements of the score which cannot be controlled from the gabc file. They can be added to any .tex file. Do not add them to any .gtex or .gabc file.

2.1 Using the Package

To use the gregoriotex package include \usepackage{gregoriotex} in the document preamble. This macro has the following form:

\usepackage[(options)]{gregoriotex}

gregoriotex.sty

The optional arguments are:

Argument	Description
nevercompile	Default. The classic behavior of gregoriotex. The user
	is responsible for compiling gabc scores into gtex files.
autocompile	Gregoriotex will automatically compile gtex files from
	gabc files when necessary. If the gabc has been modified,
	or the gtex has an outdated version, or the gtex file does
	not exist, THEN gregoriotex will compile a new gtex file.
forcecompile	Gregoriotex will compile all scores from their gabc files.

Note: nevercompile, autocompile, and forcecompile conflict with eachother. Only one should be specified in the options list.

2.2 Commands

In general, commands should not be modified. Exceptions are noted below.

\includescore[#1]{#2}

gregoriotex.tex

Macro for including scores. Works on both gabc and tex files.

	Arg	Value	Description
Ī	#1	n	Optional. Bypasses compilation checks.
		С	Optional. Forces gregoriotex to compile the gabc file.
	#2	string	Relative or absolute path to the score.

Example:

```
\includescore[n]{TecumPrincipium.tex}
\includescore{Chant/VirgoVirginum.gabc}
\includescore{/home/user/chant/AdTeLevavi}
\includescore[c]{AveMaria}

%The following lines include the same score:
\includescore{Christus}
\includescore{Christus.gtex}
\includescore{./Christus.gabc}

%With the optional arg, #2 must be a file usable by TeX.
\includescore[n]{TecumPrincipium.gabc} % Wrong
```

For the sake of clarity it is suggested that the file extension be omitted from #2.

When called with the optional argument [c] gregoriotex will automatically generate a gtex file in this format: $scorename-x_x_x$ gtex where x_x is the gregotio version.

When called with the optional argument [n] gregoriotex will include the score without doing anything else. This is the same as the old behavior of gregoriotex and the default behavior.

\forcecompilegabc

gregoriotex.tex

A switch to change the behavior of the way gregoriotex includes scores. When used, all later calls of \includescore will compile the gabc file into a gtex file. This is similar to using the package option [forcecompile], but does not necessarly apply to the entire document.

\autocompilegabc

gregoriotex.tex

A switch to change the behavior of the way gregoriotex includes scores. When used, all later calls of \includescore will use gregoriotex's automatic compilation of gabc files. This is similar to using the package option [autocompile], but does not necessarly apply to the entire document.

\nevercompilegabc

gregoriotex.tex

A switch to change the behavior of the way gregoriotex includes scores. When used, all later calls of \includescore will include the score without doing anything else. This is the same as the traditional behavior of gregoriotex. It is the package default.

The three previous macros can be combined in the same document to switch between the different includescore behaviors:

```
\usepackage{gregoriotex}
----
\includescore{TecumPrincipium} % gabc never compiled.
\includescore[c]{TecumPrincipium} % gabc always compiled.

\autocompile
\includescore{TecumPrincipium} % gabc auto compiled.
\includescore[n]{TecumPrincipium} % gabc never compiled.
\includescore[c]{TecumPrincipium} % gabc always compiled.
\includescore{TecumPrincipium} % gabc auways compiled.
\includescore{TecumPrincipium} % gabc auways compiled.
\includescore[n]{TecumPrincipium} % gabc never compiled.
```

\englishcentering

gregoriotex-syllable.tex

Changes settings to align syllables in the English style (center of syllable aligns with center of first glyph in neume). Will only affect scores which do not have "centering-scheme: english;" in their gabe header.

\defaultcentering

gregoriotex-syllable.tex

Changes settings to align syllables in the Latin style (center of vowel aligns with center of first glyph in neume). Will only affect scores which do not have "centering-scheme: english;" in their gabc header. Default.

\gresetdim{#1}{#2}{#3}

gregoriotex-spaces.tex

Macro to set one of gregoriotex's distances. Does not update dependent distances. Used primarily to initialize distances in a space configuration file. This function if gre prefixed to highlight that it should not be used for distances not defined in GregorioT_FX.

Arg	Value	Description
#1	string	The name of the distance to be changed. See Distances
		below.
#2	string	The distance in string format. Note: You cannot use a
		length register for this argument. You must use a string
		because of the way that gregoriotex handles spaces.
#3	0	Distance will not scale when staff size is changed.
	1	Distance will scale when staff size is changed.

\green the description of description of the desc

gregoriotex-spaces.tex

Macro to change one of gregoriotex's distances and update any dependent distances. This function if gre prefixed to highlight that it should not be used for distances not defined in GregorioTEX.

Arg	Value	Description
#1	string	The name of the distance to be changed. See Distances
		below.
#2	string	The distance in string format. Note: You cannot use a
		length register for this argument. You must use a string
		because of the way that gregoriotex handles spaces.
#3	0	Distance will not scale when staff size is changed.
	1	Distance will scale when staff size is changed.

\grenoscaledim{#1}

 $gregoriotex ext{-}spaces.tex$

Macro to turn off scaling for a particular distance. This function if gre prefixed to highlight that it should not be used for distances not defined in GregorioT_FX.

Arg	Value	Description
#1	string	The name of the distance for which scaling it to be
		turned off. See Distances below.

\grescaledim{#1}

gregoriotex-spaces.tex

Macro to turn on scaling for a particular distance. This function if gre prefixed to highlight that it should not be used for distances not defined in GregorioTEX.

Arg	Value	Description
#1	string	The name of the distance for which scaling it to be
		turned on. See Distances below.

\GreLoadSpaceConf{#1}

 $gregoriotex ext{-}spaces.tex$

Macro to load a space configuration file. Space configuration file names have the format gsp-identifier.tex and must be in the same directory as your project or in your texmf directory. This function if gre prefixed to highlight that it only loads distances for GregorioT_FX.

Arg	Value	Description
#1	string	The identifier of the space configuration file.

Example:

```
% loads gsp-default.tex, the default configuration file
\GreLoadSpaceConf{default}
% loads a custom configuration called gsp-myspaces.tex
\GreLoadSpaceConf{myspaces}
```

\setaboveinitialseparation{#1}{#2}

gregoriotex-spaces.tex

Macro to set the spacing between the annotations.

Arg	Value	Description
#1	string	The distance in string format. Note: You cannot use a
		length register for this argument. You must use a string
		because of the way that gregoriotex handles spaces.
#2	0	Distance will not scale when staff size is changed.
	1	Distance will scale when staff size is changed.

Warning: This function formerly had only one arguments. It now takes 2. Deprecated version: \GreSetAboveInitialSeparation which only took the first argument. If you use the deprecated command the second argument will be assumed to be 1.

\setspaceafterinitial{#1}{#2}

qreqoriotex-spaces.tex

Macro to set the spacing after the initial (and before the staff lines).

Arg	Value	Description
#1	string	The distance in string format. Note: You cannot use a
		length register for this argument. You must use a string
		because of the way that gregoriotex handles spaces.
#2	0	Distance will not scale when staff size is changed.
	1	Distance will scale when staff size is changed.

Warning: This function formerly had only one arguments. It now takes 2. Deprecated version: \GreSetSpaceAfterInitial which only took the first argument. If you use the deprecated command the second argument will be assumed to be 1.

\setspacebeforeinitial{#1}{#2}

qreqoriotex-spaces.tex

Macro to set the spacing before the initial.

Arg	Value	Description
#1	string	The distance in string format. Note: You cannot use a
		length register for this argument. You must use a string
		because of the way that gregoriotex handles spaces.
#2	0	Distance will not scale when staff size is changed.
	1	Distance will scale when staff size is changed.

Warning: This function formerly had only one arguments. It now takes 2. Deprecated version: \GreSetSpaceBeforeInitial which only took the first argument. If you use the deprecated command the second argument will be assumed to be 1.

$\left\{ 1\right\}$

gregoriotex-spaces.tex

Macro to set the spacing around and for the initial.

#1 string The distance before the initial in string format.	Note:
You cannot use a length register for this argumen	nt. You
must use a string because of the way that greg	goriotex
handles spaces.	
#2 string The distance for the initial in string format. T	his dis-
tance is ignored if set to 0pt. Note: You cannot	ot use a
length register for this argument. You must use a	a string
because of the way that gregoriotex handles spa-	ces.
#3 string The distance after the initial in string format.	Note:
You cannot use a length register for this argument	nt. You
must use a string because of the way that greg	goriotex
handles spaces.	
#4 0 Distance will not scale when staff size is changed	d.
1 Distance will scale when staff size is changed.	

Warning: This function formerly had only three arguments. It now takes 4.

\setstafflinethickness{#1}

gregoriotex-spaces.tex

Macro to adjust the thickness of the staff lines.

Arg	Value	Description
#1	integer	The relative thickness of the staff lines. The default
		value is 10. Higher numbers yield thicker staff lines.

Deprecated version: \gresetstafflinefactor.

2.3 Distances

Each of the following distances controls some aspect of the spacing of the Gregorio score. They are changed using commands documented above (e.g. \changedim). If the distance permits a rubber value then the default value will indicate the stretch and shrink (even if they are zero by default). Distances whose default value does not include a stretch or shrink may not take a rubber value.

Note: Because of the way Gregorio handles distances these cannot be manipulated as if they were normal TeX dimensions or skips. As a result they should only be changed using the commands defined by gregoriotex for this purpose.

additionallineswidth

qsp-default.tex

The additional width of the additional lines (compared to the width of the glyph they're associated with).

Default: $0.14584 \,\mathrm{cm}$

alterationspace

qsp-default.tex

Space between an alteration (flat or natural) and the next glyph.

Default: 0.07747 cm plus 0.01276 cm minus 0.00455 cm

beforealterationspace

gsp-default.tex

Negative space, difference between the normal space between two notes and the space between a note and a flat.

Default: $-0.32816 \,\mathrm{cm}$ plus $0.01093 \,\mathrm{cm}$ minus $0.01093 \,\mathrm{cm}$

beforechoralsignspace

gsp-default.tex

Space before a choral sign.

Default: $0.04556 \,\mathrm{cm}$ plus $0.00638 \,\mathrm{cm}$ minus $0.00638 \,\mathrm{cm}$

 ${\it clefflatspace} \hspace{3cm} {\it gsp-default.tex}$

Space between a clef and a flat (for clefs with flat). Default: 0.05469 cm plus 0.00638 cm minus 0.00638 cm

 ${\it interglyphspace} \hspace{3cm} {\it gsp-default.tex}$

Space between glyphs in the same element.

Default: $0.06927\,\mathrm{cm}$ plus $0.00363\,\mathrm{cm}$ minus $0.00363\,\mathrm{cm}$

 ${\tt zerowidthspace} \hspace{3cm} \textit{gsp-default.tex}$

Null space.

Default: 0 cm plus 0 cm minus 0 cm

interelementspace qsp-default.tex

Space between elements.

Default: $0.06927 \,\mathrm{cm}$ plus $0.00182 \,\mathrm{cm}$ minus $0.00363 \,\mathrm{cm}$

largerspace gsp-default.tex

Larger space between elements.

Default: $0.10938\,\mathrm{cm}$ plus $0.01822\,\mathrm{cm}$ minus $0.00911\,\mathrm{cm}$

 ${\tt glyphspace} \hspace{3cm} {\it gsp-default.tex}$

Space between elements which has the size of a note. Default: 0.21877 cm plus 0.01822 cm minus 0.01822 cm

 ${\it intersyllable space} \hspace{3cm} {\it gsp-default.tex}$

Minimum space between two notes of different syllables.

Default: $0.25523 \,\mathrm{cm}$ plus $0.31903 \,\mathrm{cm}$ minus $0 \,\mathrm{cm}$

spacebeforecusto gsp-default.tex

Space before custo.

Default: $0.1823 \,\mathrm{cm}$ plus $0.31903 \,\mathrm{cm}$ minus $0.0638 \,\mathrm{cm}$

spacebeforesigns

qsp-default.tex

Space before punctum mora and augmentum duplex. Default: 0.05469 cm plus 0.00455 cm minus 0.00455 cm

spaceaftersigns

qsp-default.tex

Space after punctum mora and augmentum duplex. Default: $0.08203\,\mathrm{cm}$ plus $0.0082\,\mathrm{cm}$ minus $0.0082\,\mathrm{cm}$

spaceafterlineclef

gsp-default.tex

Space after a clef at the beginning of a line.

Default: $0.27345\,\mathrm{cm}$ plus $0.14584\,\mathrm{cm}$ minus $0.01367\,\mathrm{cm}$

interwordspacenotes

qsp-default.tex

Space after at the end of a word when the last written symbol is a note and the first is a note.

Default: $0.29169 \,\mathrm{cm}$ plus $0.08751 \,\mathrm{cm}$ minus $0.05469 \,\mathrm{cm}$

interwordspacenotestext

qsp-default.tex

Space after at the end of a word when the last written symbol is a note and the first is text.

Default: $0.27345 \,\mathrm{cm}$ plus $0.27345 \,\mathrm{cm}$ minus $0.07292 \,\mathrm{cm}$

interwordspacetextnotes

qsp-default.tex

Space after at the end of a word when the last written symbol is text and the first is a note.

Default: $0.27345\,\mathrm{cm}$ plus $0.27345\,\mathrm{cm}$ minus $0.07292\,\mathrm{cm}$

interwordspacetext

qsp-default.tex

Space after at the end of a word when the last written symbol is text and the first is text.

Default: $0.22787 \,\mathrm{cm}$ plus $0.41019 \,\mathrm{cm}$ minus $0.07292 \,\mathrm{cm}$

bitrivirspace

qsp-default.tex

Space between notes of a bivirga or trivirga.

Default: $0.06927 \,\mathrm{cm}$ plus $0.00182 \,\mathrm{cm}$ minus $0.00546 \,\mathrm{cm}$

bitristrospace

qsp-default.tex

Space between notes of a bistropha or tristrophae. Default: 0.06927 cm plus 0.00182 cm minus 0.00546 cm

punctuminclinatumshift

qsp-default.tex

Space between two punctum inclinatum.

Default: $-0.03918\,\mathrm{cm}$ plus $0.0009\,\mathrm{cm}$ minus $0.0009\,\mathrm{cm}$

beforepunctainclinatashift

qsp-default.tex

Space before puncta inclinata.

Default: $0.05286 \,\mathrm{cm}$ plus $0.00728 \,\mathrm{cm}$ minus $0.00455 \,\mathrm{cm}$

punctuminclinatumanddebilisshift

gsp-default.tex

Space between a punctum inclinatum and a punctum inclinatum deminutus. Default: $-0.02278\,\mathrm{cm}$ plus $0.0009\,\mathrm{cm}$ minus $0.0009\,\mathrm{cm}$

punctuminclinatumdebilisshift

gsp-default.tex

Space between two punctum inclinatum deminutus. Default: $-0.00728 \,\mathrm{cm}$ plus $0.0009 \,\mathrm{cm}$ minus $0.0009 \,\mathrm{cm}$

punctuminclinatumbigshift

qsp-default.tex

Space between puncta inclinata, larger ambitus (range=3rd).

Default: $0.07565\,\mathrm{cm}$ plus $0.0009\,\mathrm{cm}$ minus $0.0009\,\mathrm{cm}$

punctuminclinatummaxshift

qsp-default.tex

Space between puncta inclinata, larger ambitus (range=4th -or more?-).

Default: $0.17865 \,\mathrm{cm}$ plus $0.0009 \,\mathrm{cm}$ minus $0.0009 \,\mathrm{cm}$

${\tt space around small bar}$

qsp-default.tex

Space around virgula and divisio minima.

Default: 0.1823 cm plus 0.22787 cm minus 0.05469 cm

spacearoundminor

gsp-default.tex

Space around divisio minor.

Default: $0.1823\,\mathrm{cm}$ plus $0.22787\,\mathrm{cm}$ minus $0.05469\,\mathrm{cm}$

spacearoundmaior

qsp-default.tex

Space around divisio maior.

Default: $0.1823 \,\mathrm{cm}$ plus $0.22787 \,\mathrm{cm}$ minus $0.05469 \,\mathrm{cm}$

spacearoundfinalis

gsp-default.tex

Space around divisio finalis.

Default: $0.1823\,\mathrm{cm}$ plus $0.1823\,\mathrm{cm}$ minus $0.05469\,\mathrm{cm}$

spacebeforefinalfinalis

gsp-default.tex

A special space for finalis, for when it is the last glyph. Default: 0.29169 cm plus 0.07292 cm minus 0.27345 cm

spacearoundclefbars

qsp-default.tex

Additional space that will appear around bars that are preceded by a custo and followed by a key.

Default: $0.03645 \,\mathrm{cm}$ plus $0.00455 \,\mathrm{cm}$ minus $0.0009 \,\mathrm{cm}$

textbartextspace

qsp-default.tex

Space between the text and the text of the bar.

Default: 0.24611 cm plus 0.13672 cm minus 0.04921 cm

notebarspace

qsp-default.tex

Minimal space between a note and a bar.

Default: $0.31903\,\mathrm{cm}$ plus $0.27345\,\mathrm{cm}$ minus $0.02824\,\mathrm{cm}$

${\tt maximumspacewithoutdash}$

gsp-default.tex

Maximal space between two syllables for which we consider a dash is not needed.

Default: $0.02005 \,\mathrm{cm}$

afterclefnospace

qsp-default.tex

An extensible space for the beginning of lines.

Default: $0 \,\mathrm{cm}$ plus $0.27345 \,\mathrm{cm}$ minus $0 \,\mathrm{cm}$

additionalcustoslineswidth

gsp-default.tex

Width of the additional lines, used only for the custos. The width is the one for the custos at end of lines, the line for custos in the middle of a score is the same multiplied by 2.

Default: 0.09114 cm

afterinitialshift

gsp-default.tex

Space between the initial and the beginning of the score.

Default: $0.2457 \,\mathrm{cm}$ plus $0 \,\mathrm{cm}$ minus $0 \,\mathrm{cm}$

beforeinitialshift

gsp-default.tex

Space between the initial and the beginning of the score.

Default: 0.2457 cm plus 0 cm minus 0 cm

minimalspaceatlinebeginning

gsp-default.tex

Minimal space at the beginning of a line.

Default: 1.7 cm

manualinitialwidth

gsp-default.tex

Space to force the initial width to. Ignored when 0.

Default: 0 cm

aboveinitialseparation

gsp-default.tex

This space is the one between the bottom of the first annotation line and the top of the second annotation line (above the initial).

Default: 0.85 cm

 ${\tt noclefspace} \hspace{3cm} \textit{gsp-default.tex}$

Space at the beginning of the lines if there is no clef.

Default: 0.1 cm

 $a {\tt bovesignsspace} \hspace{3cm} \textit{gsp-default.tex}$

Space above the chironomic signs.

Default: 0.8 cm

 $belowsignsspace \hspace{3.1cm} \textit{gsp-default.tex}$

Space below the chironomic signs.

Default: 0 cm

 ${\tt lowchoral signshift} \hspace{3cm} \textit{gsp-default.tex}$

The shift for the low choral sign and the high choral signs on totally free interlines.

Default: 0.00911 cm

 $high choral signshift \hspace{3cm} \textit{gsp-default.tex}$

The shift for the high choral sign.

Default: $-0.04556 \,\mathrm{cm}$

 $translation \texttt{height} \hspace{3cm} \textit{gsp-default.tex}$

The space for the translation.

Default: 0.5 cm

spaceabovelines gsp-default.tex

The space above the lines.

Default: $0.45576 \,\mathrm{cm}$ plus $0.36461 \,\mathrm{cm}$ minus $0.09114 \,\mathrm{cm}$

spacelinestext

gsp-default.tex

The space between the lines and the bottom of the text.

Default: $0.60617 \,\mathrm{cm}$ plus $0 \,\mathrm{cm}$ minus $0 \,\mathrm{cm}$

spacebeneathtext

gsp-default.tex

The space beneath the text.

Default: 0 cm plus 0 cm minus 0 cm

abovelinestextraise

gsp-default.tex

Height of the text above the note line.

Default: 1.7 cm

abovelinestextheight

gsp-default.tex

Height that is added at the top of the lines if there is text above the lines (it must be bigger than the text for it to be taken into consideration).

Default: 0.3 cm

 ${\it braceshift} \hspace{3cm} {\it gsp-default.tex}$

An additional shift you can give to the brace above the bars.

Default: 0 cm

curlybraceaccentusshift

qsp-default.tex

A shift you can give to the accentus above the curly brace.

Default: $-0.05 \,\mathrm{cm}$

3 Gregorio Controls

These functions are the ones written by Gregorio to the gtex file. While one could, in theory, use/change them to alter the appearance of elements of the score, it is far better to make your changes in the gabc file and let Gregorio make the changes to the gtex file.

\grefirstlinebottomspace#1#2

 $gregoriotex ext{-}spaces.tex$

Macro for calculating the additional space needed below the first line of the score.

Arg	Value	Description
#1	0	no notes below the staff
	1	note below the first staff line (c position)
	2	note on the 0 staff line (b position)
	3	note below the 0 staff line (a position)
#2	1	there is a translation below the text
	0	there is no translation below the text

4 Gregoriotex Controls

These functions are the ones used by Gregoriotex internally as it process the commands listed above. They should not appear in any user document and are listed here for programmer documentation purposes only.

\gre@calculate@constantglyphraise

qreqoriotex-spaces.tex

Macro to caluclate \gre@constantglyphraise

\gre@addtranslationspace

gregoriotex-spaces.tex

Macro to tell Gregorio to set space for the translation.

\gre@removetranslationspace

gregoriotexspaces.tex

Macro to tell Gregorio to remove the space allocated to the translation.

\gre@calculate@additionalspaces#1#2

gregoriotex-spaces.tex

Macro which calculates \gre@additionalbottomspace and \gre@additionaltopspace

Arg	Value	Description
#1	0	no note above staff
	1	note above 4th line (position k)
	2	note on 5th line (position l)
	3	note above 5th line (position m)
#2	0	no note below staff
	1	note below 1st line (position c)
	2	note on 0th line (position b)
	3	note below 0th line (position a)
	4	note below 0th line (position a) with vertical episemus

\gre@calculate@textaligncenter#1#2#3

 $gregoriotex ext{-}spaces.tex$

Macro for calculating \gre@textaligncenter.

Arg	Value	Description
#1	string	The first part of the syllable (any preceding consonants
		in Latin).
#2	string	The middle part of the syllable (the vowel in Latin, the
		whole syllable in English).
#3	0	Calculation is being performed for the current syllable.
	1	Calculation is being performed for the next syllable.

\gre@calculate@aboveinitialraise

gregoriotex.tex

Macro to give \gre@aboveinitialfirstraise and \gre@aboveinitialsecondraise their working values.

\gre@englishcentering

gregoriotex-syllable.tex

Count to track if we are using english centering scheme (1), or not (0).

\gre@calculate@textlower

 $gregoriotex ext{-}spaces.tex$

Calculates the default value of textlower. Default is spacebeneathtext.

\gre@calculate@linewidth

gregoriotex-spaces.tex

Calculates the default line width. Default is the width of the printable space (\hsize).

\gre@calculate@stafflinewidth

gregoriotex-spaces.tex

Calculates the default width of the staff lines. Default is linewidth.

\gre@calculate@stafflineheight

gregoriotex-spaces.tex

Calculates the height (thickness) of the staff lines. Dependent on stafflineheightfactor and grefactor.

\gre@calculate@interstafflinespace

gregoriotex-spaces.tex

Calculates the distance between the staff lines. Dependent on stafflineheight and grefactor

\gre@calculate@stafflinediff

gregoriotex-spaces.tex

Calculates a correction factor for when the staff lines are not their default thickness. Dependent on stafflineheight and grefactor.

\gre@calculate@staffheight

gregoriotex-spaces.tex

Calculates the total height of the staff. Dependent on stafflineheight and interstafflinespace.

\gre@calculate@constantglyphraise

gregoriotex-spaces.tex

Calculates the baseline correction for the glyphs. Dependent on grefactor, additionalbottomspace, spacebeneathtext, spacelinestext, interstafflinespace, stafflineheight, currenttranslationheight, and stafflinediff.

\gre@computespaces

gregoriotex-spaces.tex

Aggregates all of the global distance calculations and calls them in the order needed to respect dependencies.

\gre@calculate@glyphraisevalue#1#2

 $gregoriotex ext{-}spaces.tex$

Calculates the raise values for a glyph (glyphraisevalue and addedraisevalue) based on where it is to be placed and what kind of a glyph it is. This is a time of use calculation.

Arg	Value	Description
#1	integer	The number for where the glyph is located. a in gabc is
		1, b is 2, etc.
#2	0	no modification
	1	puts the value on the interline just above if it is on a
		line
	2	puts the value on the interline just beneath if it is on a
		line
	3	case of the vertical episemus, which is not placed at the
		same place if the corresponding note is on a line or not
	4	case of the punctum mora, for the same reason
	5	case of the horizontal episemus under a note, that must
		be placed a bit lower if the note is on a line
	6	case of the signs above (accentus, etc.)
	8	case of the punctum mora of the first note of a podatus
		or the 2nd note of a porrectus, etc.
	9	case of the horizontal episemus, that must be placed a
		bit lower if the note is on a line
	10	case of the low choral sign
	11	case of the high choral sign
	12	case of the low choral sign which is lower than the note
	13	case of the brace above the bars

\gre@stafflinefactor

 $gregoriotex ext{-}spaces.tex$

A number indicating the thickness of the staff lines.

\gre@scale@stafflinefactor

 $gregoriotex ext{-}spaces.tex$

Flag indicating whether the staffline factor should scale with changes of grefactor (1), or not (0).

\gre@calculate@additionalspaces#1#2

 $gregoriotex ext{-}spaces.tex$

Calculates the extra spaces above and below the staff lines. This is a time of use calculation.

Arg	Value	Description	
#1	0	no notes above the staff	
	1	there is a note above the 4th line	
	2	there is a note on the 5th line	
	3	there is a note above the 5th line	
#2	0	no notes below the staff	
	1	there is a note below the 1st line	
	2	there is a note on the 0th line	
	3	there is a note below the 0th line	
	4	there is a note below the 0th line with a vertical episemus	
		attached	

\gre@calculate@textaligncenter#1#2#3

gregoriotex-spaces.tex

Macro to calculate the distance from the beginning of the text of a syllable to its alignment point (the center of the vowel for Latin centering, the center of the syllable for English centering). This is a time of use calculation.

Arg	Value	Description
#1	string	the first part of the syllable
#2	string	the middle part of the syllable
#3	0	perform this calculation for the current syllable
	1	perform this calculation for the next syllable

\gre@calculate@enddifference#1#2#3#4#5

 $gregoriotex ext{-}spaces.tex$

Calculates the difference between the end of the notes and the end of the syllable text. Also stores the value for the previous syllable if needed. This is a time of use calculation.

Arg	Value	Description	
#1	length	the total width of the notes	
#2	length	the total width of the syllable text	
#3	length	the alignment distance for the text (textaligncenter)	
#4	length	the alignment distance for the notes	
		(notesaligncenter)	
#5	0	do not save the value for the previous syllable before	
		calculating the new value	
	1	save the value for the previous syllable before calculating	
		the new value	

\gre@changeonedimenfactor#1#2#3

 $gregoriotex ext{-}spaces.tex$

Change the scale of a single distance from one factor to another.

Arg	Value	Description	
#1	string	name of the distance to be scaled. See Distances.	
#2	integer	the factor the distance is currently in	
#3	integer	the factor the distance is to be put into	

\gre@changedimenfactor#1#2

 $gregoriotex ext{-}spaces.tex$

Rescales all the distances (and stafflinefactor) which are supposed to scale with a change in factor.

Arg	Value	Description
#1	integer	the factor the distance is currently in
#2	integer	the factor the distance is to be put into

 $\verb|\gre@calculate@nextbegindifference#1#2#3#4 | gregoriotex-spaces.tex|$

Macro to calculate nextbegindifference.

Arg	y Value	Description
#1	string	the first letters of the next syllable
#2	string	the middle letters of the next syllable (the vowel in
		Latin, the whole syllable in English)
#3	string	the end letters of the next syllable
#4	0 < integer < 19	the type of notes alignment. See Note Alignment Type.
	20 < integer < 39	Same as below 20 except there is a flat before the notes.
		Subtract 20 to get the type of notes alignment.
	40 < integer < 59	Same as below 20 except there is a natural before the
		notes. Subtract 40 to get the type of notes alignment.

\gre@tempdimcount

 $gregoriotex ext{-}spaces.tex$

Temporary count used in calculations.

\ifchecklength

 $gregoriotex ext{-}spaces.tex$

Boolean flag used in \gresetdim to indicate if we are attempting to set a rubber length.

\ifbadlength

 $gregoriotex ext{-}spaces.tex$

Boolean flag used in \gresetdim to indicate that we are attempting to assign a rubber length to a distance which cannot accept a rubber value.

\ifrubber

 $gregoriotex ext{-}spaces.tex$

Boolean flag used in \gre@changeonedimenfactor to indicate if we are dealing with one of the distances which can accept a rubber length.

\gre@makein#1

 $gregoriotex ext{-}spaces.tex$

Strips the decimals and units from a distance.

Arg	Value	Description
#1	distance	should be in the form "[0-9]+.[0-9]+pt". (i.e. the result
		of applying \the to a distance register)

\gre@makenum#1

 $gregoriotex ext{-}spaces.tex$

Strips the units from a distance.

Arg	Value	Description
#1	distance	should be in the form "[0-9]+.[0-9]+pt". (i.e. the result
		of applying \the to a distance register)

\gre@unitfactor

 $gregoriotex ext{-}spaces.tex$

Temporary count used by \gre@convertto.

\gre@basefactor

gregoriotex-spaces.tex

Temporary count used by \gre@convertto.

\gre@temp@count@one

gregoriotex-spaces.tex

Temporary count used by \gre@convertto.

\gre@convertto#1#2

gregoriotex-spaces.tex

Macro which converts a distance into a particular set of units. Result is placed in \gre@converted as a string.

Arg	Value	Description
#1	string	two letter abbreviation for the units. Should recognize
		all legal TeX units.
#2	distance	Distance to be converted.

\gre@converted

 $gregoriotex\hbox{-}spaces.tex$

Macro holding result of last call to \gre@convertto.

\gre@consistentunits#1#2

 $gregoriotex ext{-}spaces.tex$

This function takes a distance and formats it as a string so that its units conform to the pattern set by a string representation of a distance. Result is placed in \gre@stringdist.

Arg	Value	Description
#1	string	the standard whose format is to be matched.
#2	distance	the distance to be adjusted.

\gre@stringdist

gregoriotex-spaces.tex

Macro holding result of last call to \gre@consistentunits.

\gre@temp@count@two

 $gregoriotex ext{-}spaces.tex$

Temporary count used by \gre@changedimenfactor.

\gre@includescore#1

gregoriotex.tex

Macro that handles \includescore calls when they do not have an optional argument.

Arg	Value	Description
#1	string	Relative or absolute path to the score.

\gre@includescorewithoption[#1]#2

gregoriotex.tex

Macro that handles \includescore calls when they have an optional argument.

	Arg	Value	Description
Ī	#1	n	Optional. Bypasses compilation checks.
		С	Optional. Forces gregoriotex to compile the gabc file.
	#2	string	Relative or absolute path to the score.

4.1 Distances

All of the distances listed in Distances have two internals associated with them. These take the form of \gre@* and \gre@scale@*. The first stores the value of the distance (in string representation). The second is a numerical flag which indicates if the distance should scale when the staff size changes (1) or not (0).

These additional distances are calculated by Gregorio based on the values for the user customizable distances and what may be going on in the score at the time of their use.

\gre@clefwidth

 $gregoriotex ext{-}spaces.tex$

Width of the clef.

\gre@tempdimsignwidth

gregoriotex-spaces.tex

Temporary dimension used to calculate placement of signs.

gre@tempdimtwo

gregoriotex-spaces.tex

A temporary dimension used in calculations.

\gre@constantglyphraise

gregoriotex-spaces.tex

Dimension representing the space between the 0 of the gregorian fonts and the effective 0 of the TeX score.

\gre@currenttranslationheight

qreqoriotex-spaces.tex

Dimension representing the space for the translation beneath the text.

\gre@stafflinewidth

gregoriotex-spaces.tex

Dimension representing the width of a line of staff. Can vary, for example, at the first line.

\gre@linewidth

 $gregoriotex ext{-}spaces.tex$

Dimension representing the width of the score (including initial).

\gre@additionalbottomspace

gregoriotex-spaces.tex

Dimension representing extra space below the staff needed for low notes.

\gre@additionaltopspace

qreqoriotex-spaces.tex

Dimension representing extra space above the staff needed for high notes.

\gre@textlower

 $gregoriotex ext{-}spaces.tex$

Dimension representing the height of the separation between the 0th line (which is invisible except for notes in the a or b position) and the bottom of the text.

\gre@tempwidth

gregoriotex-spaces.tex

Dimension representing width of some element.

\gre@textaligncenter

gregoriotex-spaces.tex

Dimension representing the width from the beginning of the letters in a syllable to the middle of the middle letters. Used for lining up neumes and syllables.

\gre@additionalleftspace

gregoriotex-spaces.tex

Dimension representing the additional space that has to be added to the localleftbox for a big initial (one taking two lines).

\gre@initialwidth

gregoriotex-spaces.tex

Dimension representing the width of the initial (and the space after).

\gre@aboveinitialfirstraise

gregoriotex-spaces.tex

Dimension representing the space allocated to the first annotation.

\gre@aboveinitialsecondraise

gregoriotex-spaces.tex

Dimension representing the space allocated to the second annotation.

\gre@currentabovelinestextheight

 $gregoriotex ext{-}spaces.tex$

Dimension representing the space allocated above the lines for text.

\gre@staffheight

gregoriotex-spaces.tex

The total height of the staff including the width of the lines and the spaces between them.

\gre@stafflinediff

 $gregoriotex ext{-}spaces.tex$

Distance representing the difference between the actual size of the staff lines and the "standard" size.

\gre@stafflineheight

gregoriotex-spaces.tex

The height of the staff line.

\gre@interstafflinespace

gregoriotex-spaces.tex

The space between the lines.

\gre@glyphraisevalue

gregoriotex-spaces.tex

The value that a particular glyph must be raised to be set in the correct position.

\gre@addedraisevalue

qreqoriotex-spaces.tex

The additional raise needed for the vertical episema and the puncta.

\gre@enddifference

qreqoriotex-spaces.tex

Distance from the end of the notes to the end of the text for the previous syllable. Positive values when notes go further than text, negative in the other case.

\gre@previousenddifference

qreqoriotex-spaces.tex

Stored value of enddifference prior to the current one.

\gre@nextbegindifference

 $gregoriotex ext{-}spaces.tex$

The difference between the start of the notes and the start of the text for the next syllable. Positive when when text begins first, negative in other case.

\gre@begindifference

 $gregoriotex ext{-}spaces.tex$

The difference between the start of the notes and the start of the text for the current syllable. Positive when when text begins first, negative in other case.

\gre@lastglyphwidth

qreqoriotex-spaces.tex

The width of the last glyph.

\gre@notesaligncenter

gregoriotex-spaces.tex

Distance from beginning of notes to their point of alignment.

\gre@tempdim

 $gregoriotex ext{-}spaces.tex$

Temporary dimension used in calculations.

\gre@tempdimskip

qreqoriotex-spaces.tex

Temporary skip used in calculations.

\gre@skipone

qregoriotex-spaces.tex

Temporary skip used in calculations.

\gre@temp

gregoriotex-spaces.tex

Temporary skip used in calculations.

\gre@temp@dimen@one

gregoriotex-spaces.tex

Temporary dimension used in calculations.

\gre@temp@skip@one

 $gregoriotex ext{-}spaces.tex$

Temporary skip used in calculations.

\gre@unit

 $gregoriotex ext{-}spaces.tex$

Temporary dimension used by \gre@convertto.

\gre@base

qreqoriotex-spaces.tex

Temporary dimension used by \gre@convertto.

\gre@maxlen

qreqoriotex-spaces.tex

Distance holding the maximum legal length in TeX.

5 Special arguments

These arguments are used by multiple functions and take a lot of space to describe so we describe them once here and refer to this section rather than have multiple definitions.

5.1 Note Alignment Type

Integer with the following possibilities:

- 0 one-note glyph or more than two notes glyph except porrectus: here we must put the alignmenter in the middle of the first note
- two notes glyph (podatus is considered as a one-note glyph) : here we put the alignmenter in the middle of the glyph
- 2 porrectus: has a special align center
- 3 initio-debilis: same as 1 but the first note is much smaller
- 4 case of a glyph starting with a quilisma
- 5 case of a glyph starting with an oriscus
- 6 case of a punctum inclinatum
- 7 case of a stropha
- 8 flexus with an ambitus of one
- 9 flexus deminutus
- 10 virgula
- 11 divisio minima, minor and maior
- 12 divisio finalis