

Lab 2 - Configuring Basic Single-Area OSPFv2

Answer Sheet

Name: Chan Hin Yeung

Student ID: 21074786D

Part 2: Configure and Verify OSPF Routing

Step 1: Verify OSPF neighbors and routing information.

b.

What command would you use to only see the OSPF routes in the routing table?

Show ip route ospf

Part 4: Configure OSPF Passive Interfaces

- g. Re-issue the **show ip route** and **show ip ospf neighbor** commands on R1 and R3, and look for a route to the 192.168.2.0/24 network.

What interface is R3 using to route to the 192.168.2.0/24 network? S0/0/0

What is the accumulated cost metric for the 192.168.2.0/24 network on R3? 129

Does R2 show up as an OSPF neighbor on R1? Yes

Does R2 show up as an OSPF neighbor on R3? No

What does this information tell you?

All traffic to 192.168.2.0/24 from R3 will be routed via R1. The S0/0/1 interface on R2 is still configured as a passive interface, so OSPF routing information is not being advertised across the interface. The 129 accumulated cost is derived from the fact that traffic from R3 to the 192.168.2.0/24 network must pass through two T1 serial links plus the R2 Gigabit 0/0 LAN link (at a cost of 1).

- h. Change interface S0/0/1 on R2 to allow it to advertise OSPF routes. Record the commands used below.

R2(config) # router ospf 1

R2(config-router) # no passive-interface s0/0/1

- i. Re-issue the **show ip route** command on R3.

What interface is R3 using to route to the 192.168.2.0/24 network? S0/0/1

What is the accumulated cost metric for the 192.168.2.0/24 network on R3 now and how is this calculated?

65 (One T1 (1.544 Mb/s) serial link plus the R2 Gigabit 0/0 LAN.

Is R2 listed as an OSPF neighbor to R3? Yes

Part 5: Change OSPF Metrics

Step 1: Change the reference bandwidth on the routers.

- a. To reset the reference-bandwidth back to its default value, issue the **auto-cost reference-bandwidth 100** command on all three routers.

```
R1(config)# router ospf 1
R1(config-router)# auto-cost reference-bandwidth 100
% OSPF: Reference bandwidth is changed.
Please ensure reference bandwidth is consistent across all routers.
```

Formatted: Centred

Why would you want to change the OSPF default reference-bandwidth?

Because networking devices nowadays can support faster link speed than 100 Mb/s, therefore a higher default reference-bandwidth setting is needed in order to obtain a more accurate cost calculation.

Step 2: Change the bandwidth for an interface.

- g. Explain how the costs to the 192.168.3.0/24 and 192.168.23.0/30 networks from R1 were calculated.

The cost to 192.168.3.0/24: R1 S0/0/1 + R3 G0/0 (781+1=782). The cost to 192.168.23.0/30: R1 S0/0/1 and R3 S0/0/1 (781+64=845).

- i. Issue the **bandwidth 128** command on all remaining serial interfaces in the topology.

What is the new accumulated cost to the 192.168.23.0/24 network on R1? Why?

1,562. Each serial link now has a cost of 781, and the route to the 192.168.23.0/24 network travels over two serial links. 781 + 781 = 1,562.

Step 3: Change the route cost.

- c.

Explain why the route to the 192.168.3.0/24 network on R1 is now going through R2?

OSPF will choose the route with the least accumulated cost. The route with the lowest accumulated cost is: R1-S0/0/0 + R2-S0/0/1 + R3-G0/0, or 781 + 781 + 1 = 1,563. This metric is smaller than the accumulated cost of R1-S0/0/1 + R3-G0/0, or 1565 + 1 = 1,566.

Formatted: Centred

Lab - Configuring Basic Single-Area OSPFv2

Reflection

1. Why is it important to control the router ID assignment when using the OSPF protocol?

Router ID assignments control the Designated Router (DR) and Backup Designated Router (BDR) election process on a multi-access network. If the router ID is associated with an active interface, it can change if the interface goes down. For this reason it should be set using the IP address of a loopback interface (which cannot go down) or set using the router-id command.

4

2. Why is the DR/BDR election process not a concern in this lab?

The DR/BDR election process is only an issue on a multi-access network such as Ethernet or Frame Relay. The serial links used in this lab are point-to-point links, so no DR/BDR election is performed.

4

3. Why would you want to set an OSPF interface to passive?

Answers will vary, but configuring a LAN interface as passive eliminates unnecessary OSPF routing information on that interface, freeing up bandwidth. The router will still advertise the network to its neighbors.

4

4. What aspect of OSPF makes the protocol hierarchical and permits the creation of very scalable networks?

The aspect of OSPF that makes it hierarchical and highly scalable is the use of Areas.

4

5. What single OSPF router configuration command allows the assignment of OSPF area 0 to all interfaces in the range 10.0.0.0 to 10.255.255.255?

To assign OSPF area 0 to all interfaces in the 10.0.0.0 to 10.255.255.255 range (which is effectively the 10.0.0.0/8 network), you would use the following single configuration command in router configuration mode: "network 10.0.0.0 0.255.255.255 area 0"

4

6. A router has three routes to the same network: one route from a RIP with a metric of 4, another from OSPF with a metric of 3053092, and another from EIGRP with a metric of 4039043. Which of the three routes will be used for the routing decision?

The router will choose the EIGRP route. Because When a router receives routes to the exact same destination network from different routing protocols, it does not compare their metrics. Metrics are only used to choose between multiple paths within the same routing protocol. Instead, the router uses Administrative Distance (AD) to break the tie, selecting the protocol it considers most trustworthy (the one with the lowest AD).

4

Here are the default Administrative Distances for these protocols:

- EIGRP (Internal): 90
- OSPF: 110
- RIP: 120

Since EIGRP has the lowest AD of the three, its route will be placed into the routing table.