Chapter 4

Nouman M Durrani

Data Transfer Instructions

Operand Types

x86 instruction formats:

```
[label:] mnemonic [operands][; comment]
```

Because the number of operands may vary, we can further subdivide the formats to have zero, one, two, or three operands

```
mnemonic [ destination]
mnemonic [ destination],[source]
mnemonic [destination],[source-1],[source-2]
```

To give added flexibility to the instruction set, x86 assembly language uses different types of instruction operands.

- Immediate—uses a numeric literal expression
- Register—uses a named register in the CPU
- Memory—references a memory location

MOV Instruction

- The MOV instruction copies data from a source operand to a destination operand.
- Its basic format shows that the first operand is the destination and the second operand is the source:

MOV destination, source

Here is a list of the general variants of MOV, excluding segment registers:

```
MOV reg, reg
MOV mem, reg
MOV reg, mem
MOV mem, imm
MOV reg, imm
```

Segment registers should not be directly modified by programs running in protected mode. The following options are available when running in real mode, with the exception that CS cannot be a target operand:

```
MOV reg/mem16, sreg
MOV sreq, reg/mem16
```

Memory to Memory A single MOV instruction cannot be used to move data directly from one memory location to another. Instead, you must move the source operand's value to a register before moving its value to a memory operand:

```
.data
var1 WORD ?
var2 WORD ?
.code
mov ax,var1
mov var2,ax
```

Overlapping Values:

```
.data
oneByte BYTE 78h
oneWord WORD 1234h
oneDword DWORD 12345678h
```

.code

```
mov eax,0 ; EAX = 000000000h

mov al,oneByte ; EAX = 00000078h

mov ax,oneWord ; EAX = 00001234h

mov eax,oneDword ; EAX = 12345678h

mov ax,0 ; EAX = 12340000h
```

Copying Smaller Values to Larger Ones

Although MOV cannot directly copy data from a smaller operand to a larger one, programmers can create workarounds. Suppose count (unsigned, 16 bits) must be moved to ECX (32 bits). We can set ECX to zero and move count to CX:

```
.data
count WORD 1
.code
mov ecx,0
mov cx,count
```

What happens if we try the same approach with a signed integer equal to -16?

```
.data
signedVal SWORD -16 ; FFF0h (-16)
.code
mov ecx,0
mov cx,signedVal ; ECX = 0000FFF0h (+65,520)
```

Solution:

```
mov ecx, 0FFFFFFFFh
mov cx, signedVal ; ECX = FFFFFFF0h (-16)
```


MOVZX Instruction

The MOVZX instruction (move with zero-extend) copies the contents of a source operand into a destination operand and zero-extends the value to 16 or 32 bits. This instruction is only used with unsigned integers. There are three variants:

```
MOVZX reg32,reg/mem8
MOVZX reg32,reg/mem16
MOVZX reg16,reg/mem8

.data
byteVal BYTE 10001111b
.code
movzx ax.byteVal ; AX = 0000000010001111b
```

Figure 4–1 Using MOVZX to copy a byte into a 16-bit destination.



The following examples use registers for all operands, showing all the size variations:

```
mov bx,0A69Bh
movzx eax,bx ; EAX = 0000A69Bh
movzx edx,bl ; EDX = 0000009Bh
movzx cx,bl ; CX = 009Bh
```

The following examples use memory operands for the source and produce the same results:

```
.data
byte1 BYTE 9Bh
word1 WORD 0A69Bh
.code
movzx eax,word1 ; EAX = 0000A69Bh
movzx edx,byte1 ; EDX = 0000009Bh
movzx cx,byte1 ; CX = 009Bh
```

```
mov ax,@data
mov ds,ax
```

MOVSX Instruction

The MOVSX instruction (move with sign-extend) copies the contents of a source operand into a destination operand and sign-extends the value to 16 or 32 bits. This instruction is only used with signed integers. There are three variants:

```
MOVSX reg32,reg/mem8
MOVSX reg32,reg/mem16
MOVSX reg16,reg/mem8
```

```
.data
byteVal BYTE 10001111b
.code
```

movsx_ax_byteVal _______, AX = 111111111100011111b


```
mov bx,0A69Bh

movsx eax,bx ; EAX = FFFFA69Bh

movsx edx,bl ; EDX = FFFFFF9Bh

movsx cx,bl ; CX = FF9Bh
```

Figure 4–2 Using MOVSX to copy a byte into a 16-bit destination.



4.1.6 LAHF and SAHF Instructions

The LAHF (load status flags into AH) instruction copies the low byte of the EFLAGS register into AH. The following flags are copied: Sign, Zero, Auxiliary Carry, Parity, and Carry. Using this instruction, you can easily save a copy of the flags in a variable for safekeeping:

```
.data
saveflags BYTE ?
.code
lahf ; load flags into AH
mov saveflags,ah ; save them in a variable
```

The SAHF (store AH into status flags) instruction copies AH into the low byte of the EFLAGS register. For example, you can retrieve the values of flags saved earlier in a variable:

```
mov ah,saveflags ; load saved flags into AH sahf ; copy into Flags register
```

4.1.7 XCHG Instruction

The XCHG (exchange data) instruction exchanges the contents of two operands. There are three variants:

```
XCHG reg,reg
XCHG reg,mem
XCHG mem,reg
```

XCHG provides a simple way to exchange two array elements. Here are a few examples using XCHG:

```
xchgax,bx; exchange 16-bit regsxchgah,al; exchange 8-bit regsxchgvar1,bx; exchange 16-bit mem op with BXxchgeax,ebx; exchange 32-bit regs
```

To exchange two memory operands, use a register as a temporary container and combine MOV with XCHG:

```
mov ax, val1
xchg ax, val2
mov val1, ax
```

4.1.8 Direct-Offset Operands

You can add a displacement to the name of a variable, creating a direct-offset operand. This lets you access memory locations that may not have explicit labels. Let's begin with an array of bytes named arrayB:

```
arrayB BYTE 10h, 20h, 30h, 40h, 50h
```

If we use MOV with arrayB as the source operand, we automatically move the first byte in the array:

```
mov al, arrayB ; AL = 10h
```

We can access the second byte in the array by adding 1 to the offset of arrayB:

```
mov al, [arrayB+1]; AL = 20h
```

The third byte is accessed by adding 2:

```
mov al, [arrayB+2]; AL = 30h
```

Range Checking MASM has no built-in range checking for effective addresses. If we execute the following statement, the assembler just retrieves a byte of memory outside the array. The result is a sneaky logic bug, so be extra careful when checking array references:

```
mov al, [arrayB+20]; AL = ??
```

Word and Doubleword Arrays In an array of 16-bit words, the offset of each array element is 2 bytes beyond the previous one. That is why we add 2 to ArrayW in the next example to reach the second element:

```
.data
arrayW WORD 100h,200h,300h

.code
mov ax,arrayW ; AX = 100h
mov ax,[arrayW+2] ; AX = 200h
```

Similarly, the second element in a doubleword array is 4 bytes beyond the first one:

```
.data
arrayD DWORD 10000h,20000h
.code
mov eax,arrayD ; EAX = 10000h
mov eax,[arrayD+4] ; EAX = 20000h
```

4.2.1 INC and DEC Instructions

The INC (increment) and DEC (decrement) instructions, respectively, add 1 and subtract 1 from a single operand. The syntax is

```
INC reg/mem
DEC reg/mem
```

Following are some examples:

```
.data
myWord WORD 1000h
.code
inc myWord ; myWord = 1001h
mov bx,myWord
dec bx ; BX = 1000h
```


The Overflow, Sign, Zero, Auxiliary Carry, and Parity flags are changed according to the value of the destination operand. The INC and DEC instructions do not affect the Carry flag (which is something of a surprise).

example that subtracts two 32-bit integers:

```
.data
var1 DWORD 30000h
var2 DWORD 10000h
.code
mov eax,var1 ; EAX = 30000h
sub eax,var2 ; EAX = 20000h
```

Internally, the CPU can implement subtraction as a combination of negation and addition. Figure 4–3 shows how the expression 4-1 can be rewritten as 4+(-1). Two's-complement notation is used for negative numbers, so -1 is represented by 11111111.

Figure 4-3 Adding the Value -1 to 4.



4.2.4 NEG Instruction

The NEG (negate) instruction reverses the sign of a number by converting the number to its two's complement. The following operands are permitted:

```
NEG reg
```

4.2.5 Implementing Arithmetic Expressions

```
Rval = -Xval + (Yval - Zval);
```

The following signed 32-bit variables will be used:

```
Rval SDWORD ?
Xval SDWORD 26
Yval SDWORD 30
Zval SDWORD 40
```

When translating an expression, evaluate each term separately and combine the terms at the end.

First, we negate a copy of Xval:

```
; first term: -Xval
mov eax, Xval
neg eax ; EAX = -26
```

Then Yval is copied to a register and Zval is subtracted:

```
; second term: (Yval - Zval)
mov ebx,Yval
sub ebx,Zval ; EBX = -10
```


Finally, the two terms (in EAX and EBX) are added:

```
; add the terms and store:
add eax,ebx
mov Rval,eax ; -36
```

4.3.1 OFFSET Operator

The OFFSET operator returns the offset of a data label. The offset represents the distance, in bytes, of the label from the beginning of the data segment. To illustrate, Figure 4–7 shows a variable named myByte inside the data segment.

Figure 4–7 A Variable Named myByte.



OFFSET Example

In the next example, we declare three different types of variables:

```
.data
bVal BYTE ?
wVal WORD ?
dVal DWORD ?
dVal2 DWORD ?
```

If bVal were located at offset 00404000 (hexadecimal), the OFFSET operator would return the following values:

```
      mov esi,OFFSET bVal
      ; ESI = 00404000

      mov esi,OFFSET wVal
      ; ESI = 00404001

      mov esi,OFFSET dVal
      ; ESI = 00404003

      mov esi,OFFSET dVal2
      ; ESI = 00404007
```

OFFSET can also be applied to a direct-offset operand. Suppose myArray contains five 16-bit words. The following MOV instruction obtains the offset of myArray, adds 4, and moves the resulting address to ESI. We can say that ESI points to the third integer in the array:

```
.data
myArray WORD 1,2,3,4,5
.code
mov esi,OFFSET myArray + 4
```

You can initialize a doubleword variable with the offset of another variable, effectively creating a pointer. In the following example, pArray points to the beginning of bigArray:

```
.data
bigArray DWORD 500 DUP(?)
pArray DWORD bigArray
```

The following statement loads the pointer's value into ESI, so the register can point to the beginning of the array:

```
mov esi,pArray
```

4.3.2 ALIGN Directive

The ALIGN directive aligns a variable on a byte, word, doubleword, or paragraph boundary. The syntax is

ALIGN bound

Bound can be 1, 2, 4, or 16. A value of 1 aligns the next variable on a 1-byte boundary (the default). If bound is 2, the next variable is aligned on an even-numbered address. If bound is 4, the next address is a multiple of 4. If bound is 16, the next address is a multiple of 16, a paragraph boundary. The assembler can insert one or more empty bytes before the variable to fix the alignment. Why bother aligning data? Because the CPU can process data stored at even-numbered addresses more quickly than those at odd-numbered addresses.

bVal	BYTE	?	ï	00404000
ALIGN	2			
wVal	WORD	?	ï	00404002
bVal2	BYTE	?	i	00404004
ALIGN	4			
dVal	DWORD	?	ï	00404008
dVal2	DWORD	?	;	0040400C

Note that dVal would have been at offset 00404005, but the ALIGN 4 directive bumped it up to offset 00404008.

4.3.3 PTR Operator

.data

You can use the PTR operator to override the declared size of an operand. This is only necessary when you're trying to access the variable using a size attribute that's different from the one used to declare the variable.

Suppose, for example, that you would like to move the lower 16 bits of a doubleword variable named myDouble into AX. The assembler will not permit the following move because the operand sizes do not match:

```
myDouble DWORD 12345678h
.code
mov ax,myDouble ; error
```

But the WORD PTR operator makes it possible to move the low-order word (5678h) to AX:

```
mov ax, WORD PTR myDouble
mov ax, WORD PTR [myDouble+2] ; 1234h
```

Moving Smaller Values into Larger Destinations

```
.data
wordList WORD 5678h,1234h
.code
mov eax,DWORD PTR wordList ; EAX = 12345678h
```

4.3.4 TYPE Operator

The TYPE operator returns the size, in bytes, of a single element of a variable. For example, the TYPE of a byte equals 1, the TYPE of a word equals 2, the TYPE of a doubleword is 4, and the TYPE of a quadword is 8. Here are examples of each:

```
.data
var1 BYTE ?
var2 WORD ?
var3 DWORD ?
var4 QWORD ?
```

The following table shows the value of each TYPE expression.

Expression	Value
TYPE var1	1
TYPE var2	2
TYPE var3	4
TYPE var4	8

4.3.5 LENGTHOF Operator

The LENGTHOF operator counts the number of elements in an array, defined by the values appearing on the same line as its label. We will use the following data as an example:

```
.data
byte1 BYTE 10,20,30
array1 WORD 30 DUP(?),0,0
array2 WORD 5 DUP(3 DUP(?))
array3 DWORD 1,2,3,4
digitStr BYTE "12345678",0
```

When nested DUP operators are used in an array definition, LENGTHOF returns the product of the two counters. The following table lists the values returned by each LENGTHOF expression:

Expression	Value
LENGTHOF byte1	3
LENGTHOF array1	30 + 2
LENGTHOF array2	5 * 3
LENGTHOF array3	4
LENGTHOF digitStr	9

4.3.6 SIZEOF Operator

The SIZEOF operator returns a value that is equivalent to multiplying LENGTHOF by TYPE. In the following example, intArray has TYPE = 2 and LENGTHOF = 32. Therefore, SIZEOF intArray equals 64:

```
.data
intArray WORD 32 DUP(0)
.code
mov eax, SIZEOF intArray ; EAX = 64
```

4.4.2 Arrays

Indirect operands are ideal tools for stepping through arrays. In the next example, arrayB contains 3 bytes. As ESI is incremented, it points to each byte, in order:

```
.data
arrayB BYTE 10h,20h,30h
.code
mov esi,OFFSET arrayB
mov al,[esi] ; AL = 10h
inc esi
mov al,[esi] ; AL = 20h
inc esi
mov al,[esi] ; AL = 30h
```

If we use an array of 16-bit integers, we add 2 to ESI to address each subsequent array element:

```
.data
arrayW WORD 1000h,2000h,3000h
.code
mov esi,OFFSET arrayW
mov ax,[esi] ; AX = 1000h
add esi,2
mov ax,[esi] ; AX = 2000h
add esi,2
mov ax,[esi] ; AX = 3000h
```

Suppose arrayW is located at offset 10200h. The following illustration shows the initial value of ESI in relation to the array data:

Offset	Value	
10200	1000h	≺ [esi]
10202	2000h	
10204	3000h	

4.4.3 Indexed Operands

An *indexed operand* adds a constant to a register to generate an effective address. Any of the 32bit general-purpose registers may be used as index registers. There are different notational forms permitted by MASM (the brackets are part of the notation):

```
constant[reg]
[constant + reg]
```

The first notational form combines the name of a variable with a register. The variable name is translated by the assembler into a constant that represents the variable's offset. Here are examples that show both notational forms:

arrayB[esi]	[arrayB + esi]
arrayD[ebx]	[arrayD + ebx]

Indexed operands are ideally suited to array processing. The index register should be initialized to zero before accessing the first array element:

```
.data
arrayB BYTE 10h,20h,30h
.code
mov esi,0
mov al,[arrayB + esi] ; AL = 10h
```

The last statement adds ESI to the offset of arrayB. The address generated by the expression [arrayB + ESI] is dereferenced and the byte in memory is copied to AL.

Adding Displacements The second type of indexed addressing combines a register with a constant offset. The index register holds the base address of an array or structure, and the constant identifies offsets of various array elements. The following example shows how to do this with an array of 16-bit words:

```
.data
arrayW WORD 1000h,2000h,3000h
.code
mov esi,OFFSET arrayW
mov ax,[esi] ; AX = 1000h
mov ax,[esi+2] ; AX = 2000h
mov ax,[esi+4] ; AX = 3000h
```

Scale Factors in Indexed Operands

Indexed operands must take into account the size of each array element when calculating offsets. Using an array of doublewords, as in the following example, we multiply the subscript (3) by 4 (the size of a doubleword) to generate the offset of the array element containing 400h:

```
.data
arrayD DWORD 100h, 200h, 300h, 400h
.code
mov esi,3 * TYPE arrayD ; offset of arrayD[3]
mov eax,arrayD[esi] ; EAX = 400h
```

```
.data
arrayD DWORD 1,2,3,4
.code
mov esi,3 ; subscript
mov eax,arrayD[esi*4] ; EAX = 4
```

The TYPE operator can make the indexing more flexible should arrayD be redefined as another type in the future:

```
mov esi,3 ; subscript
mov eax,arrayD[esi*TYPE arrayD] ; EAX = 4
```

Array Parallel Addition

A1 word 25h, 30h, 70h
Arrayw word 1000h, 2000h, 3000h
A2 word lengthof A1 Dup(?)
.code
Mov ecx, lengthof A1
Mov ebx, offset A1
Mov ESI, offset Arrayw
MOV EDI, offset A2
MOV EDX, 0

L1: Mov AX, 0h Add ax, [ebx+EDX] Add ax, [esi+EDX] MOV [EDI+EDX], ax Add EDX, type A1 Loop L1

: Alternate code L1: Mov AX, 0h Add ax, [ebx] Add ebx, type A1 Add ax, [esi] Add ESI, type A1 MOV [EDI], ax Add EDI, type A1 Loop L1