МИНОБРНАУКИ РОССИИ САНКТ-ПЕТЕРБУРГСКИЙ ГОСУДАРСТВЕННЫЙ ЭЛЕКТРОТЕХНИЧЕСКИЙ УНИВЕРСИТЕТ «ЛЭТИ» ИМ. В.И. УЛЬЯНОВА (ЛЕНИНА) Кафедра МО ЭВМ

ОТЧЕТ

по лабораторной работе №5

по дисциплине «Операционные системы»

Тема: Сопряжение стандартного и пользовательского обработчиков прерываний.

| Студент гр. 9383 | Рыбников Р.А. |
|------------------|-------------------|
| Преподаватель | Ефремов М.А. |

Санкт-Петербург

2021

Цель работы.

Исследование возможности встраивания пользовательского обработчика прерываний в стандартный обработчик от клавиатуры. Пользовательский обработчик прерывания получает управление по прерыванию (int 09h) при нажатии клавиши на клавиатуре. Он обрабатывает скан-код и осуществляет определенные действия, если скан-код совпадает с определенными кодами, которые он должен обрабатывать. Если скан-код не совпадает с этими кодами, то управление передается стандартному прерыванию.

Постановка задачи.

Требуется написать и отладить .EXE модуль, который выполняет следующие функции:

- 1) Проверяет, установлено ли пользовательское прерывание с вектором 09h.
- 2) Если прерывание не установлено то, устанавливает резидентную функцию для обработки прерывания и настраивает вектор прерываний. Адрес точки входа в стандартный обработчик прерывания находится в теле пользовательского обработчика. Осуществляется выход по функции 4Ch прерывания int 21h..
- 3) Если прерывание установлено, то выводится соответствующее сообщение и осуществляется выход по функции 4Ch прерывания int 21h.

Программа должна содержать код устанавливаемого прерывания в виде удаленной процедуры. Код должен:

- 1) Сохранить значения регистров в стеке при входе и восстановить их при выходе.
- 2) При выполнении тела процедуры анализируется скан-код.
- 3) Если этот код совпадает с одним из заданных, то требуемый код записывается в буфер клавиатуры.

4) Если этот код не совпадает ни с одним из заданных, то осуществляется передача управления стандартному обработчику прерывания.

Выполнение работы.

Сначала был написан код для .EXE модуля. Модуль работает следующим образом: если он запущен без ключа /un, то он установит прерывание в память. Далее, при попытках снова установить это прерывание будет выводиться соответствующая строка. Это можно видеть на рисунке 1.

Рисунок 1 – Установка прерывания.

Также, прерывание можно выгрузить, запустив программу с ключом /un. Если запустить программу так же еще раз, после выгрузки, то выведется соответствующее сообщение. Это представлено на рисунке 2.

Рисунок 2 – Выгрузка прерывания.

Далее на рисунках 3-6 представлены соответственно: работа прерывания, расположение в памяти после загрузки прерывания, расположение в памяти после повторной загрузки, расположение в памяти после выгрузки.

Чтобы увидеть работу прерывания, необходимо зажать сочетание клавиш ctrl+a.

```
DOSBox 0.74-3-2, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX
F:\>
F:\>
F:\>
F:\>lb5_main.exe
Interruption is changed to custom.
F:N>lb5_main.exe
Custom interruption is already loaded.
F: \>
F : \>/un
F:\>1b5_main.exe /un
Custom interruption was unloaded.
F:\>
F:\>
F:\>lb5_main.exe
Interruption is changed to custom.
F:\>lb5_main.exe
Custom interruption is already loaded.
888888</i>
```

Рисунок 3 — Работа прерывания (нажатие ctrl+a).

```
DOSBox 0.74-3-2, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX
F:N>1b5_main.exe /un
Custom interruption was unloaded.
F:\>
F:\>
F: \> 1b5_main.exe
Interruption is changed to custom.
F:\>lb5_main.exe
Custom interruption is already loaded.
F: \>
F:\>lab3_1.com
Size of accessed memory: 644304 byte
Size of extended memory: 245760 byte
1CB:01 Adress: 016F PSP adress: 0008
                                          Size: 16
                                                        SD/SC:
1CB:02 Adress:
                 0171 PSP adress: 0000
                                          Size: 64
                                                        SD/SC:
1CB:03
                 0176
                       PSP adress: 0040
                                          Size: 256
                                                        SD/SC:
       Adress:
1CB:04
        Adress:
                 0187
                       PSP adress: 0192
                                          Size: 144
                                                        SD/SC:
1CB:05
        Adress:
                 0191
                       PSP adress: 0192
                                          Size: 4432
                                                        SD/SC: LB5 MAIN
                           adress: 02B2
                                          Size: 1442
1CB:06
                 02A7
                       PSP
        Adress:
                                                        SD/SC:
1CB:07
                       PSP adress: 02B2
                                          Size: 644304
       Adress:
                 02B1
                                                        SD/SC: LAB3 1
F:\>
```

Рисунок 4 — Расположение в памяти после загрузки прерывания.

```
DOSBox 0.74-3-2, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX
Size of accessed memory: 648912 byte
Size of extended memory: 245760 byte
MCB:01 Adress: 016F PSP adress: 0008 Size: 16
                                                       SD/SC:
       Adress:
                0171 PSP adress: 0000 Size: 64
                                                       SD/SC:
1CB:02
       Adress: 0176 PSP adress: 0040 Size: 256
                                                       SD/SC:
1CB:03
       Adress: 0187 PSP adress: 0192 Size: 144
1CB:04
                                                       SD/SC:
       Adress: 0191 PSP adress: 0192 Size: 648912 SD/SC: LAB3_1
1CB:05
:1>
':\>lb5_main.exe
Interruption is changed to custom.
':\>lb5_main.exe
Custom interruption is already loaded.
F:\>lab3_1.com
Size of accessed memory: 644304 byte
Size of extended memory: 245760 byte
MCB:01 Adress: 016F PSP adress: 0008 Size: 16
                                                       SD/SC:
       Adress: 0171 PSP adress: 0000 Size: 64
1CB:02
                                                       SD/SC:
       Adress: 0176 PSP adress: 0040 Size: 256
                                                       SD/SC:
MCB:03
                0187 PSP adress: 0192
0191 PSP adress: 0192
                                         Size: 144
ICB:04
       Adress:
                                                       SD/SC:
                                         Size: 4432
                                                       SD/SC: LB5_MAIN
CB:05
       Adress:
                02A7 PSP adress: 02B2
                                         Size: 1442
ICB:06
       Adress:
                                                       SD/SC:
                02B1 PSP adress: 02B2
                                         Size: 644304 SD/SC: LAB3 1
CB:07
       Adress:
':\>_
```

Рисунок 5 – Расположение прерывания в памяти после повторной загрузки.

```
DOSBox 0.74-3-2, Cpu speed: 3000 cycles, Frameskip 0, Program: DOSBOX
 :\>lab3 1.com
Size of accessed memory: 644304 byte
Size of extended memory: 245760 byte
MCB:01 Adress: 016F PSP adress: 0008 Size: 16
MCB:02 Adress: 0171 PSP adress: 0000 Size: 64
                                                        SD/SC:
                                                        SD/SC:
1CB:03 Adress: 0176 PSP adress: 0040 Size: 256
                                                        SD/SC:
1CB:04 Adress: 0187 PSP adress: 0192 Size: 144
                                                        SD/SC:
1CB:05 Adress: 0191 PSP adress: 0192
                                         Size: 4432
                                                        SD/SC: LB5_MAIN
ICB:06
       Adress: OZA7 PSP adress: OZBZ
                                         Size: 1442
                                                        SD/SC:
1CB:07 Adress: 02B1 PSP adress: 02B2 Size: 644304 SD/SC: LAB3_1
 :>>
':\>lb5_main.exe /un
Custom interruption was unloaded.
:\>lab3_1.com
Size of accessed memory: 648912 byte
Size of extended memory: 245760 byte
MCB:01 Adress: 016F PSP adress: 0008
                                         Size: 16
                                                        SD/SC:
MCB:02 Adress: 0171 PSP adress: 0000 Size: 64
                                                        SD/SC:
MCB:03 Adress: 0176 PSP adress: 0040 Size: 256
                                                        SD/SC:
1CB:04 Adress: 0187 PSP adress: 0192 Size: 144
                                                        SD/SC:
1CB:05 Adress: 0191 PSP adress: 0192 Size: 648912 SD/SC: LAB3_1
```

Рисунок 6 - Расположение в памяти после выгрузки прерывания.

Ответы на вопросы.

- 1. Какого типа прерывания использовались в работе? Программные прерывания int 21h и int 21h, а так же аппаратные прерывания 09h и 16h.
- 2. Чем отличается скан код от кода ASCII?

Скан-код — уникальный числовой код, присвоенный клавише клавиатуры, который определяет нажатую клавишу. Код ASCII — уникальный код каждого символа таблицы ASCII.

Выводы.

Был реализован пользовательский обработчик прерываний, который был встроен в стандартный обработчик клавиатуры.

ПРИЛОЖЕНИЕ А ИСХОДНЫЙ КОД ПРОГРАММЫ

lb5_main.asm: AStack SEGME

AStack SEGMENT STACK
DW 64 DUP(?)

AStack ENDS

DATA SEGMENT

SECOND_INFO db "Custom interruption is already loaded.\$" THIRD_INFO db "Interruption is changed to custom.\$"

FIRST_INFO db "Default interruption is set and can't be unloaded.\$"

FOURTH_INFO db "Custom interruption was unloaded.\$"

DATA ENDS

CODE SEGMENT

ASSUME CS:CODE, DS:DATA, SS:AStack

PRINT_BUFFER proc near

push ax

mov ah, 9h

int 21h

pop ax

ret

PRINT_BUFFER endp

START:

ROUT proc far

jmp start1

key_value db 0

KEEP_PSP dw 0

KEEP IP dw 0

KEEP_CS dw 0

KEEP_SS DW 0

KEEP SP DW 0

KEEP_AX DW 0

ROUT_INDEX dw 6666h

TIMER_COUNTER db 'Timer: 0000\$'

BStack DW 64 DUP(?)

start1:

mov KEEP_SP, sp

mov KEEP_AX, ax

mov KEEP_SS, ss

mov ax, seg BStack

mov ss, ax

mov ax, offset start1

mov sp, ax

```
mov ax, KEEP_AX
   push ax
   push bx
   push cx
   push dx
   push si
   push es
   push ds
         mov cx, 040h
         mov es, cx
         mov cx, es:[0017h]
   mov ax, SEG key_value
   mov ds, ax
   and cx, 0100b
   jz defolt_int
   in al, 60h
   cmp al, 1Eh
   je key
defolt_int:
   call dword ptr cs:[KEEP_IP]
   jmp re_reg
key:
   mov key_value, '&'
   jmp next
next:
   in al, 61h
   mov ah, al
   or al, 80h
   out 61h, al
   xchg ah, al
   out 61h, al
   mov al, 20H
   out 20h, al
```

print_key:

mov ah, 05h

mov cl, key_value

9

```
mov ch, 00h
 int 16h
 or al, al
 jz re_reg
 mov ax, 040h
 mov es, ax
 mov ax, es:[1Ah]
 mov es:[1Ch], ax
 jmp print_key
skip:
  mov al, es:[1Ah]
  mov es:[1Ch], al
  jmp print_key
re_reg:
  pop ds
  pop es
  pop si
  pop dx
  pop cx
  pop bx
  pop ax
  mov sp, KEEP_SP
  mov ax, KEEP_SS
  mov ss, ax
  mov ax, KEEP_AX
  mov al, 20H
  out 20H, al
  iret
end_rout:
ROUT endp
UNLOAD proc near
      push ax
  push es
      mov al,es:[81h+1]
      cmp al,'/'
      jne need_unload
      mov al,es:[81h+2]
      cmp al, 'u'
      jne need_unload
      mov al,es:[81h+3]
```

```
cmp al, 'n'
     jne need_unload
  mov cl,1h
need_unload:
  pop es
      pop ax
      ret
UNLOAD endp
LOAD PROC near
      push ax
      push dx
  mov KEEP_PSP, es
     mov ah,35h
     mov al,09h
     int 21h
  mov KEEP_IP, bx
  mov KEEP_CS, es
     push ds
     lea dx, ROUT
     mov ax, SEG ROUT
     mov ds,ax
     mov ah,25h
     mov al,09h
     int 21h
     pop ds
     lea dx, end_rout
     mov cl,4h
     shr dx,cl
     inc dx
     add dx,100h
  xor ax, ax
     mov ah,31h
     int 21h
     pop dx
     pop ax
     ret
LOAD ENDP
UNLOAD_ROUT PROC near
     push ax
     push si
```

```
push ds
      mov ah,35h
      mov al,09h
  int 21h
  mov si,offset KEEP_IP
  sub si,offset ROUT
  mov dx,es:[bx+si]
      mov ax,es:[bx+si+2]
  mov ds,ax
  mov ah,25h
  mov al,09h
  int 21h
  pop ds
  mov ax,es:[bx+si-2]
  mov es,ax
  push es
  mov ax,es:[2ch]
  mov es,ax
  mov ah,49h
  int 21h
  pop es
  mov ah,49h
  int 21h
  sti
  pop si
  pop ax
  ret
UNLOAD_ROUT endp
CHECK_LOAD proc near
      push ax
      push si
  push es
  push dx
      mov ah,35h
      mov al,09h
      int 21h
      mov si, offset ROUT_INDEX
      sub si, offset ROUT
      mov dx,es:[bx+si]
      cmp dx, ROUT_INDEX
      jne end_check
      mov ch,1h
```

```
end_check:
  pop dx
  pop es
     pop si
     pop ax
     ret
CHECK_LOAD ENDP
MAIN proc far
  push DS
  push AX
  mov AX,DATA
  mov DS,AX
  call UNLOAD
  cmp cl, 1h
  je start_unload
  call CHECK_LOAD
  cmp ch, 1h
  je marker_1
  mov dx, offset THIRD_INFO
  call PRINT_BUFFER
  call LOAD
  jmp exit
start unload:
  call CHECK_LOAD
  cmp ch, 1h
  jne marker_2
  call UNLOAD_ROUT
  mov dx, offset FOURTH_INFO
  call PRINT_BUFFER
  jmp exit
marker_2:
  mov dx, offset FIRST_INFO
  call PRINT_BUFFER
  jmp exit
marker_1:
  mov dx, offset SECOND_INFO
  call PRINT_BUFFER
  jmp exit
exit:
  mov ah, 4ch
  int 21h
MAIN endp
CODE ends
END Main
```

lab3_1.asm:

```
TESTPC SEGMENT
 ASSUME CS:TESTPC, DS:TESTPC, ES:NOTHING, SS:NOTHING
 ORG 100H
START: JMP BEGIN
ACCESSED_MEMORY db 13,10,'Size of accessed memory:
                                                      $'
EXTENDED_MEMORY db 13,10,'Size of extended memory:
                                                      $'
STR_BYTE db 'byte $'
STR MCB db 13,10,'MCB:0 $'
ADRESS db 'Adress:
                             $'
ADRESS PSP db 'PSP adress:
STR SIZE db 'Size:
MCB_SD_SC db 'SD/SC: $'
STR_ERROR db 13,10,'Memory Error!$'
STR_SUCCECC db 13,10,'Success!$'
TETR_TO_HEX PROC near
 and AL,0Fh
 cmp AL,09
 jbe next
 add AL,07
next:
 add AL,30h
TETR_TO_HEX ENDP
BYTE_TO_HEX PROC near
 push CX
 mov AH,AL
 call TETR_TO_HEX
 xchg AL,AH
 mov CL,4
 shr AL,CL
 call TETR_TO_HEX
 рор СХ ;в АН младшая
 ret
BYTE TO HEX ENDP
WRD_TO_HEX PROC near
;перевод в 16 с/с 16-ти разрядного числа
; в АХ - число, DI - адрес последнего символа
 push BX
 mov BH,AH
 call BYTE_TO_HEX
 mov [DI],AH
 dec DI
 mov [DI],AL
 dec DI
 mov AL,BH
 call BYTE TO HEX
 mov [DI],AH
```

```
dec DI
 mov [DI],AL
 pop BX
 ret
WRD_TO_HEX ENDP
•
BYTE_TO_DEC PROC near
; перевод в 10c/c, SI - адрес поля младшей цифры
 push CX
 push DX
 xor AH,AH
 xor DX,DX
 mov CX,10
loop_bd:
 div CX
 or DL,30h
 mov [SI],DL
 dec SI
 xor DX,DX
 cmp AX,10
 jae loop_bd
 cmp AL,00h
 je end_1
 or AL,30h
 mov [SI],AL
end_l:
 pop DX
 pop CX
 ret
BYTE_TO_DEC ENDP
WRITE_STRING PROC near
 push AX
 mov AH,09h
 int 21h
 pop AX
 ret
WRITE_STRING ENDP
·
?-----
WRITE_SIZE PROC
 push ax
 push bx
 push cx
 push dx
 push si
     mov bx,10h
     mul bx
     mov bx,0ah
     xor cx,cx
delenie:
```

```
div bx
      push dx
      inc cx
      xor dx,dx
      cmp ax,0h
      jnz delenie
write_symbol:
      pop dx
      or dl,30h
      mov [si], dl
      inc si
      loop write_symbol
 pop si
 pop dx
 pop cx
 pop bx
 pop ax
      ret
WRITE_SIZE ENDP
PRINT_MCB PROC
 push ax
 push bx
 push cx
 push dx
 push si
 mov ah,52h
 int 21h
 mov ax,es:[bx-2]
 mov es,ax
 xor cx,cx
      inc cx
pargraph_MCB:
      lea si, STR_MCB
      add si, 7
      mov al,cl
      push cx
      call BYTE_TO_DEC
      lea dx, STR_MCB
      call WRITE_STRING
      mov ax,es
      lea di, ADRESS
      add di,12
      call WRD_TO_HEX
      lea dx, ADRESS
      call WRITE_STRING
```

```
xor ah,ah
      mov al,es:[0]
      push ax
      mov ax,es:[1]
      lea di, ADRESS_PSP
      add di, 15
      call WRD_TO_HEX
      lea dx, ADRESS_PSP
      call WRITE_STRING
      mov ax,es:[3]
      lea si,STR_SIZE
      add si, 6
      call WRITE_SIZE
      lea dx,STR_SIZE
      call WRITE_STRING
      xor dx, dx
      lea dx, MCB_SD_SC
      call WRITE_STRING
      mov cx,8
      xor di,di
write_char:
      mov dl,es:[di+8]
      mov ah,02h
      int 21h
      inc di
      loop write_char
      mov ax,es:[3]
      mov bx,es
      add bx,ax
      inc bx
      mov es,bx
      pop ax
      pop cx
      inc cx
      cmp al,5Ah
      je exit
      cmp al,4Dh
      jne exit
      jmp pargraph_MCB
      exit:
 pop si
 pop dx
 pop cx
 pop bx
 pop ax
      ret
PRINT_MCB ENDP
```

```
BEGIN:
 mov ah,4ah
      mov bx,0ffffh
      int 21h
 mov ax,bx
 lea si, ACCESSED_MEMORY
 add si, 27
 call WRITE_SIZE
 lea dx, ACCESSED_MEMORY
 call WRITE_STRING
 lea dx,STR_BYTE
 call WRITE_STRING
 ; расширенная память
 mov AL,30h
 out 70h,AL
 in AL,71h
 mov BL,AL
 mov AL,31h
 out 70h,AL
 in AL,71h
      mov bh,al
      mov ax,bx
      lea si, EXTENDED_MEMORY
      add si, 27
      call WRITE_SIZE
      lea dx,EXTENDED_MEMORY
      call WRITE_STRING
      lea dx,STR_BYTE
 call WRITE_STRING
 ;MCB
 call PRINT_MCB
 xor AL,AL
 mov AH,4Ch
 int 21H
TESTPC ENDS
END START
```