Malloc Recitation

Ben Spinelli

Recitation 11: November 9, 2015

Agenda

- Macros / Inline functions
- Quick pointer review
- Malloc

Macros / Inline Functions

Macros

- Pre-compile time
- Define constants:
 - #define NUM_ENTRIES 100
 - OK
- Define simple operations:
 - # define twice(x) 2*x
 - Not OK
 - twice(x+1) becomes 2*x+1
 - # define twice(x) (2*(x))
 - OK
 - Always wrap in parentheses; it's a naive search-and-replace!

Macros

Why macros?

- "Faster" than function calls
 - Why?
- For malloc
 - Quick access to header information (payload size, valid)

Drawbacks

- Less expressive than functions
- Arguments are not typechecked, local variables
 - This can easily lead to errors that are more difficult to find

Inline Functions

- What's the keyword inline do?
 - At compile-time replaces "function calls" with code
- More efficient than a normal function call
 - Less overhead no need to set up stack/function call
 - Useful for functions that are
 - Called frequently
 - Small, e.g., int add(int x, int y);

Differences

- Macros done at pre-compile time
- Inline functions done at compile time
 - Stronger type checking / Argument consistency
- Macros cannot return anything (why not?)
- Macros can have unintended side effects
 - #define xsquared(x) (x*x)
 - What happens when xsquared(x++) is called?
- Hard to debug macros errors generated on expanded code, not code that you typed

Macros / Inline Functions

- You will likely use both in malloc lab
- Macros are good for small tasks
 - Saves work in retyping tedious calculations
 - Can make code easier to understand
 - HEADER(ptr) versus doing the pointer arithmetic
- Some things are hard to code in macros, so this is where inline functions come into play
 - More efficient than normal function call
 - More expressive than macros

Pointers: casting, arithmetic, and dereferencing

Pointer casting

Cast from

- <type_a>* to <type_b>*
 - Gives back the same value
 - Changes the behavior that will happen when dereferenced
- <type_a>* to integer/ unsigned int
 - Pointers are really just 8-byte numbers
 - Taking advantage of this is an important part of malloc lab
 - Be careful, though, as this can easily lead to errors
- integer/ unsigned int to <type_a>*

Pointer arithmetic

- The expression ptr + a doesn't mean the same thing as it would if ptr were an integer.
- Example:

```
type_a* pointer = ...;
(void *) pointer2 = (void *) (pointer + a);
```

- This is really computing:
 - pointer2 = pointer + (a * sizeof(type_a))
 - lea (pointer, a, sizeof(type a)), pointer2;
- Pointer arithmetic on void* is undefined

Pointer arithmetic

```
\blacksquare int * ptr = (int *)0x12341230;
  int * ptr2 = ptr + 1;
\blacksquare char * ptr = (char *)0x12341230;
  char * ptr2 = ptr + 1;
\blacksquare int * ptr = (int *)0x12341230;
  int * ptr2 = ((int *) (((char *) ptr) + 1));
\blacksquare char * ptr = (char *)0x12341230;
  void * ptr2 = ptr + 1;
■ char * ptr = (int *)0x12341230;
  void * ptr2 = ptr + 1;
```

Pointer arithmetic

```
int * ptr = (int *)0x12341230;
  int * ptr2 = ptr + 1; //ptr2 is 0x12341234
\blacksquare char * ptr = (char *)0x12341230;
  char * ptr2 = ptr + 1; //ptr2 is 0x12341231
\blacksquare int * ptr = (int *)0x12341230;
  int * ptr2 = ((int *) (((char *) ptr) + 1));
  //ptr2 is 0x12341231
\blacksquare char * ptr = (char *)0x12341230;
  void * ptr2 = ptr + 1; //ptr2 is 0x12341231
\blacksquare char * ptr = (int *)0x12341230;
  void * ptr2 = ptr + 1; //ptr2 is still 0x12341231
```

More pointer arithmetic

```
int ** ptr = (int **)0x12341230;
  int * ptr2 = (int *) (ptr + 1);
\blacksquare char ** ptr = (char **)0x12341230;
  short * ptr2 = (short *) (ptr + 1);
\blacksquare int * ptr = (int *)0x12341230;
  void * ptr2 = &ptr + 1;
\blacksquare int * ptr = (int *)0x12341230;
  void * ptr2 = ((void *) (*ptr + 1));
```

This is on a 64-bit machine!

More pointer arithmetic

```
\blacksquare int ** ptr = (int **)0x12341230;
  int * ptr2 = (int *) (ptr + 1); //ptr2 = 0x12341238
\blacksquare char ** ptr = (char **)0x12341230;
  short * ptr2 = (short *) (ptr + 1);
  //ptr2 = 0x12341238
\blacksquare int * ptr = (int *)0x12341230;
  void * ptr2 = ptr + 1; //ptr2 = ??
  //ptr2 is actually 8 bytes higher than the address of
  the variable ptr, which is somewhere on the stack
\blacksquare int * ptr = (int *)0x12341230;
  void * ptr2 = ((void *) (*ptr + 1)); //ptr2 = ??
  //ptr2 is one plus the value at 0x12341230
   (so undefined, but it probably segfaults)
```

Pointer dereferencing

Basics

- It must be a POINTER type (or cast to one) at the time of dereference
- Cannot dereference expressions with type void*
- Dereferencing a t* evaluates to a value with type t

Pointer dereferencing

What gets "returned?"

```
int * ptr1 = malloc(sizeof(int));
*ptr1 = 0xdeadbeef;

int val1 = *ptr1;
int val2 = (int) *((char *) ptr1);
```

What are val1 and val2?

Pointer dereferencing

What happened??

What gets "returned?" int * ptr1 = malloc(sizeof(int)); *ptr1 = 0xdeadbeef; int val1 = *ptr1; int val2 = (int) *((char *) ptr1); val1 = 0xdeadbeef; Little endian, and sign extension. // val2 = 0xffffffef;


Malloc

Malloc basics

What is dynamic memory allocation?


- Terms you will need to know
 - malloc/ calloc / realloc
 - free
 - sbrk
 - payload
 - fragmentation (internal vs. external)
 - coalescing
 - Bi-directional
 - Immediate vs. Deferred

Allocation Example






$$p2 = malloc(5)$$




$$p3 = malloc(6)$$



free(p2)



$$p4 = malloc(2)$$




Fragmentation

- Internal fragmentation
 - Result of <u>payload</u> being smaller than block size.
 - void * m1 = malloc(3); void * m1 = malloc(3);
 - m1, m2 both have to be aligned to 8 bytes...

External fragmentation

External Fragmentation

Occurs when there is enough aggregate heap memory,
 but no single free block is large enough



- Depends on the pattern of future requests
 - Thus, difficult to measure

Implementation Hurdles

- How do we know where the blocks are?
- How do we know how big the blocks are?
- How do we know which blocks are free?
- Remember: can't buffer calls to malloc and free... must deal with them real-time.
- Remember: calls to free only takes a pointer, not a pointer and a size.
- Solution: <u>Need a data structure to store information on</u> the "blocks"
 - Where do I keep this data structure?
 - We can't allocate a space for it, that's what we are writing!

Requirements:

- The data structure needs to tell us where the blocks are, how big they are, and whether they're free
- We need to be able to CHANGE the data structure during calls to malloc and free
- We need to be able to find the next free block that is "a good fit for" a given payload
- We need to be able to quickly mark a block as free/allocated
- We need to be able to detect when we're out of blocks.
 - What do we do when we're out of blocks?

It would be convenient if it worked like:

```
malloc_struct malloc_data_structure;
...
ptr = malloc(100, &malloc_data_structure);
...
free(ptr, &malloc_data_structure);
...
```

- Instead all we have is the memory we're giving out.
 - All of it doesn't have to be payload! We can use some of that for our data structure.

- The data structure IS your memory!
- A start:
 - <h1> <pl1> <h2> <pl2> <h3> <pl3>
 - What goes in the header?
 - That's your job!
 - Lets say somebody calls free(p2), how can I coalesce?
 - Maybe you need a footer? Maybe not?

Common types

- Implicit List
 - Root -> block1 -> block2 -> block3 -> ...
- Explicit List
 - Root -> free block 1 -> free block 2 -> free block 3 -> ...
- Segregated List
 - Small-malloc root -> free small block 1 -> free small block 2 -> ...
 - Medium-malloc root -> free medium block 1 -> ...
 - Large-malloc root -> free block chunk1 -> ...

Implicit List

- From the root, can traverse across blocks using headers
- Can find a free block this way
- Can take a while to find a free block
 - How would you know when you have to call sbrk?

Explicit List

- Improvement over implicit list
- From a root, keep track of all free blocks in a (doubly) linked list
 - Remember a doubly linked list has pointers to next and previous
- When malloc is called, can now find a free block quickly
 - What happens if the list is a bunch of small free blocks but we want a really big one?
 - How can we speed this up?

Segregated List

- An optimization for explicit lists
- Can be thought of as multiple explicit lists
 - What should we group by?
- Grouped by size let's us quickly find a block of the size we want
- What size/number of buckets should we use?
 - This is up to you to decide

Design Considerations

- I found a chunk that fits the necessary payload... should I look for a better fit or not? (First fit vs. Best fit)
- Splitting a free block:

Design Considerations

- Free blocks: address-ordered or LIFO
 - What's the difference?
 - Pros and cons?
- Coalescing
 - When do you coalesce?
- You will need to be using an explicit list at minimum score points
 - But don't try to go straight to your final design, build it up iteratively.

Heap Checker

Part of the assignment is writing a heap checker

- This is here to help you.
- Write the heap checker as you go, don't think of it as something to do at the end
- A good heap checker will make debugging much, much easier

Heap checker tips

- Heap checker should run silently until it finds an error
 - Otherwise you will get more output than is useful
 - You might find it useful to add a "verbose" flag, however
- Consider using a macro to turn the heap checker on and off
 - This way you don't have to edit all of the places you call it
- There is a built-in macro called ___LINE___ that gets replaced with the line number it's on
 - You can use this to make the heap checker tell you where it failed

Demo

- Running Traces
- Heap checker
- Using gprof to profile