VPC Networking

1 hour 30 minutes

Free

Rate Lab

Overview

Google Cloud Virtual Private Cloud (VPC) provides networking functionality to Compute Engine virtual machine (VM) instances, Kubernetes Engine containers, and the App Engine flexible environment. In other words, without a VPC network, you cannot create VM instances, containers, or App Engine applications.

Therefore, each Google Cloud project has a **default** network to get you started.

You can think of a VPC network as similar to a physical network, except that it is virtualized within Google Cloud. A VPC network is a global resource that consists of a list of regional virtual subnetworks (subnets) in data centers, all connected by a global wide area network (WAN). VPC networks are logically isolated from each other in Google Cloud.

In this lab, you create an auto mode VPC network with firewall rules and two VM instances. Then, you convert the auto mode network to a custom mode network and create other custom mode networks as shown in the network diagram below. You also test connectivity across networks.

Objectives

In this lab, you learn how to perform the following tasks:
Explore the default VPC network
Create an auto mode network with firewall rules
Convert an auto mode network to a custom mode network
Create custom mode VPC networks with firewall rules
Create VM instances using Compute Engine
Explore the connectivity for VM instances across VPC networks
For each lab, you get a new GCP project and set of resources for a fixed time at no cost.
1. Make sure you signed into Qwiklabs using an incognito window .
2. Note the lab's access time (for example, and make sure you can finish in that time block.
There is no pause feature. You can restart if needed, but you have to start at the beginning.
3. When ready, click [SEE]
4. Note your lab credentials. You will use them to sign in to Cloud Platform Console. [5]
5. Click Open Google Console.
6. Click Use another account and copy/paste credentials for this lab into the prompts.
Mark and the second a
If you use other credentials, you'll get errors or incur charges .

7. Accept the terms and skip the recovery resource page.

Do not click **End Lab** unless you are finished with the lab or want to restart it. This clears your work and removes the project.

Task 1. Explore the default network

Each Google Cloud project has a **default** network with subnets, routes, and firewall rules.

View the subnets

The **default** network has a subnet in each Google Cloud region.

In the Cloud Console, on the Navigation menu (), click VPC network > VPC networks. Notice
the default network with its subnets. Each subnet is associated with a Google Cloud region and a
private RFC 1918 CIDR block for its internal IP addresses range and a gateway.

View the routes

Routes tell VM instances and the VPC network how to send traffic from an instance to a destination, either inside the network or outside Google Cloud. Each VPC network comes with some default routes to route traffic among its subnets and send traffic from eligible instances to the internet.

• In the left pane, click **Routes**. Notice that there is a route for each subnet and one for the **Default**internet gateway (0.0.0.0/0). These routes are managed for you, but you can create custom static routes to direct some packets to specific destinations. For example, you can create a route that sends all outbound traffic to an instance configured as a NAT gateway.

View the firewall rules

Each VPC network implements a distributed virtual firewall that you can configure. Firewall rules allow you to control which packets are allowed to travel to which destinations. Every VPC network has two implied firewall rules that block all incoming connections and allow all outgoing connections.

- In the left pane, click Firewall rules. Notice that there are 4 Ingress firewall rules for the default network:
- default-allow-icmp
- default-allow-rdp
- default-allow-ssh
- default-allow-internal
- These firewall rules allow ICMP, RDP, and SSH ingress traffic from anywhere (0.0.0.0/0) and all TCP, UDP, and ICMP traffic within the network (10.128.0.0/9).

The Targets, Filters, Protocols/ports, and Action columns explain these rules.

Delete the Firewall rules

- 1. In the left pane, click Firewall rules.
- 2. Select all default network firewall rules.[5]
- 3. Click **Delete**.
- 4. Click **Delete** to confirm the deletion of the firewall rules.

Delete the default network

1. In the left pane, click VPC networks .
2. Select the default network.
3. Click Delete VPC network .
4. Click Delete to confirm the deletion of the default network. Wait for the network to be deleted before continuing.
5. In the left pane, click Routes . Notice that there are no routes.
6. In the left pane, click Firewall rules . Notice that there are no firewall rules.
Without a VPC network, there are no routes!
Without a VPC network, you cannot create VM instances, containers, or App Engine applications.
True
False
Try to create a VM instance
Verify that you cannot create a VM instance without a VPC network.
1. On the Navigation menu (), click Compute Engine > VM instances.
2. Click Create .

- 3. Accept the default values and click **Create**. Notice the error.
- 4. Click Management, security, disks, networking, sole tenancy.
- 5. Click Networking. Notice the No local network available error under Network interfaces.
- 6. Click Cancel

As expected, you cannot create a VM instance without a VPC network!

Task 2. Create an auto mode network

You have been tasked to create an auto mode network with two VM instances. Auto mode networks are easy to set up and use because they automatically create subnets in each region. However, you don't have complete control over the subnets created in your VPC network, including regions and IP address ranges used. Feel free to explore more considerations for choosing an auto mode network, but for now, assume that you are using the auto mode network for prototyping purposes.

Create an auto mode VPC network with firewall rules

- 1. On the Navigation menu (), click VPC network > VPC networks.
- 2. Click Create VPC network.
- 3. For Name, type mynetwork
- For Subnet creation mode, click Automatic. Auto mode networks create subnets in each region automatically.
- 5. For **Firewall rules**, select all available rules.

These are the same standard firewall rules that the default network had. The deny-all-

ingress and **allow-all-egress** rules are also displayed, but you cannot select or disable them because they are implied. These two rules have a lower **Priority** (higher integers indicate lower priorities) so that the allow ICMP, internal, RDP, and SSH rules are considered first.

- 6. Click **Create**. When the new network is ready, notice that a subnet was created for each region.
- 7. Record the IP address range for the subnets in **us-central1** and **europe-west1**. These will be referred to in the next steps.

Tip: If you ever delete the default network, you can quickly re-create it by creating an auto mode network as you just did.

Create a VM instance in us-central1

Create a VM instance in the us-central1 region. Selecting a region and zone determines the subnet and assigns the internal IP address from the subnet's IP address range.

- 1. On the Navigation menu (), click Compute Engine > VM instances.
- 2. Click Create.
- 3. Specify the following, and leave the remaining settings as their defaults:

1.	1.Property	1.	1.Value (type value or select option as specified)
1.	1.Name	1.	1.mynet-us-vm
1.	1.Region	1.	1.us-central1
1.	1.Zone	1.	1.us-central1-c
1.	1.Machine type	1.	1.n1-standard-1 (1 vCPU, 3.75 GB memory)

4. Click Create.

5. Verify that the **Internal IP** for the new instance was assigned from the IP address range for the subnet in **us-central1** (10.128.0.0/20). The **Internal IP** should be 10.128.0.2 because 10.128.0.1 is reserved for the gateway, and you have not configured any other instances in that subnet.

Create a VM instance in europe-west1

Create a VM instance in the europe-west1 region.

- 1. Click Create instance.
- 2. Specify the following, and leave the remaining settings as their defaults:

1.	1.Property	1.Value (type value or select option as specified)	
1.	1.Name	1.mynet-eu-vm	
1.	1.Region	1.europe-west1	
1.	1.Zone	1.europe-west1-c	
1.	1.Machine type	1.n1-standard-1 (1 vCPU, 3.75 GB memory)	

- 3. Click Create. SEP
- 4. Verify that the **Internal IP** for the new instance was assigned from the IP address range for the subnet in **europe-west1** (10.132.0.0/20). The **Internal IP** should be 10.132.0.2 because 10.132.0.1 is reserved for the gateway, and you have not configured any other instances in that subnet.

The **External IP addresses** for both VM instances are ephemeral. If an instance is stopped, any ephemeral external IP addresses assigned to the instance are released back into the general Compute

Engine pool and become available for use by other projects. When a stopped instance is started again, a new ephemeral external IP address is assigned to the instance. Alternatively, you can reserve a static external IP address, which assigns the address to your project indefinitely until you explicitly release it.

Verify connectivity for the VM instances

The firewall rules that you created with **mynetwork** allow ingress SSH and ICMP traffic from within **mynetwork** (internal IP) and outside that network (external IP).

- On the Navigation menu (), click Compute Engine > VM instances. Note the external and internal IP addresses for mynet-eu-vm.
- 2. For **mynet-us-vm**, click **SSH** to launch a terminal and connect.

You can SSH because of the **allow-ssh** firewall rule, which allows incoming traffic from anywhere (0.0.0.0/0) for **tcp:22**. The SSH connection works seamlessly because Compute Engine generates an SSH key for you and stores it in one of the following locations:

- By default, Compute Engine adds the generated key to project or instance metadata.
- If your account is configured to use OS Login, Compute Engine stores the generated key with your user account.

Alternatively, you can control access to Linux instances by creating SSH keys and editing public SSH key metadata.

3. To test connectivity to **mynet-eu-vm**'s internal IP, run the following command, replacing **mynet-eu-vm**'s internal IP:

ping -c 3 <Enter mynet-eu-vm's internal IP here>

You can ping mynet-eu-vm's internal IP because of the allow-internal firewall rule.

4. Repeat the same test by running the following:
ping -c 3 mynet-eu-vm
You can ping mynet-eu-vm by its name because VPC networks have an internal DNS service that allows
you to address instances by their DNS names instead of their internal IP addresses. This is very useful
because the internal IP address can change when you delete and re-create an instance.
5. To test connectivity to mynet-eu-vm 's external IP, run the following command, replacing mynet-eu-
vm's external IP:[sep]
ping -c 3 <enter external="" here="" ip="" mynet-eu-vm's=""></enter>
Which firewall rule allows the ping to mynet-eu-vm's external IP address?
mynetwork-allow-internal
mynetwork-allow-rdp
mynetwork-allow-icmp
mynetwork-allow-ssh Submit
You can SSH to mynet-us-vm and ping mynet-eu-vm 's internal and external IP addresses as

expected. Alternatively, you can SSH to $\mathbf{mynet}\text{-}\mathbf{eu}\text{-}\mathbf{vm}$ and ping $\mathbf{mynet}\text{-}\mathbf{us}\text{-}\mathbf{vm}$'s internal and external

IP addresses, which also works.

Convert the network to a custom mode network

The auto mode network worked great so far, but you have been asked to convert it to a custom mode network so that new subnets aren't automatically created as new regions become available. This could result in overlap with IP addresses used by manually created subnets or static routes, or could interfere with your overall network planning.

- 1. On the **Navigation menu** (), click **VPC network > VPC networks**.
- 2. Click **mynetwork** to open the network details.
- 3. Click Edit.
- 4. Select Custom for the Subnet creation mode.
- 5. Click Save.
- 6. Return to the VPC networks page. Wait for the Mode of mynetwork to change to Custom. You can click Refresh while you wait.

Click *Check my progress* to verify the objective.

Create a VPC network and VM instances

Check my progress

Converting an auto mode network to a custom mode network is an easy task, and it provides you with more flexibility. We recommend that you use custom mode networks in production.

Task 3. Create custom mode networks

You have been tasked to create two additional custom networks, **managementnet** and **privatenet**, along with firewall rules to allow **SSH**, **ICMP**, and **RDP** ingress traffic and VM instances as shown in this diagram (with the exception of vm-appliance):

Note that the IP CIDR ranges of these networks do not overlap. This allows you to set up mechanisms such as VPC peering between the networks. If you specify IP CIDR ranges that are different from your on-premises network, you could even configure hybrid connectivity using VPN or Cloud Interconnect.

Create the managementnet network

Create the **managementnet** network using the Cloud Console.

- 1. In the Cloud Console, on the Navigation menu (), click VPC network > VPC networks.
- 2. Click Create VPC Network.
- 3. For Name, type managementnet
- 4. For Subnet creation mode, click Custom.
- 5. Specify the following, and leave the remaining settings as their defaults:

1.	1.Property	1.	1.Value (type value or select option as specified)
1.	1.Name	1.	1.managementsubnet-us
1.	1.Region	1.	1.us-central1

1. 1.10.130.0.0/20					
6. Click Done .[17]					
7. Click command line . These commands illustrate that networks and subnets can be created using					
the gcloud command line. You will create the privatenet network using these commands with similar parameters.					
8. Click Close [3]					
9. Click Create .					
Create the privatenet network					
Create the privatenet network using the gcloud command line.					
1. In the Cloud Console, click Activate Cloud Shell ().					
2. If prompted, click Continue					
3. To create the privatenet network, run the following command:					
gcloud compute networks create privatenetsubnet-mode=custom					
4. To create the privatesubnet-us subnet, run the following command:					
gcloud compute networks subnets create privatesubnet-usnetwork=privatenetregion=us-central1range=172.16.0.0/24					

5. To create the privatesubnet-eu subnet, run the following command:

gcloud compute networks subnets create privatesubnet-eu --network=privatenet --region=europe-west1 -range=172.20.0.0/20

6. To list the available VPC networks, run the following command:

gcloud compute networks list

The output should look like this (do not copy; this is example output):

NAME	SUBNET_MODE	BGP_ROUTING_MODE	IPV4_RANGE	GATEWAY_IPV4
managementnet	CUSTOM	REGIONAL		
mynetwork	CUSTOM	REGIONAL		
privatenet	CUSTOM	REGIONAL		

7. To list the available VPC subnets (sorted by VPC network), run the following command:

gcloud compute networks subnets list --sort-by=NETWORK

The output should look like this (do not copy; this is example output):

NAME	REGION	NETWORK	RANGE
managementsubnet-us	us-central1	managementnet	10.130.0.0/20
mynetwork	asia-northeast1	mynetwork	10.146.0.0/20
mynetwork	us-west1	mynetwork	10.138.0.0/20
mynetwork	southamerica-east1	mynetwork	10.158.0.0/20
mynetwork	europe-west4	mynetwork	10.164.0.0/20
mynetwork	asia-east1	mynetwork	10.140.0.0/20
mynetwork	europe-north1	mynetwork	10.166.0.0/20
mynetwork	asia-southeast1	mynetwork	10.148.0.0/20
mynetwork	us-east4	mynetwork	10.150.0.0/20
mynetwork	europe-west1	mynetwork	10.132.0.0/20
mynetwork	europe-west2	mynetwork	10.154.0.0/20
mynetwork	europe-west3	mynetwork	10.156.0.0/20
mynetwork	australia-southeast1	mynetwork	10.152.0.0/20
mynetwork	asia-south1	mynetwork	10.160.0.0/20

mynetwork	us-east1	mynetwork	10.142.0.0/20
mynetwork	us-central1	mynetwork	10.128.0.0/20
mynetwork	northamerica-northeast1	mynetwork	10.162.0.0/20
privatesubnet-eu	europe-west1	privatenet	172.20.0.0/20
privatesubnet-us	us-central1	privatenet	172.16.0.0/24

The **managementnet** and **privatenet** networks only have the subnets that you created because they are custom mode networks. **mynetwork** is also a custom mode network, but it started out as an auto mode network, resulting in subnets in each region.

8. In the Cloud Console, on the **Navigation menu** (), click **VPC network** > **VPC networks**. Verify that the same networks and subnets are listed in the Cloud Console.

Create the firewall rules for managementnet

Create firewall rules to allow **SSH**, **ICMP**, and **RDP** ingress traffic to VM instances on the **managementnet** network.

- 1. In the Cloud Console, on the Navigation menu (), click VPC network > Firewall rules.
- 2. Click Create Firewall Rule
- 3. Specify the following, and leave the remaining settings as their defaults:

1.	1.Property	1.	1.Value (type value or select option as specified)
1.	1.Name	1.	1.managementnet-allow-icmp-ssh-rdp
1.	1.Network	1.	1.managementnet
1.	1.Targets	1.	1.All instances in the network
1.	1.Source filter	1.	1.IP Ranges

1.	1.Source IP ranges	1.	1.0.0.0/0
1.	1.Protocols and ports	1.	1.Specified protocols and ports

Make sure to include the **/0** in the **Source IP ranges** to specify all networks.

- 4. Select tcp and specify ports 22 and 3389.
- 5. Select **Other protocols** and specify **icmp** protocol.
- 6. Click **command line**. These commands illustrate that firewall rules can also be created using the gcloud command line. You will create the **privatenet**'s firewall rules using these commands with similar parameters.
- 7. Click Close. SEP
- 8. Click Create.

Create the firewall rules for privatenet

Create the firewall rules for **privatenet** network using the gcloud command line.

- 1. Return to Cloud Shell. If necessary, click Activate Cloud Shell ().
- 2. To create the **privatenet-allow-icmp-ssh-rdp** firewall rule, run the following command:

```
gcloud compute firewall-rules create privatenet-allow-icmp-ssh-rdp --direction=INGRESS --
priority=1000 --network=privatenet --action=ALLOW --rules=icmp,tcp:22,tcp:3389 --source-
ranges=0.0.0.0/0
```

The output should look like this (do not copy; this is example output):

NAME	NETWORK	DIRECTION	PRIORITY	ALLOW	DENY
			1000		

3. To list all the firewall rules (sorted by VPC network), run the following command:

gcloud compute firewall-rules list --sort-by=NETWORK

The output should look like this (do not copy; this is example output):

NAME	NETWORK	DIRECTION	PRIORITY	ALLOW
managementnet-allow-icmp-ssh-rdp	managementnet	INGRESS	1000	icmp,tcp:22,tcp:3389
mynetwork-allow-icmp	mynetwork	INGRESS	1000	icmp
mynetwork-allow-internal	mynetwork	INGRESS	65534	all
mynetwork-allow-rdp	mynetwork	INGRESS	1000	tcp:3389
mynetwork-allow-ssh	mynetwork	INGRESS	1000	tcp:22
privatenet-allow-icmp-ssh-rdp	privatenet	INGRESS	1000	icmp,tcp:22,tcp:3389

The firewall rules for **mynetwork** network have been created for you. You can define multiple protocols and ports in one firewall rule (**privatenet** and **managementnet**) or spread them across multiple rules (**default** and **mynetwork**).

4. In the Cloud Console, on the Navigation menu (), click VPC network > Firewall rules. Verify that the same firewall rules are listed in the Cloud Console.

Click Check my progress to verify the objective.

Create custom mode VPC networks with firewall rules

Check my progress

Next, create two VM instances:

• managementnet-us-vm in managementsubnet-us

• privatenet-us-vm in privatesubnet-us

Create the managementnet-us-vm instance

Create the **managementnet-us-vm** instance using the Cloud Console.

- 1. In the Cloud Console, on the Navigation menu (), click Compute Engine > VM instances.
- 2. Click Create instance
- 3. Specify the following, and leave the remaining settings as their defaults:

1.	1.Property	1.	1.Value (type value or select option as specified)
1.	1.Name	1.	1.managementnet-us-vm
1.	1.Region	1.	1.us-central1
1.	1.Zone	1.	1.us-central1-c
1.	1.Machine type	1.	1.f1-micro (1 vCPU, 614 MB memory)

- 4. Click Management, security, disks, networking, sole tenancy.
- 5. Click **Networking**.
- 6. For **Network interfaces**, click the pencil icon to edit.
- 7. Specify the following, and leave the remaining settings as their defaults:

ı				
	1.	1.Property	1.	1.Value (type value or select option as specified)
l	1.	1.Network	1.	1.managementnet

1. 1.Subnetwor
 1. 1.managementsubnet-us
 k

The subnets available for selection are restricted to those in the selected region (us-central1).

- 8. Click **Done**. SEP
- 9. Click **command line**. This illustrates that VM instances can also be created using the gcloud command line. You will create the **privatenet-us-vm** instance using these commands with similar parameters.
- 10. Click Close. SEP
- 11. Click Create.

Create the privatenet-us-vm instance

Create the **privatenet-us-vm** instance using the gcloud command line.

- 1. Return to Cloud Shell. If necessary, click Activate Cloud Shell ().
- 2. To create the **privatenet-us-vm** instance, run the following command:

```
gcloud compute instances create privatenet-us-vm --zone=us-central1-c --machine-type=f1-micro --
subnet=privatesubnet-us
```

The output should look like this (do not copy; this is example output):

3. To list all the VM instances (sorted by zone), run the following command: [SEP]

```
gcloud compute instances list --sort-by=ZONE
```

The output should look like this (do not copy; this is example output):

NAME	ZONE	MACHINE_TYPE PREEMPTIBLE	INTERNAL_IP	EXTERNAL_IP	STATUS
mynet-eu-vm	europe-west1-c	n1-standard-1	10.132.0.2	34.76.115.41	RUNNING
managementnet-us-vm	us-central1-c	f1-micro	10.130.0.2	35.239.68.123	RUNNING
mynet-us-vm	us-central1-c	n1-standard-1	10.128.0.2	35.202.101.52	RUNNING
privatenet-us-vm	us-central1-c	f1-micro	172.16.0.2	34.66.197.202	RUNNING

4. In the Cloud Console, on the **Navigation menu** (), click **Compute Engine > VM instances**.

Verify that the VM instances are listed in the Cloud Console.

5. For **Columns**, select **Network**. There are three instances in **us-central1-c** and one instance in **europe-west1-c**. However, these instances are spread across three VPC networks (**managementnet**, **mynetwork**, and **privatenet**), with no instance in the same zone and network as another. In the next task, you explore the effect this has on internal connectivity.

Click *Check my progress* to verify the objective.

Create VM instances

Check my progress

You can explore more networking information on each VM instance by clicking the **nic0** link in the **Internal**IP column. The resulting network interface details page shows the subnet along with the IP CIDR range, the firewall rules and routes that apply to the instance, and other network analysis.

Task 4. Explore the connectivity across networks

Explore the connectivity between the VM instances. Specifically, determine the effect of having VM instances in the same zone versus having instances in the same VPC network.

Ping the external IP addresses

Ping the external IP addresses of the VM instances to determine whether you can reach the instances from the public internet.

- 1. In the Cloud Console, on the **Navigation menu**, click **Compute Engine > VM instances**. Note the external IP addresses for **mynet-eu-vm**, **managementnet-us-vm**, and **privatenet-us-vm**.
- 2. For mynet-us-vm, click SSH to launch a terminal and connect.
- 3. To test connectivity to **mynet-eu-vm**'s external IP, run the following command, replacing **mynet-eu-vm**'s external IP:

```
ping -c 3 <Enter mynet-eu-vm's external IP here>
```

This should work!

4. To test connectivity to **managementnet-us-vm**'s external IP, run the following command, replacing **managementnet-us-vm**'s external IP:

```
ping -c 3 <Enter managementnet-us-vm's external IP here>
```

This should work!

5. To test connectivity to **privatenet-us-vm**'s external IP, run the following command,

replacing **privatenet-us-vm**'s external IP:

2. Return to the \boldsymbol{SSH} terminal for $\boldsymbol{mynet\text{-us-vm}}.$

ping -c 3 <enter external="" here="" ip="" privatenet-us-vm's=""></enter>
This should work!
You can ping the external IP address of all VM instances, even though they are in either a different zone or
VPC network. This confirms that public access to those instances is only controlled by the ICMP firewall
rules that you established earlier.
Ping the internal IP addresses
Ping the internal IP addresses of the VM instances to determine whether you can reach the instances from
within a VPC network.
Which instances should you be able to ping from mynet-us-vm using internal IP addresses?
privatenet-us-vm
managementnet-us-vm
mynet-eu-vm
Submit
1. In the Cloud Console, on the Navigation menu , click Compute Engine > VM instances . Note
the internal IP addresses for mynet-eu-vm, managementnet-us-vm, and privatenet-us
vm.seg

3. To test connectivity to **mynet-eu-vm**'s internal IP, run the following command, replacing **mynet-eu-vm**'s internal IP:

```
ping -c 3 <Enter mynet-eu-vm's internal IP here>
```

You can ping the internal IP address of **mynet-eu-vm** because it is on the same VPC network as the source of the ping (**mynet-us-vm**), even though both VM instances are in separate zones, regions, and continents!

4. To test connectivity to **managementnet-us-vm**'s internal IP, run the following command, replacing **managementnet-us-vm**'s internal IP:

```
ping -c 3 <Enter managementnet-us-vm's internal IP here>
```

This should not work, as indicated by a 100% packet loss!

5. To test connectivity to **privatenet-us-vm**'s internal IP, run the following command,

replacing privatenet-us-vm's internal IP:

```
ping -c 3 <Enter privatenet-us-vm's internal IP here>
```

This should not work either, as indicated by a 100% packet loss! You cannot ping the internal IP address of **managementnet-us-vm** and **privatenet-us-vm** because they are in separate VPC networks from the source of the ping (**mynet-us-vm**), even though they are all in the same zone, **us-central1-c**.

Task 5. Review

In this lab, you explored the default network and determined that you cannot create VM instances without a VPC network. Thus, you created a new auto mode VPC network with subnets, routes, firewall rules, and two VM instances and tested the connectivity for the VM instances. Because auto mode networks aren't recommended for production, you converted the auto mode network to a custom mode network. Next, you created two more custom mode VPC networks with firewall rules and VM instances using the Cloud Console

and the gcloud command line. Then you tested the connectivity across VPC networks, which worked when pinging external IP addresses but not when pinging internal IP addresses.

VPC networks are by default isolated private networking domains. Therefore, no internal IP address communication is allowed between networks, unless you set up mechanisms such as VPC peering or VPN.

End your lab

When you have completed your lab, click **End Lab**. Qwiklabs removes the resources you've used and cleans the account for you.

You will be given an opportunity to rate the lab experience. Select the applicable number of stars, type a comment, and then click **Submit**.

The number of stars indicates the following:

- 1 star = Very dissatisfied
- · 2 stars = Dissatisfied
- 3 stars = Neutral
- 4 stars = Satisfied
- 5 stars = Very satisfied

You can close the dialog box if you don't want to provide feedback.

For feedback, suggestions, or corrections, please use the **Support** tab.

Copyright 2020 Google LLC All rights reserved. Google and the Google logo are trademarks of Google LLC.

All other company and product names may be trademarks of the respective companies with which they are

associated.