NAME

strtol, strtoll, strtoq - convert a string to a long integer

SYNOPSIS

```
#include <stdlib.h>
```

long int strtol(const char *nptr, char **endptr, int base);

long long int strtoll(const char *nptr, char **endptr, int base);

Feature Test Macro Requirements for glibc (see **feature_test_macros**(7)):

strtoll():

```
_ISOC99_SOURCE
```

| /* Glibc versions <= 2.19: */_SVID_SOURCE | _BSD_SOURCE

DESCRIPTION

The **strtol**() function converts the initial part of the string in *nptr* to a long integer value according to the given *base*, which must be between 2 and 36 inclusive, or be the special value 0.

The string may begin with an arbitrary amount of white space (as determined by **isspace**(3)) followed by a single optional '+' or '-' sign. If *base* is zero or 16, the string may then include a "0x" or "0X" prefix, and the number will be read in base 16; otherwise, a zero *base* is taken as 10 (decimal) unless the next character is '0', in which case it is taken as 8 (octal).

The remainder of the string is converted to a *long int* value in the obvious manner, stopping at the first character which is not a valid digit in the given base. (In bases above 10, the letter 'A' in either uppercase or lowercase represents 10, 'B' represents 11, and so forth, with 'Z' representing 35.)

If *endptr* is not NULL, **strtol**() stores the address of the first invalid character in **endptr*. If there were no digits at all, **strtol**() stores the original value of *nptr* in **endptr* (and returns 0). In particular, if **nptr* is not '\0' but ***endptr* is '\0' on return, the entire string is valid.

The **strtol(**) function works just like the **strtol(**) function but returns a long long integer value.

RETURN VALUE

The **strtol**() function returns the result of the conversion, unless the value would underflow or overflow. If an underflow occurs, **strtol**() returns **LONG_MIN**. If an overflow occurs, **strtol**() returns **LONG_MAX**. In both cases, *errno* is set to **ERANGE**. Precisely the same holds for **strtoll**() (with **LLONG_MIN** and **LLONG_MAX** instead of **LONG_MIN** and **LONG_MAX**).

ERRORS

EINVAL

(not in C99) The given base contains an unsupported value.

ERANGE

The resulting value was out of range.

The implementation may also set *errno* to **EINVAL** in case no conversion was performed (no digits seen, and 0 returned).

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
<pre>strtol(), strtol(), strtoq()</pre>	Thread safety	MT-Safe locale

CONFORMING TO

 $\textbf{strtol}() : POSIX.1-2001, POSIX.1-2008, C89, C99 \ SVr4, 4.3BSD.$

strtoll(): POSIX.1-2001, POSIX.1-2008, C99.

NOTES

Since **strtol**() can legitimately return 0, **LONG_MAX**, or **LONG_MIN** (**LLONG_MAX** or **LLONG_MIN** for **strtoll**()) on both success and failure, the calling program should set *errno* to 0 before the call, and then determine if an error occurred by checking whether *errno* has a nonzero value after the

call.

According to POSIX.1, in locales other than the "C" and "POSIX", these functions may accept other, implementation-defined numeric strings.

BSD also has

```
quad_t strtoq(const char *nptr, char **endptr, int base);
```

with completely analogous definition. Depending on the wordsize of the current architecture, this may be equivalent to **strtol(**) or to **strtol(**).

EXAMPLE

The program shown below demonstrates the use of **strtol**(). The first command-line argument specifies a string from which **strtol**() should parse a number. The second (optional) argument specifies the base to be used for the conversion. (This argument is converted to numeric form using **atoi**(3), a function that performs no error checking and has a simpler interface than **strtol**().) Some examples of the results produced by this program are the following:

```
$ ./a.out 123
strtol() returned 123
$ ./a.out ' 123'
strtol() returned 123
$ ./a.out 123abc
strtol() returned 123
Further characters after number: abc
$ ./a.out 123abc 55
strtol: Invalid argument
$ ./a.out ''
No digits were found
$ ./a.out 400000000
strtol: Numerical result out of range
```

Program source

```
#include <stdlib.h>
#include <limits.h>
#include <stdio.h>
#include <errno.h>
main(int argc, char *argv[])
    int base;
    char *endptr, *str;
    long val;
    if (argc < 2) {
        fprintf(stderr, "Usage: %s str [base]\n", argv[0]);
        exit(EXIT_FAILURE);
    }
    str = argv[1];
    base = (argc > 2) ? atoi(argv[2]) : 10;
                 /* To distinguish success/failure after call */
    errno = 0;
    val = strtol(str, &endptr, base);
    /* Check for various possible errors */
```

SEE ALSO

atof(3), atoi(3), atol(3), strtod(3), strtoul(3), strtoimax(3)

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.