NAME

tgamma, tgammaf, tgammal - true gamma function

SYNOPSIS

```
#include <math.h>
```

double tgamma(double x);

float tgammaf(float x);

long double tgammal(long double x);

Link with -lm.

Feature Test Macro Requirements for glibc (see **feature_test_macros**(7)):

```
tgamma(), tgammaf(), tgammal():
```

```
_ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L
```

DESCRIPTION

These functions calculate the Gamma function of x.

The Gamma function is defined by

 $Gamma(x) = integral from 0 to infinity of t^(x-1) e^-t dt$

It is defined for every real number except for nonpositive integers. For nonnegative integral m one has

Gamma(m+1) = m!

and, more generally, for all x:

Gamma(x+1) = x * Gamma(x)

Furthermore, the following is valid for all values of *x* outside the poles:

Gamma(x) * Gamma(1 - x) = PI / sin(PI * x)

RETURN VALUE

On success, these functions return Gamma(x).

If x is a NaN, a NaN is returned.

If *x* is positive infinity, positive infinity is returned.

If x is a negative integer, or is negative infinity, a domain error occurs, and a NaN is returned.

If the result overflows, a range error occurs, and the functions return HUGE_VAL, HUGE_VALF, or HUGE_VALL, respectively, with the correct mathematical sign.

If the result underflows, a range error occurs, and the functions return 0, with the correct mathematical sign.

If x is -0 or +0, a pole error occurs, and the functions return **HUGE_VAL**, **HUGE_VALF**, or **HUGE_VALL**, respectively, with the same sign as the 0.

ERRORS

See **math_error**(7) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Domain error: x is a negative integer, or negative infinity

errno is set to **EDOM**. An invalid floating-point exception (**FE_INVALID**) is raised (but see BUGS).

Pole error: x is +0 or -0

errno is set to **ERANGE**. A divide-by-zero floating-point exception (**FE_DIVBYZERO**) is raised.

Range error: result overflow

errno is set to **ERANGE**. An overflow floating-point exception (**FE_OVERFLOW**) is raised. glibc also gives the following error which is not specified in C99 or POSIX.1-2001.

Range error: result underflow

An underflow floating-point exception (FE_UNDERFLOW) is raised, and *errno* is set to ERANGE.

VERSIONS

These functions first appeared in glibc in version 2.1.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
tgamma(), tgammaf(), tgammal()	Thread safety	MT-Safe

CONFORMING TO

C99, POSIX.1-2001, POSIX.1-2008.

NOTES

This function had to be called "true gamma function" since there is already a function **gamma**(3) that returns something else (see **gamma**(3) for details).

BUGS

Before version 2.18, the glibc implementation of these functions did not set errno to **EDOM** when x is negative infinity.

Before glibc 2.19, the glibc implementation of these functions did not set errno to **ERANGE** on an underflow range error. x

In glibc versions 2.3.3 and earlier, an argument of +0 or -0 incorrectly produced a domain error (*errno* set to **EDOM** and an **FE_INVALID** exception raised), rather than a pole error.

SEE ALSO

gamma(3), lgamma(3)

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.