#### **NAME**

getpriority, setpriority - get/set program scheduling priority

# **SYNOPSIS**

#include <sys/time.h>
#include <sys/resource.h>

int getpriority(int which, id\_t who);

int setpriority(int which, id t who, int prio);

### DESCRIPTION

The scheduling priority of the process, process group, or user, as indicated by *which* and *who* is obtained with the **getpriority**() call and set with the **setpriority**() call. The process attribute dealt with by these system calls is the same attribute (also known as the "nice" value) that is dealt with by **nice**(2).

The value *which* is one of **PRIO\_PROCESS**, **PRIO\_PGRP**, or **PRIO\_USER**, and *who* is interpreted relative to *which* (a process identifier for **PRIO\_PROCESS**, process group identifier for **PRIO\_PGRP**, and a user ID for **PRIO\_USER**). A zero value for *who* denotes (respectively) the calling process, the process group of the calling process, or the real user ID of the calling process.

The *prio* argument is a value in the range -20 to 19 (but see NOTES below). with -20 being the highest priority and 19 being the lowest priority. Attempts to set a priority outside this range are silently clamped to the range. The default priority is 0; lower values give a process a higher scheduling priority.

The **getpriority**() call returns the highest priority (lowest numerical value) enjoyed by any of the specified processes. The **setpriority**() call sets the priorities of all of the specified processes to the specified value.

Traditionally, only a privileged process could lower the nice value (i.e., set a higher priority). However, since Linux 2.6.12, an unprivileged process can decrease the nice value of a target process that has a suitable **RLIMIT\_NICE** soft limit; see **getrlimit**(2) for details.

#### **RETURN VALUE**

On success, **getpriority**() returns the calling thread's nice value, which may be a negative number. On error, it returns -1 and sets *errno* to indicate the cause of the error. Since a successful call to **getpriority**() can legitimately return the value -1, it is necessary to clear the external variable *errno* prior to the call, then check it afterward to determine if -1 is an error or a legitimate value.

setpriority() returns 0 on success. On error, it returns -1 and sets errno to indicate the cause of the error.

## **ERRORS**

## **EINVAL**

which was not one of PRIO\_PROCESS, PRIO\_PGRP, or PRIO\_USER.

### **ESRCH**

No process was located using the which and who values specified.

In addition to the errors indicated above, **setpriority**() may fail if:

#### **EACCES**

The caller attempted to set a lower nice value (i.e., a higher process priority), but did not have the required privilege (on Linux: did not have the **CAP\_SYS\_NICE** capability).

### **EPERM**

A process was located, but its effective user ID did not match either the effective or the real user ID of the caller, and was not privileged (on Linux: did not have the **CAP\_SYS\_NICE** capability). But see NOTES below.

## **CONFORMING TO**

POSIX.1-2001, POSIX.1-2008, SVr4, 4.4BSD (these interfaces first appeared in 4.2BSD).

#### **NOTES**

For further details on the nice value, see **sched**(7).

*Note*: the addition of the "autogroup" feature in Linux 2.6.38 means that the nice value no longer has its traditional effect in many circumstances. For details, see **sched**(7).

A child created by **fork**(2) inherits its parent's nice value. The nice value is preserved across **execve**(2).

The details on the condition for **EPERM** depend on the system. The above description is what POSIX.1-2001 says, and seems to be followed on all System V-like systems. Linux kernels before 2.6.12 required the real or effective user ID of the caller to match the real user of the process *who* (instead of its effective user ID). Linux 2.6.12 and later require the effective user ID of the caller to match the real or effective user ID of the process *who*. All BSD-like systems (SunOS 4.1.3, Ultrix 4.2, 4.3BSD, FreeBSD 4.3, OpenBSD-2.5, ...) behave in the same manner as Linux 2.6.12 and later.

Including <sys/time.h> is not required these days, but increases portability. (Indeed, <sys/resource.h> defines the rusage structure with fields of type struct timeval defined in <sys/time.h>.)

### C library/kernel differences

Within the kernel, nice values are actually represented using the range 40..1 (since negative numbers are error codes) and these are the values employed by the **setpriority**() and **getpriority**() system calls. The glibc wrapper functions for these system calls handle the translations between the user-land and kernel representations of the nice value according to the formula unice = 20 - knice. (Thus, the kernel's 40..1 range corresponds to the range -20..19 as seen by user space.)

## **BUGS**

According to POSIX, the nice value is a per-process setting. However, under the current Linux/NPTL implementation of POSIX threads, the nice value is a per-thread attribute: different threads in the same process can have different nice values. Portable applications should avoid relying on the Linux behavior, which may be made standards conformant in the future.

### **SEE ALSO**

nice(1), renice(1), fork(2), capabilities(7), sched(7)

Documentation/scheduler/sched-nice-design.txt in the Linux kernel source tree (since Linux 2.6.23)

#### **COLOPHON**

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.