## **NAME**

SLIST\_EMPTY, SLIST\_ENTRY, SLIST\_FIRST, SLIST\_FOREACH, SLIST\_HEAD, SLIST\_HEAD\_INITIALIZER, SLIST\_INIT, SLIST\_INSERT\_AFTER, SLIST\_INSERT\_HEAD, SLIST\_NEXT, SLIST\_REMOVE\_HEAD, SLIST\_REMOVE, STAILQ\_CONCAT, STAILQ\_EMPTY, STAILO\_ENTRY, STAILO\_FIRST, STAILO\_FOREACH, STAILO HEAD. STAILO\_HEAD\_INITIALIZER, STAILQ\_INIT, STAILQ\_INSERT\_AFTER, STAILQ\_INSERT\_HEAD, STAILQ\_INSERT\_TAIL, STAILQ\_NEXT, STAILQ\_REMOVE\_HEAD, STAILO REMOVE, LIST\_EMPTY, LIST\_ENTRY, LIST\_FIRST, LIST\_FOREACH, LIST\_HEAD, LIST\_HEAD\_INITIALIZER, LIST\_INIT, LIST\_INSERT\_AFTER, LIST\_INSERT\_BEFORE, LIST\_INSERT\_HEAD, LIST\_NEXT, LIST\_REMOVE, TAILQ\_CONCAT, TAILQ\_EMPTY, TAILO\_ENTRY, TAILO\_FIRST, TAILO\_FOREACH, TAILO\_FOREACH\_REVERSE, TAILO\_HEAD, TAILO\_HEAD\_INITIALIZER, TAILO\_INIT, TAILO\_INSERT\_AFTER, TAILO\_INSERT\_BEFORE, TAILO\_INSERT\_HEAD, TAILO\_INSERT\_TAIL, TAILO\_LAST, TAILO\_NEXT, TAILO\_PREV, TAILO\_REMOVE, TAILO\_SWAP — implementations of singly-linked lists, singly-linked tail queues, lists and tail queues

## **SYNOPSIS**

```
#include <sys/queue.h>
```

SLIST\_EMPTY(SLIST\_HEAD \*head);

**SLIST\_ENTRY**(*TYPE*);

SLIST\_FIRST(SLIST\_HEAD \*head);

**SLIST\_FOREACH**(TYPE \*var, SLIST\_HEAD \*head, SLIST\_ENTRY NAME);

**SLIST\_HEAD**(*HEADNAME*, *TYPE*);

SLIST\_HEAD\_INITIALIZER(SLIST\_HEAD head);

**SLIST\_INIT**(SLIST\_HEAD \*head);

SLIST\_INSERT\_AFTER(TYPE \*listelm, TYPE \*elm, SLIST\_ENTRY NAME);

 $\textbf{SLIST\_INSERT\_HEAD}(SLIST\_HEAD * head, TYPE * elm, SLIST\_ENTRY NAME);$ 

SLIST\_NEXT(TYPE \*elm, SLIST\_ENTRY NAME);

**SLIST\_REMOVE\_HEAD**(SLIST\_HEAD \*head, SLIST\_ENTRY NAME);

SLIST\_REMOVE(SLIST\_HEAD \*head, TYPE \*elm, TYPE, SLIST\_ENTRY NAME);

**STAILO\_CONCAT**(STAILO\_HEAD \*head1, STAILO\_HEAD \*head2);

**STAILQ\_EMPTY**(STAILQ\_HEAD \*head);

**STAILO\_ENTRY**(TYPE);

**STAILQ\_FIRST**(STAILQ\_HEAD \*head);

STAILO\_FOREACH(TYPE \*var, STAILO\_HEAD \*head, STAILO\_ENTRY NAME);

**STAILO\_HEAD**(HEADNAME, TYPE);

STAILQ\_HEAD\_INITIALIZER(STAILQ\_HEAD head);

**STAILQ\_INIT**(STAILQ\_HEAD \*head);

```
STAILO_INSERT_HEAD(STAILO_HEAD *head, TYPE *elm, STAILO_ENTRY NAME);
STAILQ_INSERT_TAIL(STAILQ_HEAD *head, TYPE *elm, STAILQ_ENTRY NAME);
STAILO_NEXT(TYPE *elm, STAILO_ENTRY NAME);
STAILQ_REMOVE_HEAD(STAILQ_HEAD *head, STAILQ_ENTRY NAME);
STAILQ_REMOVE(STAILQ_HEAD *head, TYPE *elm, TYPE, STAILQ_ENTRY NAME);
LIST_EMPTY(LIST_HEAD *head);
LIST_ENTRY(TYPE);
LIST_FIRST(LIST_HEAD *head);
LIST_FOREACH(TYPE *var, LIST_HEAD *head, LIST_ENTRY NAME);
LIST_HEAD(HEADNAME, TYPE);
LIST_HEAD_INITIALIZER(LIST_HEAD head);
LIST_INIT(LIST_HEAD *head);
LIST_INSERT_AFTER(TYPE *listelm, TYPE *elm, LIST_ENTRY NAME);
LIST_INSERT_BEFORE(TYPE *listelm, TYPE *elm, LIST_ENTRY NAME);
LIST_INSERT_HEAD(LIST_HEAD *head, TYPE *elm, LIST_ENTRY NAME);
LIST_NEXT(TYPE *elm, LIST_ENTRY NAME);
LIST_REMOVE(TYPE *elm, LIST_ENTRY NAME);
LIST_SWAP(LIST_HEAD *head1, LIST_HEAD *head2, TYPE, LIST_ENTRY NAME);
TAILQ_CONCAT(TAILQ_HEAD *head1, TAILQ_HEAD *head2, TAILQ_ENTRY NAME);
TAILQ_EMPTY(TAILQ_HEAD *head);
TAILQ\_ENTRY(TYPE);
TAILQ_FIRST(TAILQ_HEAD *head);
TAILO_FOREACH(TYPE *var, TAILO_HEAD *head, TAILO_ENTRY NAME);
TAILQ_FOREACH_REVERSE(TYPE *var, TAILQ_HEAD *head, HEADNAME,
    TAILQ_ENTRY NAME);
TAILO_HEAD(HEADNAME, TYPE);
TAILQ_HEAD_INITIALIZER(TAILQ_HEAD head);
TAILQ_INIT(TAILQ_HEAD *head);
TAILO_INSERT_AFTER(TAILO_HEAD *head, TYPE *listelm, TYPE *elm,
    TAILQ_ENTRY NAME);
TAILO_INSERT_BEFORE(TYPE *listelm, TYPE *elm, TAILO_ENTRY NAME);
TAILQ_INSERT_HEAD(TAILQ_HEAD *head, TYPE *elm, TAILQ_ENTRY NAME);
TAILO_INSERT_TAIL(TAILO_HEAD *head, TYPE *elm, TAILO_ENTRY NAME);
TAILQ_LAST(TAILQ_HEAD *head, HEADNAME);
```

```
TAILQ_NEXT(TYPE *elm, TAILQ_ENTRY NAME);

TAILQ_PREV(TYPE *elm, HEADNAME, TAILQ_ENTRY NAME);

TAILQ_REMOVE(TAILQ_HEAD *head, TYPE *elm, TAILQ_ENTRY NAME);

TAILQ_SWAP(TAILQ_HEAD *head1, TAILQ_HEAD *head2, TYPE, TAILQ_ENTRY NAME);
```

## **DESCRIPTION**

These macros define and operate on four types of data structures: singly-linked lists, singly-linked tail queues, lists, and tail queues. All four structures support the following functionality:

- 1. Insertion of a new entry at the head of the list.
- 2. Insertion of a new entry after any element in the list.
- 3. O(1) removal of an entry from the head of the list.
- 4. Forward traversal through the list.
- 5. Swapping the contents of two lists.

Singly-linked lists are the simplest of the four data structures and support only the above functionality. Singly-linked lists are ideal for applications with large datasets and few or no removals, or for implementing a LIFO queue. Singly-linked lists add the following functionality:

1. O(n) removal of any entry in the list.

Singly-linked tail queues add the following functionality:

- 1. Entries can be added at the end of a list.
- 2. O(n) removal of any entry in the list.
- 3. They may be concatenated.

## However:

- 1. All list insertions must specify the head of the list.
- 2. Each head entry requires two pointers rather than one.
- 3. Code size is about 15% greater and operations run about 20% slower than singly-linked lists.

Singly-linked tail queues are ideal for applications with large datasets and few or no removals, or for implementing a FIFO queue.

All doubly linked types of data structures (lists and tail queues) additionally allow:

- 1. Insertion of a new entry before any element in the list.
- 2. O(1) removal of any entry in the list.

### However:

- 1. Each element requires two pointers rather than one.
- Code size and execution time of operations (except for removal) is about twice that of the singly-linked data-structures.

Linked lists are the simplest of the doubly linked data structures. They add the following functionality over the above:

1. They may be traversed backwards.

### However:

1. To traverse backwards, an entry to begin the traversal and the list in which it is contained must be specified.

Tail queues add the following functionality:

- 1. Entries can be added at the end of a list.
- 2. They may be traversed backwards, from tail to head.
- 3. They may be concatenated.

### However:

- 1. All list insertions and removals must specify the head of the list.
- 2. Each head entry requires two pointers rather than one.
- 3. Code size is about 15% greater and operations run about 20% slower than singly-linked lists.

In the macro definitions, *TYPE* is the name of a user defined structure, that must contain a field of type SLIST\_ENTRY, STAILQ\_ENTRY, LIST\_ENTRY, or TAILQ\_ENTRY, named *NAME*. The argument *HEADNAME* is the name of a user defined structure that must be declared using the macros SLIST\_HEAD, STAILQ\_HEAD, LIST\_HEAD, or TAILQ\_HEAD. See the examples below for further explanation of how these macros are used.

# Singly-linked lists

A singly-linked list is headed by a structure defined by the **SLIST\_HEAD** macro. This structure contains a single pointer to the first element on the list. The elements are singly linked for minimum space and pointer manipulation overhead at the expense of O(n) removal for arbitrary elements. New elements can be added to the list after an existing element or at the head of the list. An SLIST\_HEAD structure is declared as follows:

```
SLIST_HEAD (HEADNAME, TYPE) head;
```

where *HEADNAME* is the name of the structure to be defined, and *TYPE* is the type of the elements to be linked into the list. A pointer to the head of the list can later be declared as:

```
struct HEADNAME *headp;
```

(The names head and headp are user selectable.)

The macro **SLIST\_HEAD\_INITIALIZER** evaluates to an initializer for the list head.

The macro **SLIST\_EMPTY** evaluates to true if there are no elements in the list.

The macro **SLIST\_ENTRY** declares a structure that connects the elements in the list.

The macro **SLIST\_FIRST** returns the first element in the list or NULL if the list is empty.

The macro **SLIST\_FOREACH** traverses the list referenced by *head* in the forward direction, assigning each element in turn to *var*.

The macro **SLIST\_INIT** initializes the list referenced by head.

The macro **SLIST\_INSERT\_HEAD** inserts the new element *elm* at the head of the list.

The macro **SLIST INSERT AFTER** inserts the new element *elm* after the element *listelm*.

The macro **SLIST\_NEXT** returns the next element in the list.

The macro **SLIST\_REMOVE\_HEAD** removes the element *elm* from the head of the list. For optimum efficiency, elements being removed from the head of the list should explicitly use this macro instead of the generic *SLIST\_REMOVE* macro.

The macro **SLIST\_REMOVE** removes the element *elm* from the list.

## Singly-linked list example

```
head. */
struct entry {
       . . .
       SLIST_ENTRY(entry) entries; /* Singly-linked List. */
} *n1, *n2, *n3, *np;
                                      /* Initialize the list. */
SLIST_INIT(&head);
n1 = malloc(sizeof(struct entry));  /* Insert at the head. */
SLIST_INSERT_HEAD(&head, n1, entries);
n2 = malloc(sizeof(struct entry));  /* Insert after. */
SLIST_INSERT_AFTER(n1, n2, entries);
SLIST_REMOVE(&head, n2, entry, entries);/* Deletion. */
free (n2);
n3 = SLIST_FIRST(&head);
SLIST_REMOVE_HEAD(&head, entries); /* Deletion from the head. */
free(n3);
                                      /* Forward traversal. */
SLIST_FOREACH(np, &head, entries)
       np-> ...
while (!SLIST_EMPTY(&head)) {
                                     /* List Deletion. */
       n1 = SLIST_FIRST(&head);
       SLIST_REMOVE_HEAD(&head, entries);
       free (n1);
}
```

## Singly-linked tail queues

A singly-linked tail queue is headed by a structure defined by the **STAILQ\_HEAD** macro. This structure contains a pair of pointers, one to the first element in the tail queue and the other to the last element in the tail queue. The elements are singly linked for minimum space and pointer manipulation overhead at the expense of O(n) removal for arbitrary elements. New elements can be added to the tail queue after an existing element, at the head of the tail queue, or at the end of the tail queue. A STAILQ\_HEAD structure is declared as follows:

```
STAILQ_HEAD(HEADNAME, TYPE) head;
```

where HEADNAME is the name of the structure to be defined, and TYPE is the type of the elements to be linked into the tail queue. A pointer to the head of the tail queue can later be declared as:

```
struct HEADNAME *headp;
```

(The names head and headp are user selectable.)

The macro **STAILQ\_HEAD\_INITIALIZER** evaluates to an initializer for the tail queue head.

The macro **STAILQ\_CONCAT** concatenates the tail queue headed by *head2* onto the end of the one headed by *head1* removing all entries from the former.

The macro **STAILO\_EMPTY** evaluates to true if there are no items on the tail queue.

The macro **STAILQ\_ENTRY** declares a structure that connects the elements in the tail queue.

The macro **STAILO\_FIRST** returns the first item on the tail queue or NULL if the tail queue is empty.

The macro **STAILQ\_FOREACH** traverses the tail queue referenced by *head* in the forward direction, assigning each element in turn to *var*.

The macro **STAILQ\_INIT** initializes the tail queue referenced by *head*.

The macro **STAILO\_INSERT\_HEAD** inserts the new element *elm* at the head of the tail queue.

The macro **STAILQ\_INSERT\_TAIL** inserts the new element elm at the end of the tail queue.

The macro **STAILO\_INSERT\_AFTER** inserts the new element elm after the element listelm.

The macro **STAILQ\_NEXT** returns the next item on the tail queue, or NULL this item is the last.

The macro **STAILQ\_REMOVE\_HEAD** removes the element at the head of the tail queue. For optimum efficiency, elements being removed from the head of the tail queue should use this macro explicitly rather than the generic *STAILQ\_REMOVE* macro.

The macro **STAILO\_REMOVE** removes the element *elm* from the tail queue.

## Singly-linked tail queue example

```
STAILQ_HEAD(stailhead, entry) head =
    STAILQ_HEAD_INITIALIZER(head);
struct stailhead *headp;
                                      /* Singly-linked tail queue head. */
struct entry {
       . . .
       STAILQ_ENTRY(entry) entries; /* Tail queue. */
} *n1, *n2, *n3, *np;
STAILQ_INIT(&head);
                                      /* Initialize the queue. */
                                     /* Insert at the head. */
n1 = malloc(sizeof(struct entry));
STAILQ_INSERT_HEAD(&head, n1, entries);
n1 = malloc(sizeof(struct entry));
                                     /* Insert at the tail. */
STAILQ_INSERT_TAIL(&head, n1, entries);
                                     /* Insert after. */
n2 = malloc(sizeof(struct entry));
STAILQ_INSERT_AFTER(&head, n1, n2, entries);
                                      /* Deletion. */
STAILQ_REMOVE(&head, n2, entry, entries);
free(n2);
                                      /* Deletion from the head. */
n3 = STAILQ_FIRST(&head);
STAILQ_REMOVE_HEAD(&head, entries);
free(n3);
                                      /* Forward traversal. */
STAILQ_FOREACH(np, &head, entries)
       np-> ...
                                      /* TailQ Deletion. */
while (!STAILQ_EMPTY(&head)) {
       n1 = STAILQ_FIRST(&head);
```

```
STAILQ_REMOVE_HEAD(&head, entries);
    free(n1);
}

/* Faster TailQ Deletion. */
n1 = STAILQ_FIRST(&head);
while (n1 != NULL) {
    n2 = STAILQ_NEXT(n1, entries);
    free(n1);
    n1 = n2;
}
STAILQ_INIT(&head);
```

### Lists

A list is headed by a structure defined by the **LIST\_HEAD** macro. This structure contains a single pointer to the first element on the list. The elements are doubly linked so that an arbitrary element can be removed without traversing the list. New elements can be added to the list after an existing element, before an existing element, or at the head of the list. A LIST\_HEAD structure is declared as follows:

```
LIST_HEAD (HEADNAME, TYPE) head;
```

where *HEADNAME* is the name of the structure to be defined, and *TYPE* is the type of the elements to be linked into the list. A pointer to the head of the list can later be declared as:

```
struct HEADNAME *headp;
```

(The names head and headp are user selectable.)

The macro LIST\_HEAD\_INITIALIZER evaluates to an initializer for the list head.

The macro **LIST\_EMPTY** evaluates to true if there are no elements in the list.

The macro **LIST\_ENTRY** declares a structure that connects the elements in the list.

The macro **LIST\_FIRST** returns the first element in the list or NULL if the list is empty.

The macro **LIST\_FOREACH** traverses the list referenced by *head* in the forward direction, assigning each element in turn to *var*.

The macro **LIST\_INIT** initializes the list referenced by head.

The macro **LIST\_INSERT\_HEAD** inserts the new element elm at the head of the list.

The macro LIST\_INSERT\_AFTER inserts the new element elm after the element listelm.

The macro LIST\_INSERT\_BEFORE inserts the new element elm before the element listelm.

The macro **LIST\_NEXT** returns the next element in the list, or NULL if this is the last.

The macro **LIST\_REMOVE** removes the element *elm* from the list.

## List example

```
/* Initialize the list. */
LIST_INIT(&head);
n1 = malloc(sizeof(struct entry));  /* Insert at the head. */
LIST_INSERT_HEAD(&head, n1, entries);
n2 = malloc(sizeof(struct entry));
                                      /* Insert after. */
LIST_INSERT_AFTER(n1, n2, entries);
                                      /* Insert before. */
n3 = malloc(sizeof(struct entry));
LIST_INSERT_BEFORE (n2, n3, entries);
LIST_REMOVE(n2, entries);
                                      /* Deletion. */
free (n2);
                                      /* Forward traversal. */
LIST_FOREACH(np, &head, entries)
       np-> ...
                                    /* List Deletion. */
while (!LIST_EMPTY(&head)) {
       n1 = LIST_FIRST(&head);
       LIST_REMOVE(n1, entries);
       free(n1);
}
                                             /* Faster List Deletion. */
n1 = LIST_FIRST(&head);
while (n1 != NULL) {
       n2 = LIST_NEXT(n1, entries);
       free(n1);
       n1 = n2;
}
LIST_INIT(&head);
```

## Tail queues

A tail queue is headed by a structure defined by the **TAILQ\_HEAD** macro. This structure contains a pair of pointers, one to the first element in the tail queue and the other to the last element in the tail queue. The elements are doubly linked so that an arbitrary element can be removed without traversing the tail queue. New elements can be added to the tail queue after an existing element, before an existing element, at the head of the tail queue, or at the end of the tail queue. A TAILQ\_HEAD structure is declared as follows:

```
TAILQ_HEAD (HEADNAME, TYPE) head;
```

where HEADNAME is the name of the structure to be defined, and TYPE is the type of the elements to be linked into the tail queue. A pointer to the head of the tail queue can later be declared as:

```
struct HEADNAME *headp;
```

(The names head and headp are user selectable.)

The macro TAILQ\_HEAD\_INITIALIZER evaluates to an initializer for the tail queue head.

The macro **TAILO\_CONCAT** concatenates the tail queue headed by *head2* onto the end of the one headed by *head1* removing all entries from the former.

The macro **TAILQ\_EMPTY** evaluates to true if there are no items on the tail queue.

The macro TAILQ\_ENTRY declares a structure that connects the elements in the tail queue.

The macro **TAILQ\_FIRST** returns the first item on the tail queue or NULL if the tail queue is empty.

The macro **TAILO\_FOREACH** traverses the tail queue referenced by *head* in the forward direction, assigning each element in turn to *var*. *var* is set to NULL if the loop completes normally, or if there were no elements.

The macro **TAILQ\_FOREACH\_REVERSE** traverses the tail queue referenced by *head* in the reverse direction, assigning each element in turn to *var*.

The macro **TAILQ\_INIT** initializes the tail queue referenced by head.

The macro **TAILO\_INSERT\_HEAD** inserts the new element elm at the head of the tail queue.

The macro **TAILQ\_INSERT\_TAIL** inserts the new element elm at the end of the tail queue.

The macro TAILQ\_INSERT\_AFTER inserts the new element elm after the element listelm.

The macro TAILO\_INSERT\_BEFORE inserts the new element elm before the element listelm.

The macro **TAILO\_LAST** returns the last item on the tail queue. If the tail queue is empty the return value is NULL.

The macro TAILQ\_NEXT returns the next item on the tail queue, or NULL if this item is the last.

The macro **TAILO\_PREV** returns the previous item on the tail queue, or NULL if this item is the first.

The macro **TAILO\_REMOVE** removes the element *elm* from the tail queue.

The macro **TAILQ\_SWAP** swaps the contents of head1 and head2.

## Tail queue example

```
TAILQ_HEAD(tailhead, entry) head =
    TAILQ_HEAD_INITIALIZER(head);
struct tailhead *headp;
                                             /* Tail queue head. */
struct entry {
       TAILQ_ENTRY(entry) entries; /* Tail queue. */
} *n1, *n2, *n3, *np;
                                     /* Initialize the queue. */
TAILQ_INIT(&head);
n1 = malloc(sizeof(struct entry));
                                   /* Insert at the head. */
TAILQ_INSERT_HEAD(&head, n1, entries);
                                   /* Insert at the tail. */
n1 = malloc(sizeof(struct entry));
TAILQ_INSERT_TAIL(&head, n1, entries);
n2 = malloc(sizeof(struct entry));  /* Insert after. */
TAILQ_INSERT_AFTER(&head, n1, n2, entries);
                                     /* Insert before. */
n3 = malloc(sizeof(struct entry));
TAILQ_INSERT_BEFORE(n2, n3, entries);
TAILQ_REMOVE(&head, n2, entries); /* Deletion. */
free (n2);
```

```
/* Forward traversal. */
TAILQ_FOREACH(np, &head, entries)
       np-> ...
                                      /* Reverse traversal. */
TAILQ_FOREACH_REVERSE(np, &head, tailhead, entries)
       np-> ...
                                     /* TailQ Deletion. */
while (!TAILQ_EMPTY(&head)) {
       n1 = TAILQ_FIRST(&head);
       TAILQ_REMOVE(&head, n1, entries);
       free(n1);
}
                                      /* Faster TailQ Deletion. */
n1 = TAILQ_FIRST(&head);
while (n1 != NULL) {
       n2 = TAILQ_NEXT(n1, entries);
       free(n1);
       n1 = n2;
}
TAILQ_INIT(&head);
n2 = malloc(sizeof(struct entry)); /* Insert before. */
CIRCLEQ_INSERT_BEFORE(&head, n1, n2, entries);
                                    /* Forward traversal. */
for (np = head.cqh_first; np != (void *) &head;
       np = np->entries.cqe_next)
   np-> ...
                                    /* Reverse traversal. */
for (np = head.cqh_last; np != (void *) &head; np = np->entries.cqe_prev)
    np-> ...
                                    /* Delete. */
while (head.cqh_first != (void *)&head)
    CIRCLEQ_REMOVE(&head, head.cqh_first, entries);
```

## **CONFORMING TO**

Not in POSIX.1, POSIX.1-2001 or POSIX.1-2008. Present on the BSDs. **queue** functions first appeared in 44BSD.

# **SEE ALSO**

insque(3)

# COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.