NAME

ibv_create_ah, ibv_destroy_ah - create or destroy an address handle (AH)

SYNOPSIS

#include <infiniband/verbs.h>

int ibv_destroy_ah(struct ibv_ah *ah);

DESCRIPTION

ibv_create_ah() creates an address handle (AH) associated with the protection domain pd. The argument attr is an ibv_ah_attr struct, as defined in <infiniband/verbs.h>.

```
struct ibv_ah_attr {
                   struct ibv_global_route grh;
                                                      /* Global Routing Header (GRH) attributes */
                                                /* Destination LID */
                   uint16_t
                                     dlid;
                                    sl;
                   uint8_t
                                              /* Service Level */
                   uint8_t
                                    src_path_bits; /* Source path bits */
                   uint8_t
                                    static_rate; /* Maximum static rate */
                   uint8_t
                                    is_global;
                                                 /* GRH attributes are valid */
                                                 /* Physical port number */
                   uint8_t
                                    port_num;
};
struct ibv_global_route {
                   union ibv_gid
                                       dgid;
                                                   /* Destination GID or MGID */
                                                  /* Flow label */
                                     flow_label;
                   uint32_t
                                    sgid_index;
                                                  /* Source GID index */
                   uint8_t
                                    hop_limit;
                                                  /* Hop limit */
                   uint8_t
                   uint8_t
                                    traffic_class; /* Traffic class */
};
```

ibv_destroy_ah() destroys the AH *ah*.

RETURN VALUE

ibv_create_ah() returns a pointer to the created AH, or NULL if the request fails.

NOTES

If port flag IBV_QPF_GRH_REQUIRED is set then **ibv_create_ah()** must be created with definition of 'struct ibv_ah_attr { .is_global = 1; .grh = {...}; }'.

ibv_destroy_ah() returns 0 on success, or the value of errno on failure (which indicates the failure reason).

SEE ALSO

```
ibv_alloc_pd(3), ibv_init_ah_from_wc(3), ibv_create_ah_from_wc(3)
```

AUTHORS

Dotan Barak <dotanba@gmail.com>