#### **NAME**

cp - copy files and directories

### **SYNOPSIS**

- **cp** [OPTION]... [-T] SOURCE DEST
- **cp** [OPTION]... SOURCE... DIRECTORY
- **cp** [OPTION]... -t DIRECTORY SOURCE...

## **DESCRIPTION**

Copy SOURCE to DEST, or multiple SOURCE(s) to DIRECTORY.

Mandatory arguments to long options are mandatory for short options too.

#### -a, --archive

same as **-dR --preserve**=*all* 

### --attributes-only

don't copy the file data, just the attributes

## --backup[=CONTROL]

make a backup of each existing destination file

**-b** like **--backup** but does not accept an argument

## --copy-contents

copy contents of special files when recursive

-d same as --no-dereference --preserve=links

#### -f, --force

if an existing destination file cannot be opened, remove it and try again (this option is ignored when the  $-\mathbf{n}$  option is also used)

### -i, --interactive

prompt before overwrite (overrides a previous -n option)

**-H** follow command–line symbolic links in SOURCE

## –l, ––link

hard link files instead of copying

## -L, --dereference

always follow symbolic links in SOURCE

## -n, --no-clobber

do not overwrite an existing file (overrides a previous **–i** option)

### -P, --no-dereference

never follow symbolic links in SOURCE

**-p** same as **--preserve**=*mode*,ownership,timestamps

## --preserve[=ATTR\_LIST]

preserve the specified attributes (default: mode,ownership,timestamps), if possible additional attributes: context, links, xattr, all

## --no-preserve=ATTR\_LIST

don't preserve the specified attributes

#### --parents

use full source file name under DIRECTORY

## -R, -r, --recursive

copy directories recursively

## --reflink[=WHEN]

control clone/CoW copies. See below

#### --remove-destination

remove each existing destination file before attempting to open it (contrast with --force)

#### --sparse=WHEN

control creation of sparse files. See below

#### --strip-trailing-slashes

remove any trailing slashes from each SOURCE argument

#### -s, --symbolic-link

make symbolic links instead of copying

#### -S, --suffix=SUFFIX

override the usual backup suffix

## -t, --target-directory=DIRECTORY

copy all SOURCE arguments into DIRECTORY

## -T, --no-target-directory

treat DEST as a normal file

### -u, --update

copy only when the SOURCE file is newer than the destination file or when the destination file is missing

### -v, --verbose

explain what is being done

### -x, --one-file-system

stay on this file system

**-Z** set SELinux security context of destination file to default type

#### --context[=CTX]

like -Z, or if CTX is specified then set the SELinux or SMACK security context to CTX

--help display this help and exit

## --version

output version information and exit

By default, sparse SOURCE files are detected by a crude heuristic and the corresponding DEST file is made sparse as well. That is the behavior selected by —-sparse=auto. Specify —-sparse=always to create a sparse DEST file whenever the SOURCE file contains a long enough sequence of zero bytes. Use —-sparse=never to inhibit creation of sparse files.

When **—reflink**[=always] is specified, perform a lightweight copy, where the data blocks are copied only when modified. If this is not possible the copy fails, or if **—reflink**=auto is specified, fall back to a standard copy. Use **—reflink**=never to ensure a standard copy is performed.

The backup suffix is '~', unless set with **—-suffix** or SIMPLE\_BACKUP\_SUFFIX. The version control method may be selected via the **—-backup** option or through the VERSION\_CONTROL environment variable. Here are the values:

```
none, off
```

never make backups (even if --backup is given)

## numbered, t

make numbered backups

### existing, nil

numbered if numbered backups exist, simple otherwise

## simple, never

always make simple backups

As a special case, cp makes a backup of SOURCE when the force and backup options are given and

SOURCE and DEST are the same name for an existing, regular file.

## **AUTHOR**

Written by Torbjorn Granlund, David MacKenzie, and Jim Meyering.

## **REPORTING BUGS**

GNU coreutils online help: <a href="https://www.gnu.org/software/coreutils/">https://www.gnu.org/software/coreutils/</a>> Report cp translation bugs to <a href="https://translationproject.org/team/">https://translationproject.org/team/</a>>

# **COPYRIGHT**

Copyright © 2018 Free Software Foundation, Inc. License GPLv3+: GNU GPL version 3 or later <a href="https://gnu.org/licenses/gpl.html">https://gnu.org/licenses/gpl.html</a>.

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

## **SEE ALSO**

Full documentation at: <a href="https://www.gnu.org/software/coreutils/cp">https://www.gnu.org/software/coreutils/cp</a> or available locally via: info '(coreutils) cp invocation'