NAME

errno - number of last error

SYNOPSIS

#include <errno.h>

DESCRIPTION

The <errno.h> header file defines the integer variable errno, which is set by system calls and some library functions in the event of an error to indicate what went wrong.

errno

The value in *errno* is significant only when the return value of the call indicated an error (i.e., -1 from most system calls; -1 or NULL from most library functions); a function that succeeds *is* allowed to change *errno*. The value of *errno* is never set to zero by any system call or library function.

For some system calls and library functions (e.g., **getpriority**(2)), -1 is a valid return on success. In such cases, a successful return can be distinguished from an error return by setting *errno* to zero before the call, and then, if the call returns a status that indicates that an error may have occurred, checking to see if *errno* has a nonzero value.

errno is defined by the ISO C standard to be a modifiable lvalue of type *int*, and must not be explicitly declared; *errno* may be a macro. *errno* is thread-local; setting it in one thread does not affect its value in any other thread.

Error numbers and names

Valid error numbers are all positive numbers. The *<errno.h>* header file defines symbolic names for each of the possible error numbers that may appear in *errno*.

All the error names specified by POSIX.1 must have distinct values, with the exception of **EAGAIN** and **EWOULDBLOCK**, which may be the same.

The error numbers that correspond to each symbolic name vary across UNIX systems, and even across different architectures on Linux. Therefore, numeric values are not included as part of the list of error names below. The **perror**(3) and **strerror**(3) functions can be used to convert these names to corresponding textual error messages.

On any particular Linux system, one can obtain a list of all symbolic error names and the corresponding error numbers using the **errno**(1) command (part of the *moreutils* package):

```
$ errno -1
EPERM 1 Operation not permitted
ENOENT 2 No such file or directory
ESRCH 3 No such process
EINTR 4 Interrupted system call
EIO 5 Input/output error
```

The **errno**(1) command can also be used to look up individual error numbers and names, and to search for errors using strings from the error description, as in the following examples:

```
$ errno 2
ENOENT 2 No such file or directory
$ errno ESRCH
ESRCH 3 No such process
$ errno -s permission
EACCES 13 Permission denied
```

List of error names

In the list of the symbolic error names below, various names are marked as follows:

* *POSIX.1-2001*: The name is defined by POSIX.1-2001, and is defined in later POSIX.1 versions, unless otherwise indicated.

- * POSIX.1-2008: The name is defined in POSIX.1-2008, but was not present in earlier POSIX.1 standards.
- * C99: The name is defined by C99. Below is a list of the symbolic error names that are defined on Linux:

E2BIG Argument list too long (POSIX.1-2001).

EACCES Permission denied (POSIX.1-2001).

EADDRINUSE Address already in use (POSIX.1-2001).

EADDRNOTAVAIL

Address not available (POSIX.1-2001).

EAFNOSUPPORT

Address family not supported (POSIX.1-2001).

EAGAIN Resource temporarily unavailable (may be the same value as **EWOULDBLOCK**)

(POSIX.1-2001).

EALREADY Connection already in progress (POSIX.1-2001).

EBADE Invalid exchange.

EBADF Bad file descriptor (POSIX.1-2001).

EBADFD File descriptor in bad state.

EBADMSG Bad message (POSIX.1-2001).

EBADR Invalid request descriptor.

EBADRQC Invalid request code.

EBADSLT Invalid slot.

EBUSY Device or resource busy (POSIX.1-2001).

ECANCELED Operation canceled (POSIX.1-2001).

ECHILD No child processes (POSIX.1-2001).

ECHRNG Channel number out of range.

ECOMM Communication error on send.

ECONNABORTED

Connection aborted (POSIX.1-2001).

ECONNREFUSED

Connection refused (POSIX.1-2001).

ECONNRESET Connection reset (POSIX.1-2001).

EDEADLK Resource deadlock avoided (POSIX.1-2001).

EDEADLOCK Synonym for **EDEADLK**.

EDESTADDRREQ

Destination address required (POSIX.1-2001).

EDOM Mathematics argument out of domain of function (POSIX.1, C99).

EDQUOT Disk quota exceeded (POSIX.1-2001).

EEXIST File exists (POSIX.1-2001).

EFAULT Bad address (POSIX.1-2001).

EFBIG File too large (POSIX.1-2001).

EHOSTDOWN Host is down.

EHOSTUNREACH

Host is unreachable (POSIX.1-2001).

EHWPOISON Memory page has hardware error. **EIDRM** Identifier removed (POSIX.1-2001).

EILSEQ Invalid or incomplete multibyte or wide character (POSIX.1, C99).

The text shown here is the glibc error description; in POSIX.1, this error is described as

"Illegal byte sequence".

EINPROGRESS Operation in progress (POSIX.1-2001).

EINTR Interrupted function call (POSIX.1-2001); see **signal**(7).

EINVAL Invalid argument (POSIX.1-2001).EIO Input/output error (POSIX.1-2001).EISCONN Socket is connected (POSIX.1-2001).

EISDIR Is a directory (POSIX.1-2001).

EISNAM Is a named type file. **EKEYEXPIRED** Key has expired.

EKEYREJECTED

Key was rejected by service.

EKEYREVOKED

Key has been revoked.

EL2HLT Level 2 halted.

EL2NSYNC Level 2 not synchronized.

EL3HLT Level 3 halted.
EL3RST Level 3 reset.

ELIBAD Cannot access a needed shared library.

ELIBBAD Accessing a corrupted shared library.

ELIBMAX Attempting to link in too many shared libraries.

ELIBSCN .lib section in a.out corrupted

ELIBEXEC Cannot exec a shared library directly.

ELNRANGE Link number out of range.

ELOOP Too many levels of symbolic links (POSIX.1-2001).

EMEDIUMTYPE

Wrong medium type.

EMFILE Too many open files (POSIX.1-2001). Commonly caused by exceeding the

RLIMIT_NOFILE resource limit described in **getrlimit**(2).

EMLINK Too many links (POSIX.1-2001).
 EMSGSIZE Message too long (POSIX.1-2001).
 EMULTIHOP Multihop attempted (POSIX.1-2001).

ENAMETOOLONG

Filename too long (POSIX.1-2001).

ENETDOWN Network is down (POSIX.1-2001).

ENETRESET Connection aborted by network (POSIX.1-2001).

ENETUNREACH

Network unreachable (POSIX.1-2001).

ENFILE Too many open files in system (POSIX.1-2001). On Linux, this is probably a result of

encountering the /proc/sys/fs/file-max limit (see **proc**(5)).

ENOANO No anode.

ENOBUFS No buffer space available (POSIX.1 (XSI STREAMS option)).

ENODATA No message is available on the STREAM head read queue (POSIX.1-2001).

ENODEV No such device (POSIX.1-2001).

ENOENT No such file or directory (POSIX.1-2001).

Typically, this error results when a specified pathname does not exist, or one of the components in the directory prefix of a pathname does not exist, or the specified path-

name is a dangling symbolic link.

ENOEXEC Exec format error (POSIX.1-2001).

ENOKEY Required key not available.

ENOLCK No locks available (POSIX.1-2001).

ENOLINK Link has been severed (POSIX.1-2001).

ENOMEDIUM No medium found.

ENOMEM Not enough space/cannot allocate memory (POSIX.1-2001).

ENOMSG No message of the desired type (POSIX.1-2001).

ENONET Machine is not on the network.

ENOPKG Package not installed.

ENOPROTOOPT

Protocol not available (POSIX.1-2001).

ENOSPC No space left on device (POSIX.1-2001).

ENOSR No STREAM resources (POSIX.1 (XSI STREAMS option)).

ENOSTR Not a STREAM (POSIX.1 (XSI STREAMS option)).

ENOSYS Function not implemented (POSIX.1-2001).

ENOTBLK Block device required.

ENOTCONN The socket is not connected (POSIX.1-2001).

ENOTDIR Not a directory (POSIX.1-2001).

ENOTEMPTY Directory not empty (POSIX.1-2001).

ENOTRECOVERABLE

State not recoverable (POSIX.1-2008).

ENOTSOCK Not a socket (POSIX.1-2001).

ENOTSUP Operation not supported (POSIX.1-2001).

ENOTTY Inappropriate I/O control operation (POSIX.1-2001).

ENOTUNIQ Name not unique on network.

ENXIO No such device or address (POSIX.1-2001).

EOPNOTSUPP Operation not supported on socket (POSIX.1-2001).

2019-03-06 4

(ENOTSUP and EOPNOTSUPP have the same value on Linux, but according to

POSIX.1 these error values should be distinct.)

EOVERFLOW Value too large to be stored in data type (POSIX.1-2001).

EOWNERDEAD Owner died (POSIX.1-2008).

EPERM Operation not permitted (POSIX.1-2001).

EPFNOSUPPORT

Protocol family not supported.

EPIPE Broken pipe (POSIX.1-2001).

EPROTO Protocol error (POSIX.1-2001).

EPROTONOSUPPORT

Protocol not supported (POSIX.1-2001).

EPROTOTYPE Protocol wrong type for socket (POSIX.1-2001).

ERANGE Result too large (POSIX.1, C99).

EREMCHG Remote address changed.

EREMOTE Object is remote.

EREMOTEIO Remote I/O error.

ERESTART Interrupted system call should be restarted.

ERFKILL Operation not possible due to RF-kill. **EROFS** Read-only filesystem (POSIX.1-2001).

ESHUTDOWN Cannot send after transport endpoint shutdown.

ESPIPE Invalid seek (POSIX.1-2001).

ESOCKTNOSUPPORT

Socket type not supported.

ESRCH No such process (POSIX.1-2001).

ESTALE Stale file handle (POSIX.1-2001).

This error can occur for NFS and for other filesystems.

ESTRPIPE Streams pipe error.

ETIME Timer expired (POSIX.1 (XSI STREAMS option)).

(POSIX.1 says "STREAM ioctl(2) timeout".)

ETIMEDOUT Connection timed out (POSIX.1-2001).

ETOOMANYREFS

Too many references: cannot splice.

ETXTBSY Text file busy (POSIX.1-2001).

EUCLEAN Structure needs cleaning.

EUNATCH Protocol driver not attached.

EUSERS Too many users.

EWOULDBLOCK

Operation would block (may be same value as **EAGAIN**) (POSIX.1-2001).

EXDEV Improper link (POSIX.1-2001).

EXFULL Exchange full.

2019-03-06 5

NOTES

A common mistake is to do

```
if (somecall() == -1) {
    printf("somecall() failed\n");
    if (errno == ...) { ... }
}
```

where *errno* no longer needs to have the value it had upon return from *somecall*() (i.e., it may have been changed by the **printf**(3)). If the value of *errno* should be preserved across a library call, it must be saved:

```
if (somecall() == -1) {
   int errsv = errno;
   printf("somecall() failed\n");
   if (errsv == ...) { ... }
}
```

On some ancient systems, <errno.h> was not present or did not declare errno, so that it was necessary to declare errno manually (i.e., extern int errno). Do not do this. It long ago ceased to be necessary, and it will cause problems with modern versions of the C library.

SEE ALSO

```
errno(1), err(3), error(3), perror(3), strerror(3)
```

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.