#### **NAME**

GNU Parted – a partition manipulation program

#### **SYNOPSIS**

parted [options] [device [command [options...]...]]

# **DESCRIPTION**

**parted** is a program to manipulate disk partitions. It supports multiple partition table formats, including MS-DOS and GPT. It is useful for creating space for new operating systems, reorganising disk usage, and copying data to new hard disks.

This manual page documents **parted** briefly. Complete documentation is distributed with the package in GNU Info format.

### **OPTIONS**

#### -h, --help

displays a help message

-l, --list lists partition layout on all block devices

### -m, --machine

displays machine parseable output

# -s, --script

never prompts for user intervention

#### -v, --version

displays the version

## -a alignment-type, --align alignment-type

Set alignment for newly created partitions, valid alignment types are:

none Use the minimum alignment allowed by the disk type.

cylinder

Align partitions to cylinders.

#### minimal

Use minimum alignment as given by the disk topology information. This and the opt value will use layout information provided by the disk to align the logical partition table addresses to actual physical blocks on the disks. The min value is the minimum alignment needed to align the partition properly to physical blocks, which avoids performance degradation.

optimal Use optimum alignment as given by the disk topology information. This aligns to a multiple of the physical block size in a way that guarantees optimal performance.

## **COMMANDS**

# [device]

The block device to be used. When none is given, parted will use the first block device it finds.

# [command [options]]

Specifies the command to be executed. If no command is given, **parted** will present a command prompt. Possible commands are:

# help [command]

Print general help, or help on command if specified.

# align-check type partition

Check if *partition* satisfies the alignment constraint of *type*. *type* must be "minimal" or "optimal".

# mklabel label-type

Create a new disklabel (partition table) of *label-type*. *label-type* should be one of "aix", "amiga", "bsd", "dvh", "gpt", "loop", "mac", "msdos", "pc98", or "sun".

## mkpart part-type [fs-type] start end

Make a *part-type* partition for filesystem *fs-type* (if specified), beginning at *start* and ending at *end* (by default in megabytes). *part-type* should be one of "primary", "logical", or "extended".

# name partition name

Set the name of *partition* to *name*. This option works only on Mac, PC98, and GPT disklabels. The name can be placed in quotes, if necessary.

**print** Display the partition table.

quit Exit from parted.

#### rescue start end

Rescue a lost partition that was located somewhere between *start* and *end*. If a partition is found, **parted** will ask if you want to create an entry for it in the partition table.

### resizepart partition end

Change the *end* position of *partition*. Note that this does not modify any filesystem present in the partition.

#### rm partition

Delete partition.

#### select device

Choose *device* as the current device to edit. *device* should usually be a Linux hard disk device, but it can be a partition, software raid device, or an LVM logical volume if necessary.

# set partition flag state

Change the state of the *flag* on *partition* to *state*. Supported flags are: "boot", "root", "swap", "hidden", "raid", "lvm", "lba", "legacy\_boot", "irst", "esp" and "palo". *state* should be either "on" or "off".

#### unit unit

Set *unit* as the unit to use when displaying locations and sizes, and for interpreting those given by the user when not suffixed with an explicit unit. *unit* can be one of "s" (sectors), "B" (bytes), "kB", "MB", "MB", "GB", "GiB", "TB", "TiB", "%" (percentage of device size), "cyl" (cylinders), "chs" (cylinders, heads, sectors), or "compact" (megabytes for input, and a human-friendly form for output).

# toggle partition flag

Toggle the state of flag on partition.

#### version

Display version information and a copyright message.

## **REPORTING BUGS**

Report bugs to <bug-parted@gnu.org>

# **SEE ALSO**

**fdisk**(8), **mkfs**(8), The *parted* program is fully documented in the **info(1)** format *GNU partitioning software* manual which is distributed with the parted-doc Debian package.

#### **AUTHOR**

This manual page was written by Timshel Knoll <timshel@debian.org>, for the Debian GNU/Linux system (but may be used by others).