### **NAME**

lpoptions - display or set printer options and defaults

### **SYNOPSIS**

```
lpoptions [ -E ] [ -h server[:port] ] -d destination[/instance] [ -l ]
lpoptions [ -E ] [ -h server[:port] ] [ -p destination[/instance] ] -o option[=value] ...
lpoptions [ -E ] [ -h server[:port] ] [ -p destination[/instance] ] -r option
lpoptions [ -E ] [ -h server[:port] ] -x destination[/instance]
```

### DESCRIPTION

**lpoptions** displays or sets printer options and defaults. If no printer is specified using the -p option, the default printer is used as described in lp(1).

If no -l, -o, or -r options are specified, the current options are reported on the standard output.

Options set with the **lpoptions** command are used by the lp(1) and lpr(1) commands when submitting jobs.

When run by the root user, **lpoptions** gets and sets default options and instances for all users in the /etc/cups/lpoptions file. Otherwise, the per-user defaults are managed in the ~/.cups/lpoptions file.

### **OPTIONS**

**lpoptions** supports the following options:

- **-E** Enables encryption when communicating with the CUPS server.
- **-d** *destination*[/instance]

Sets the user default printer to *destination*. If *instance* is supplied then that particular instance is used. This option overrides the system default printer for the current user.

-h server[:port]

Uses an alternate server.

- -l Lists the printer specific options and their current settings.
- **-o** option[=value]

Specifies a new option for the named destination.

**-p** *destination*[/*instance*]

Sets the destination and instance, if specified, for any options that follow. If the named instance does not exist then it is created. Destinations can only be created using the **lpadmin**(8) program.

-r ontion

Removes the specified option from the named destination.

**-x** *destination*[/*instance*]

Removes the options for the named destination and instance, if specified. If the named instance does not exist then this does nothing. Destinations can only be removed using the **lpadmin**(8) command.

## **FILES**

~/.cups/lpoptions — user defaults and instances created by non-root users. /etc/cups/lpoptions — system-wide defaults and instances created by the root user.

# **CONFORMING TO**

The **lpoptions** command is unique to CUPS.

### **SEE ALSO**

```
cancel(1), lp(1), lpadmin(8), lpr(1), lprm(1), CUPS Online Help (http://localhost:631/help)
```

# **COPYRIGHT**

Copyright © 2007-2018 by Apple Inc.