#### **NAME**

```
isfdtype - test file type of a file descriptor
```

#### **SYNOPSIS**

```
#include <sys/stat.h>
    #include <sys/socket.h>
    int isfdtype(int fd, int fdtype);
Feature Test Macro Requirements for glibc (see feature_test_macros(7)):
    isfdtype():
         Since glibc 2.20:
```

```
_DEFAULT_SOURCE
Before glibc 2.20:
   _BSD_SOURCE || _SVID_SOURCE
```

#### DESCRIPTION

The **isfdtype**() function tests whether the file descriptor fd refers to a file of type fdtype. The fdtype argument specifies one of the S\_IF\* constants defined in <sys/stat.h> and documented in stat(2) (e.g., S\_IFREG).

# **RETURN VALUE**

The **isfdtype**() function returns 1 if the file descriptor fd is of type fdtype and 0 if it is not. On error, -1 is returned and errno is set to indicate the cause.

#### **ERRORS**

The **isfdtype**() function can fail with any of the same errors as **fstat**(3).

# **CONFORMING TO**

The isfdtype() function is not specified in any standard, but did appear in the draft POSIX.1g standard. It is present on OpenBSD and Tru64 UNIX (where the required header file in both cases is just <sys/stat.h>, as shown in the POSIX.1g draft), and possibly other systems.

## **NOTES**

Portable applications should use **fstat**(3) instead.

# **SEE ALSO**

fstat(3)

### **COLOPHON**

This page is part of release 5.02 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be https://www.kernel.org/doc/man-pages/.