NAME

pthread_mutex_consistent - make a robust mutex consistent

SYNOPSIS

#include <pthread.h>

int pthread mutex consistent(pthread mutex t *mutex);

Compile and link with -pthread.

Feature Test Macro Requirements for glibc (see **feature test macros**(7)):

```
pthread mutex consistent():
```

_POSIX_C_SOURCE >= 200809L

DESCRIPTION

This function makes a robust mutex consistent if it is in an inconsistent state. A mutex can be left in an inconsistent state if its owner terminates while holding the mutex, in which case the next owner who acquires the mutex will succeed and be notified by a return value of **EOWNERDEAD** from a call to **pthread_mutex_lock**().

RETURN VALUE

On success, *pthread_mutex_consistent()* returns 0. Otherwise, it returns a positive error number to indicate the cause of the error.

ERRORS

EINVAL

The mutex is either not robust or is not in an inconsistent state.

VERSIONS

pthread_mutex_consistent() was added to glibc in version 2.12.

CONFORMING TO

POSIX.1-2008.

NOTES

pthread_mutex_consistent() simply informs the implementation that the state (shared data) guarded by the mutex has been restored to a consistent state and that normal operations can now be performed with the mutex. It is the application's responsibility to ensure that the shared data has been restored to a consistent state before calling **pthread_mutex_consistent**().

Before the addition of **pthread_mutex_consistent**() to POSIX, glibc defined the following equivalent non-standard function if **_GNU_SOURCE** was defined:

int pthread_mutex_consistent(const pthread_mutex_t *mutex);

This GNU-specific API, which first appeared in glibc 2.4, is nowadays obsolete and should not be used in new programs.

EXAMPLE

See pthread_mutexattr_setrobust(3).

SEE ALSO

```
\label{lem:pthread_mutexattr_init} pthread\_mutexattr\_init(3), pthread\_mutexattr\_setrobust(3), pthread\_mutexattr\_getrobust(3), pthreads(7)
```

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.