### **NAME**

gendict - Compiles word list into ICU string trie dictionary

### **SYNOPSIS**

```
gendict [ --uchars | --bytes --transform transform ] [ -h, -?, --help ] [ -V, --version ] [ -c, --copyright ] [ -v, --verbose ] [ -i, --icudatadir directory ] input-file output-file
```

# **DESCRIPTION**

**gendict** reads the word list from *dictionary-file* and creates a string trie dictionary file. Normally this data file has the .dict extension.

Words begin at the beginning of a line and are terminated by the first whitespace. Lines that begin with whitespace are ignored.

## **OPTIONS**

### -h, -?, --help

Print help about usage and exit.

### -V, --version

Print the version of **gendict** and exit.

# -c, --copyright

Embeds the standard ICU copyright into the *output-file*.

### -v, --verbose

Display extra informative messages during execution.

### -i, --icudatadir directory

Look for any necessary ICU data files in *directory*. For example, the file **pnames.icu** must be located when ICU's data is not built as a shared library. The default ICU data directory is specified by the environment variable ICU\_DATA. Most configurations of ICU do not require this argument.

### --uchars

Set the output trie type to UChar. Mutually exclusive with --bytes.

### --bytes

Set the output trie type to Bytes. Mutually exclusive with --uchars.

## --transform

Set the transform type. Should only be specified with **--bytes.** Currently supported transforms are: **offset-<hex-number>**, which specifies an offset to subtract from all input characters. It should be noted that the offset transform also maps U+200D to 0xFF and U+200C to 0xFE, in order to offer compatibility to languages that require these characters. A transform must be specified for a bytes trie, and when applied to the non-value characters in the *input-file* must produce output between 0x00 and 0xFF.

## input-file

The source file to read.

## output-file

The file to write the output dictionary to.

### **CAVEATS**

The *input-file* is assumed to be encoded in UTF-8. The integers in the *input-file* that are used as values must be made up of ASCII digits. They may be specified either in hex, by using a 0x prefix, or in decimal. Either **--bytes** or **--uchars** must be specified.

### **ENVIRONMENT**

## ICU\_DATA

Specifies the directory containing ICU data. Defaults to \${prefix}/share/icu/63.2/. Some tools in ICU depend on the presence of the trailing slash. It is thus important to make sure that it is present if ICU\_DATA is set.

# **AUTHORS**

Maxime Serrano

# **VERSION**

1.0

# **COPYRIGHT**

Copyright (C) 2012 International Business Machines Corporation and others

# **SEE ALSO**

http://www.icu-project.org/userguide/boundaryAnalysis.html