


MODULE CODE & TITLE: IS80662 – SYSTEMS & SERVICES MANAGEMENT

LAB ACTIVITY: PART 1

NETWORK TOPOLOGY



CONFIGURATIONS

R1 Configurations

Router>en

Router#conf ter

Router(config)#hostname RT1

Interfaces & Inter-VLAN routing configurations

RT1(config)#int g0/0

RT1(config-if)#no shut

RT1(config-if)#int g0/0.10

RT1(config-subif)#encapsulation dot1q 10

RT1(config-subif)#ip address 10.10.0.1 255.255.255.192

RT1(config-subif)#int g0/0.20

RT1(config-subif)#encapsulation dot1q 20

RT1(config-subif)#ip address 10.10.0.65 255.255.255.224

RT1(config-subif)#int se0/0/0

RT1(config-if)#ip address 10.10.0.241 255.255.255.252

RT1(config-if)#no shut

RT1(config-if)#exit

DHCP Configuration

RT1(config)#ip dhcp excluded-address 10.10.0.1 10.10.0.5

RT1(config)#ip dhcp pool LAN-Guests

RT1(dhcp-config)#network 10.10.0.0 255.255.255.192

RT1(dhcp-config)#def

RT1(dhcp-config)#default-router 10.10.0.1

RT1(dhcp-config)#dns-server 10.10.0.230

RT1(dhcp-config)#ip dhcp excluded-address 10.10.0.65 10.10.0.70

RT1(config)#ip dhcp pool LAN-IT

RT1(dhcp-config)#network 10.10.0.64 255.255.255.224

RT1(dhcp-config)#default-router 10.10.0.65

RT1(dhcp-config)#dns-server 10.10.0.230

RT1(dhcp-config)#end

Dynamic Routing Protocol configurations

```
RT1(config)#router ospf 5
RT1(config-router)#network 10.10.0.0 0.0.0.63 area 0
RT1(config-router)#network 10.10.0.64 0.0.0.31 area 0
RT1(config-router)#network 10.10.0.240 0.0.0.3 area 0
RT1(config-router)#end
RT1#
```

S1 configurations

```
Switch>en
Switch#conf ter
Switch(config)#hostname S1
S1(config)#vlan 10
S1(config-vlan)#name Guests
S1(config-vlan)#vlan 20
S1(config-vlan)#name IT
S1(config-vlan)#exit
S1(config)#int range fa0/5-15
S1(config-if-range)#switchport mode access
S1(config-if-range)#switchport access vlan 10
S1(config-if-range)#int range fa0/16-24
S1(config-if-range)#switchport mode access
S1(config-if-range)#switchport access vlan 20
S1(config-if-range)#int range fa0/1-4
S1(config-if-range)#switchport mode trunk
S1(config-if-range)#switchport trunk native vlan 1
S1(config-if-range)#end
S1#
```

ASSIGNMENT

Reference to the above configurations, provide configurations on your devices (make 2 copies and submit one). Submit it in **20 minutes** and immediately start your devices configuration.